

INSIDE MACINTOSH

Sound



Addison-Wesley Publishing Company

Reading, Massachusetts Menlo Park, California New York
Don Mills, Ontario Wokingham, England Amsterdam Bonn
Sydney Singapore Tokyo Madrid San Juan
Paris Seoul Milan Mexico City Taipei

Apple Computer, Inc.
© 1994 Apple Computer, Inc.
All rights reserved.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, mechanical, electronic, photocopying, recording, or otherwise, without prior written permission of Apple Computer, Inc. Printed in the United States of America.

No licenses, express or implied, are granted with respect to any of the technology described in this book. Apple retains all intellectual property rights associated with the technology described in this book. This book is intended to assist application developers to develop applications only for Apple Macintosh computers.

Every effort has been made to ensure that the information in this manual is accurate. Apple is not responsible for printing or clerical errors.

Apple Computer, Inc.
20525 Mariani Avenue
Cupertino, CA 95014
408-996-1010

Apple, the Apple logo, APDA, HyperCard, LaserWriter, Macintosh, Macintosh Quadra, MPW, and PowerBook are trademarks of Apple Computer, Inc., registered in the United States and other countries.

AppleDesign, AudioVision, Finder, MacinTalk, QuickDraw, and QuickTime are trademarks of Apple Computer, Inc.

Adobe Illustrator, Adobe Photoshop, and PostScript are trademarks of Adobe Systems Incorporated, which may be registered in certain jurisdictions.

Classic[®] is a registered trademark licensed to Apple Computer, Inc.

FrameMaker is a registered trademark of Frame Technology Corporation.

Helvetica and Palatino are registered trademarks of Linotype Company.

Internet is a trademark of Digital Equipment Corporation.

ITC Zapf Dingbats is a registered trademark of International Typeface Corporation.

NuBus[™] is a trademark of Texas Instruments.

Optrotech is a trademark of Orbotech Corporation.

Sony[™] is a trademark of Sony Corporation, registered in the U.S. and other countries.

Simultaneously published in the United States and Canada.

authorized to make any modification, extension, or addition to this warranty.

Some states do not allow the exclusion or limitation of implied warranties or liability for incidental or consequential damages, so the above limitation or exclusion may not apply to you. This warranty gives you specific legal rights, and you may also have other rights which vary from state to state.

LIMITED WARRANTY ON MEDIA AND REPLACEMENT

ALL IMPLIED WARRANTIES ON THIS MANUAL, INCLUDING IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, ARE LIMITED IN DURATION TO NINETY (90) DAYS FROM THE DATE OF THE ORIGINAL RETAIL PURCHASE OF THIS PRODUCT.

Even though Apple has reviewed this manual, APPLE MAKES NO WARRANTY OR REPRESENTATION, EITHER EXPRESS OR IMPLIED, WITH RESPECT TO THIS MANUAL, ITS QUALITY, ACCURACY, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. AS A RESULT, THIS MANUAL IS SOLD "AS IS," AND YOU, THE PURCHASER, ARE ASSUMING THE ENTIRE RISK AS TO ITS QUALITY AND ACCURACY.

IN NO EVENT WILL APPLE BE LIABLE FOR DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES RESULTING FROM ANY DEFECT OR INACCURACY IN THIS MANUAL, even if advised of the possibility of such damages.

THE WARRANTY AND REMEDIES SET FORTH ABOVE ARE EXCLUSIVE AND IN LIEU OF ALL OTHERS, ORAL OR WRITTEN, EXPRESS OR IMPLIED. No Apple dealer, agent, or employee is

ISBN 0-201-62272-6
1 2 3 4 5 6 7 8 9-CRW-9897969594
First Printing, May 1994



The paper used in this book meets the EPA standards for recycled fiber.

Library of Congress Cataloging-in-Publication Data

Inside Macintosh. Sound / [Apple Computer, Inc.]

p. cm.

Includes index.

ISBN 0-201-62272-6

1. Macintosh (Computer) 2. Computer sound processing. I. Apple

Computer, Inc.

QA76.8.M3I53 1994

006.5--dc20

94-16209

CIP

Contents

	Figures, Tables, and Listings	xi
Preface	About This Book	xv
	Format of a Typical Chapter	xvi
	Conventions Used in This Book	xvi
	Special Fonts	xvi
	Types of Notes	xvii
	Assembly-Language Information	xvii
	Development Environment	xviii
	For More Information	xix
Chapter 1	Introduction to Sound on the Macintosh	1-1
	About Sound on Macintosh Computers	1-4
	Sound Capabilities	1-4
	Sound Production	1-9
	Sound Recording	1-15
	Sound Resources	1-17
	Sound Files	1-18
	Speech Generation	1-20
	The User Interface for Sound	1-23
	Using Sound on Macintosh Computers	1-24
	Producing an Alert Sound	1-24
	Playing a Sound Resource	1-25
	Playing a Sound File	1-26
	Checking For Sound-Recording Equipment	1-27
	Recording a Sound Resource	1-28
	Recording a Sound File	1-31
	Checking For Speech Capabilities	1-31
	Generating Speech From a String	1-32
	Sound Reference	1-34
	Routines	1-34
	Playing Sounds	1-34
	Recording Sounds	1-38
	Generating and Stopping Speech	1-41
	Summary of Sound	1-44
	Pascal Summary	1-44
	Constants	1-44
	Routines	1-44
	C Summary	1-45

Constants	1-45
Routines	1-46
Result Codes	1-47

Chapter 2 Sound Manager 2-1

About the Sound Manager	2-6
Sound Data	2-7
Square-Wave Data	2-7
Wave-Table Data	2-8
Sampled-Sound Data	2-9
Sound Commands	2-11
Sound Channels	2-13
Sound Compression and Expansion	2-14
Using the Sound Manager	2-17
Managing Sound Channels	2-19
Allocating Sound Channels	2-20
Initializing Sound Channels	2-22
Releasing Sound Channels	2-24
Manipulating a Sound That Is Playing	2-25
Stopping Sound Channels	2-28
Pausing and Restarting Sound Channels	2-29
Synchronizing Sound Channels	2-30
Managing Sound Volumes	2-31
Obtaining Sound-Related Information	2-32
Obtaining Information About Available Sound Features	2-33
Obtaining Version Information	2-34
Testing for Multichannel Sound and Play-From-Disk Capabilities	2-35
Obtaining Information About a Single Sound Channel	2-37
Obtaining Information About All Sound Channels	2-39
Determining and Changing the Status of the System Alert Sound	2-40
Playing Notes	2-41
Installing Voices Into Channels	2-43
Looping a Sound Indefinitely	2-45
Playing Sounds Asynchronously	2-46
Using Callback Procedures	2-47
Synchronizing Sound With Other Actions	2-51
Managing an Asynchronous Play From Disk	2-52
Playing Selections	2-53
Managing Multiple Sound Channels	2-53
Parsing Sound Resources and Sound Files	2-56
Obtaining a Pointer to a Sound Header	2-57
Playing Sounds Using Low-Level Routines	2-61
Finding a Chunk in a Sound File	2-62
Compressing and Expanding Sounds	2-66
Using Double Buffers	2-68

Setting Up Double Buffers	2-70
Writing a Doubleback Procedure	2-72
Sound Storage Formats	2-73
Sound Resources	2-74
The Format 1 Sound Resource	2-75
The Format 2 Sound Resource	2-80
Sound Files	2-81
Chunk Organization and Data Types	2-82
The Form Chunk	2-83
The Format Version Chunk	2-84
The Common Chunk	2-85
The Sound Data Chunk	2-87
Format of Entire Sound Files	2-87
Sound Manager Reference	2-89
Constants	2-89
Gestalt Selector and Response Bits	2-90
Channel Initialization Parameters	2-91
Sound Command Numbers	2-92
Chunk IDs	2-98
Data Structures	2-99
Sound Command Records	2-99
Audio Selection Records	2-100
Sound Channel Status Records	2-101
Sound Manager Status Records	2-102
Sound Channel Records	2-103
Sound Header Records	2-104
Extended Sound Header Records	2-106
Compressed Sound Header Records	2-108
Sound Double Buffer Header Records	2-111
Sound Double Buffer Records	2-112
Chunk Headers	2-113
Form Chunks	2-113
Format Version Chunks	2-114
Common Chunks	2-115
Extended Common Chunks	2-115
Sound Data Chunks	2-117
Version Records	2-118
Leftover Blocks	2-119
State Blocks	2-119
Sound Manager Routines	2-119
Playing Sound Resources	2-120
Playing From Disk	2-123
Allocating and Releasing Sound Channels	2-127
Sending Commands to a Sound Channel	2-130
Obtaining Information	2-132
Controlling Volume Levels	2-139
Compressing and Expanding Audio Data	2-142

Managing Double Buffers	2-147
Performing Unsigned Fixed-Point Arithmetic	2-148
Linking Modifiers to Sound Channels	2-149
Application-Defined Routines	2-151
Completion Routines	2-151
Callback Procedures	2-152
Doubleback Procedures	2-153
Resources	2-154
The Sound Resource	2-154
Summary of the Sound Manager	2-157
Pascal Summary	2-157
Constants	2-157
Data Types	2-161
Sound Manager Routines	2-168
Application-Defined Routines	2-170
C Summary	2-170
Constants	2-170
Data Types	2-175
Sound Manager Routines	2-182
Application-Defined Routines	2-184
Assembly-Language Summary	2-184
Data Structures	2-184
Trap Macros	2-188
Result Codes	2-188

Chapter 3

Sound Input Manager 3-1

About the Sound Input Manager	3-3
Sound Recording Without the Standard Interface	3-4
Interaction With Sound Input Devices	3-4
Sound Input Device Drivers	3-5
Using the Sound Input Manager	3-5
Recording Sounds Directly From a Device	3-6
Defining a Sound Input Completion Routine	3-9
Defining a Sound Input Interrupt Routine	3-10
Getting and Setting Sound Input Device Information	3-10
Writing a Sound Input Device Driver	3-13
Responding to Status and Control Requests	3-13
Responding to Read Requests	3-15
Supporting Stereo Recording	3-16
Supporting Continuous Recording	3-17
Sound Input Manager Reference	3-17
Constants	3-17
Gestalt Selector and Response Bits	3-17
Sound Input Device Information Selectors	3-18
Data Structures	3-26

Sound Input Parameter Blocks	3-26	
Sound Input Manager Routines	3-27	
Recording Sounds	3-28	
Opening and Closing Sound Input Devices	3-31	
Recording Sounds Directly From Sound Input Devices	3-33	
Manipulating Device Settings	3-41	
Constructing Sound Resource and File Headers	3-44	
Registering Sound Input Devices	3-48	
Converting Between Milliseconds and Bytes	3-51	
Obtaining Information	3-53	
Application-Defined Routines	3-53	
Sound Input Completion Routines	3-54	
Sound Input Interrupt Routines	3-55	
Summary of the Sound Input Manager	3-57	
Pascal Summary	3-57	
Constants	3-57	
Data Types	3-58	
Sound Input Manager Routines	3-59	
Application-Defined Routines	3-60	
C Summary	3-61	
Constants	3-61	
Data Types	3-62	
Sound Input Manager Routines	3-63	
Application-Defined Routines	3-65	
Assembly-Language Summary	3-65	
Data Structures	3-65	
Trap Macros	3-66	
Result Codes	3-66	

Chapter 4

Speech Manager 4-1

About the Speech Manager	4-4	
Voices	4-5	
Speech Attributes	4-6	
Speech Channels	4-9	
Callback Routines	4-10	
Using the Speech Manager	4-11	
Checking for Speech Manager Capabilities	4-12	
Creating, Using, and Disposing of a Speech Channel	4-13	
Working With Different Voices	4-14	
Adjusting Speech Attributes	4-16	
Pausing Speech	4-18	
Implementing Callback Procedures	4-19	
Writing Embedded Speech Commands	4-23	
Embedded Command Delimiters	4-23	
Syntax of Embedded Speech Commands	4-24	

Examples of Embedded Speech Commands	4-30
Phonemic Representation of Speech	4-32
Phonemic Symbols	4-33
Prosodic Control Symbols	4-34
Including Pronunciation Dictionaries	4-36
Speech Manager Reference	4-39
Constants	4-39
Speech Information Selectors	4-39
Data Structures	4-45
Voice Specification Records	4-46
Voice Description Records	4-47
Voice File Information Records	4-48
Speech Status Information Records	4-48
Speech Error Information Records	4-49
Speech Version Information Records	4-50
Phoneme Information Records	4-52
Phoneme Descriptor Records	4-53
Speech Extension Data Records	4-53
Delimiter Information Records	4-54
Speech Manager Routines	4-54
Starting, Stopping, and Pausing Speech	4-55
Obtaining Information About Voices	4-63
Managing Speech Channels	4-69
Obtaining Information About Speech	4-71
Changing Speech Attributes	4-73
Converting Text To Phonemes	4-79
Installing a Pronunciation Dictionary	4-80
Application-Defined Routines	4-82
Text-Done Callback Procedure	4-82
Speech-Done Callback Procedure	4-84
Synchronization Callback Procedure	4-85
Error Callback Procedure	4-86
Phoneme Callback Procedure	4-87
Word Callback Procedure	4-88
Resources	4-89
The Pronunciation Dictionary Resource	4-89
Summary of the Speech Manager	4-94
Pascal Summary	4-94
Constants	4-94
Data Structures	4-95
Speech Manager Routines	4-98
Application-Defined Routines	4-100
C Summary	4-100
Constants	4-100
Data Types	4-102
Speech Manager Routines	4-105
Application-Defined Routines	4-106

Assembly-Language Information	4-107
Data Structures	4-107
Trap Macros	4-109
Result Codes	4-110

Chapter 5	Sound Components	5-1
-----------	-------------------------	-----

About Sound Components	5-4
Sound Component Chains	5-4
The Apple Mixer	5-6
The Data Stream	5-7
Writing a Sound Component	5-8
Creating a Sound Component	5-8
Specifying Sound Component Capabilities	5-11
Dispatching to Sound Component-Defined Routines	5-12
Registering and Opening a Sound Component	5-16
Finding and Changing Component Capabilities	5-18
Sound Components Reference	5-22
Constants	5-22
Sound Component Information Selectors	5-22
Audio Data Types	5-26
Sound Component Features Flags	5-26
Action Flags	5-27
Data Format Flags	5-28
Data Structures	5-29
Sound Component Data Records	5-29
Sound Parameter Blocks	5-30
Sound Information Lists	5-31
Compression Information Records	5-32
Sound Manager Utilities	5-33
Opening and Closing the Apple Mixer Component	5-33
Saving and Restoring Sound Component Preferences	5-35
Sound Component-Defined Routines	5-36
Managing Sound Components	5-37
Creating and Removing Audio Sources	5-42
Getting and Setting Sound Component Information	5-44
Managing Source Data	5-46
Summary of Sound Components	5-50
C Summary	5-50
Constants	5-50
Data Types	5-53
Sound Manager Utilities	5-54
Sound Component-Defined Routines	5-55
Assembly-Language Summary	5-56
Data Structures	5-56

About Audio Components	6-3
Writing an Audio Component	6-5
Creating an Audio Component	6-5
Dispatching to Audio Component-Defined Routines	6-7
Audio Components Reference	6-8
Data Structures	6-8
Audio Information Records	6-9
Audio Component-Defined Routines	6-9
Getting and Setting Volumes	6-10
Managing the Mute State	6-11
Resetting Audio Components	6-13
Getting Audio Component Information	6-13
Summary of Audio Components	6-15
C Summary	6-15
Constants	6-15
Data Types	6-16
Audio Component-Defined Routines	6-16
Assembly-Language Summary	6-17
Data Structures	6-17

Figures, Tables, and Listings

Chapter 1

Introduction to Sound on the Macintosh 1-1

Figure 1-1	Basic sound capabilities on Macintosh computers	1-4
Figure 1-2	Enhanced sound capabilities on Macintosh computers	1-6
Figure 1-3	High quality sound capabilities on Macintosh computers	1-7
Figure 1-4	A sound component chain	1-8
Figure 1-5	A sound component chain with a DSP board	1-9
Figure 1-6	The Sound Out control panel	1-10
Figure 1-7	The relation of the Sound Manager to the audio hardware	1-11
Figure 1-8	Bypassing the command queue	1-13
Figure 1-9	Mixing multiple channels of sampled sound	1-14
Figure 1-10	The Sound In control panel	1-15
Figure 1-11	The Alert Sounds control panel	1-16
Figure 1-12	The sound recording dialog box	1-17
Table 1-1	AIFF and AIFF-C capabilities	1-19
Figure 1-13	The speech generation process	1-21
Figure 1-14	The Speech Manager and multiple voices	1-21
Figure 1-15	An icon for a Finder sound	1-23
Figure 1-16	A sound in the Scrapbook	1-24
Listing 1-1	Playing a sound resource with <code>SndPlay</code>	1-25
Listing 1-2	Playing a sound file with <code>SndStartFilePlay</code>	1-26
Listing 1-3	Determining whether sound recording equipment is available	1-27
Listing 1-4	Recording through the sound recording dialog box	1-28
Listing 1-5	Recording a sound resource	1-29
Listing 1-6	Recording a sound file	1-31
Listing 1-7	Checking for speech generation capabilities	1-31
Listing 1-8	Using <code>SpeakString</code> to generate speech from a string	1-32
Listing 1-9	Generating speech synchronously	1-33
Listing 1-10	Stopping speech generated by <code>SpeakString</code>	1-34

Chapter 2

Sound Manager 2-1

Figure 2-1	The position of the Sound Manager	2-6
Figure 2-2	A graph of a wave table	2-9
Figure 2-3	Interleaving stereo sample points	2-11
Table 2-1	Sample rates	2-16
Listing 2-1	Creating a sound channel	2-20
Listing 2-2	Reinitializing a sound channel	2-24
Listing 2-3	Disposing of memory associated with a sound channel	2-25
Listing 2-4	Halving the frequency of a sampled sound	2-26
Listing 2-5	Changing the amplitude of a sound channel	2-27
Listing 2-6	Getting the amplitude of a sound in progress	2-28
Listing 2-7	Adding a channel to a group of channels to be synchronized	2-30

Listing 2-8	Setting left and right volumes	2-32
Listing 2-9	Determining if stereo capability is available	2-34
Listing 2-10	Determining if the enhanced Sound Manager is present	2-35
Listing 2-11	Testing for multichannel play capability	2-36
Listing 2-12	Testing for play-from-disk capability	2-37
Listing 2-13	Determining whether a sound channel is paused	2-39
Listing 2-14	Determining the number of allocated sound channels	2-40
Listing 2-15	Using the <code>freqDurationCmd</code> command	2-42
Table 2-2	Frequencies expressed as MIDI note values	2-43
Listing 2-16	Installing a sampled sound as a voice in a channel	2-44
Listing 2-17	Looping an entire sampled sound	2-45
Listing 2-18	Issuing a callback command	2-48
Listing 2-19	Defining a callback procedure	2-48
Listing 2-20	Checking whether a callback procedure has executed	2-49
Listing 2-21	Stopping a sound that is playing asynchronously	2-50
Listing 2-22	Starting an asynchronous sound play	2-50
Listing 2-23	Defining a completion routine	2-52
Listing 2-24	Defining a data structure to track many sound channels	2-54
Listing 2-25	Marking a channel for disposal	2-55
Listing 2-26	Disposing of channels that have been marked for disposal	2-55
Listing 2-27	Playing a sound resource	2-57
Listing 2-28	Obtaining the offset in bytes to a sound header	2-58
Listing 2-29	Converting an offset to a sound header into a pointer to a sound header	2-60
Listing 2-30	Playing a sound using the <code>bufferCmd</code> command	2-62
Listing 2-31	Finding a chunk in a sound file	2-63
Listing 2-32	Loading a chunk from a sound file	2-65
Listing 2-33	Compressing audio data	2-67
Listing 2-34	Setting up double buffers	2-70
Listing 2-35	Defining a doubleback procedure	2-73
Figure 2-4	The structure of 'snd' resources	2-74
Figure 2-5	The location of the data offset bit	2-75
Listing 2-36	A format 1 'snd' resource	2-76
Listing 2-37	A format 1 'snd' resource containing sampled-sound data	2-77
Listing 2-38	An 'snd' resource containing compressed sound data	2-78
Listing 2-39	A resource specification	2-79
Listing 2-40	A resource specification for the Simple Beep	2-79
Listing 2-41	A format 2 'snd' resource	2-81
Figure 2-6	The general structure of a chunk	2-83
Figure 2-7	A sample AIFF-C file	2-88
Figure 2-8	The 'snd' resource type	2-155
Figure 2-9	The sound resource header	2-156

Chapter 3

Sound Input Manager 3-1

Listing 3-1	Recording directly from a sound input device	3-7
Listing 3-2	Determining the name of a sound input device	3-12
Listing 3-3	Determining some sound input device settings	3-12
Figure 3-1	An example of the <code>csParam</code> field for a Status request	3-14
Figure 3-2	An example of the <code>csParam</code> field for a Control request	3-14
Table 3-1	The sampled sound header format used by <code>SetupSndHeader</code>	3-45

Chapter 4

Speech Manager 4-1

Figure 4-1	The speech generation process	4-4
Figure 4-2	The Speech Manager and multiple voices	4-5
Figure 4-3	MIDI note values and corresponding piano keys	4-7
Figure 4-4	An example of pitch range for a voice	4-8
Listing 4-1	Checking for speech generation capabilities	4-12
Listing 4-2	Speaking text with a speech channel	4-13
Listing 4-3	Getting a description of a voice	4-15
Listing 4-4	Changing the speech rate and pitch	4-16
Listing 4-5	Pausing and continuing speech production	4-18
Listing 4-6	Setting up a speech channel for callbacks	4-21
Listing 4-7	Installing a word callback procedure	4-21
Listing 4-8	A typical word callback procedure	4-22
Table 4-1	The embedded command syntax structure	4-25
Table 4-2	Embedded speech commands	4-26
Table 4-3	American English phoneme symbols	4-33
Table 4-4	Prosodic control symbols	4-34
Table 4-5	Effect of punctuation marks on English-language synthesizers	4-35
Listing 4-9	Installing a pronunciation dictionary resource into a speech channel	4-37
Listing 4-10	A sample pronunciation dictionary resource	4-38
Figure 4-5	Format of a pronunciation dictionary resource	4-90
Figure 4-6	Format of a dictionary entry in a dictionary resource	4-92
Figure 4-7	Format of a dictionary entry field	4-93

Chapter 5

Sound Components 5-1

Figure 5-1	The component-based sound architecture	5-5
Figure 5-2	A component chain for audio hardware that can convert sample rates	5-5
Figure 5-3	Mixing multiple channels of sound	5-6
Figure 5-4	A sound output device component that can mix sound channels	5-7
Listing 5-1	Rez input for a component resource	5-11
Listing 5-2	Handling Component Manager selectors	5-14
Listing 5-3	Finding the address of a component-defined routine	5-14
Listing 5-4	Initializing an output device	5-17
Listing 5-5	Getting sound component information	5-19

Figure 6-1 The Apple AudioVision 14 Display 6-4

Figure 6-2 The Volumes control panel for the Apple AudioVision 14 Display 6-4

About This Book

This book, *Inside Macintosh: Sound*, describes the parts of the Macintosh system software that allow you to manage sounds. It describes the services provided by the three principal sound-related system software managers (the Sound Manager, the Sound Input Manager, and the Speech Manager) and shows in detail how your application can record and play back sounds, compress and expand audio data, convert text to speech, and perform other similar operations.

If you are not yet experienced with playing or recording sounds on Macintosh computers, you should begin with the chapter “Introduction to Sound on the Macintosh.” That chapter describes the services provided by the system software and shows how to use the most basic sound-related capabilities of Macintosh computers. It provides complete source code examples illustrating how to record sounds into resources and files, how to play sounds stored in resources and files, and how to convert written text into spoken words. It’s possible that this introductory chapter contains all the information you need to successfully integrate sound into your application.

Once you are familiar with basic sound recording and production on Macintosh computers, you might want to read other chapters in this book. The chapter “Sound Manager” provides complete information about sound output. It shows how to control sound production at a very low level, how to produce sound asynchronously (that is, while other operations in the computer take place), and how to compress and expand audio data. This chapter also provides complete details about the structure of the two main sound storage formats, sound resources and sound files.

If you need more control over the sound recording process than is offered by the basic recording functions described in the chapter “Introduction to Sound on the Macintosh,” you need to read the chapter “Sound Input Manager.” That chapter shows how to record sound without displaying the sound recording dialog box or to interact directly with a sound input device driver.

The chapter “Speech Manager” shows how you can convert written text into speech. You’ll need to read this chapter if you want to convert arbitrary blocks of text (such as very large buffers of text) into spoken words, or if you need to gain very fine control over speech production (for example, to synchronize speech production with other activities, or to use customized pronunciation dictionaries).

The chapter “Sound Components” describes how to write sound components. The Sound Manager uses sound components to manipulate audio data or to communicate with sound output devices. You need to read this chapter only if you are developing a new sound output device or want to use a custom audio data compression and expansion scheme.

The chapter “Audio Components” describes how to write audio components. The Sound Manager uses audio components to adjust volumes or other settings of a sound output device when the device contains multiple output ports that can be independently controlled by software. You need to read this chapter only if you are developing a new sound output device that contains several sound-producing ports (such as both speakers and headphones).

Format of a Typical Chapter

Almost all chapters in this book follow a standard structure. For example, the chapter “Sound Input Manager” contains these sections:

- “About the Sound Input Manager.” This section provides an overview of the features provided by the Sound Input Manager.
- “Using the Sound Input Manager.” This section describes the tasks you can accomplish using the Sound Input Manager. It describes how to use the most common routines, gives related user interface information, provides code samples, and supplies additional information.
- “Sound Input Manager Reference.” This section provides a complete reference for the Sound Input Manager by describing the constants, data structures, routines, and resources it uses. Each routine description also follows a standard format, which presents the routine declaration followed by a description of every parameter of the routine. Some routine descriptions also give additional descriptive information, such as assembly-language information or result codes.
- “Summary of the Sound Input Manager.” This section provides the Pascal and C interfaces for the constants, data structures, routines, and result codes associated with the Sound Input Manager. It also includes relevant assembly-language interface information.

Conventions Used in This Book

Inside Macintosh uses special conventions to present certain types of information. Words that require special treatment appear in specific fonts or font styles. Certain information, such as parameter blocks, appears in special formats so that you can scan it quickly.

Special Fonts

All code listings, reserved words, and the names of actual data structures, constants, fields, parameters, and routines are shown in Courier (`this is Courier`).

Words that appear in **boldface** are key terms or concepts and are defined in the glossary.

Types of Notes

There are several types of notes used in this book.

Note

A note like this contains information that is interesting but possibly not essential to an understanding of the main text. (An example appears on page 1-6.) ◆

IMPORTANT

A note like this contains information that is essential for an understanding of the main text. (An example appears on page 1-9.) ▲

▲ WARNING

Warnings like this indicate potential problems that you should be aware of as you design your application. Failure to heed these warnings could result in system crashes or loss of data. (An example appears on page 2-24.) ▲

Assembly-Language Information

Inside Macintosh provides information about the registers for specific routines in this format:

Registers on entry

A0 Contents of register A0 on entry

Registers on exit

D0 Contents of register D0 on exit

In the “Assembly-Language Summary” section at the end of each chapter, *Inside Macintosh* presents information about the fields of data structures in this format:

0	what	word	event code
2	message	long	event message
6	when	long	ticks since startup

The left column indicates the byte offset of the field from the beginning of the data structure. The second column shows the field name as defined in the MPW Pascal interface files; the third column indicates the size of that field. The fourth column provides a brief description of the use of the field. For a complete description of each field, see the discussion of the data structure in the reference section of the chapter.

In addition, *Inside Macintosh* presents information about the fields of a parameter block in this format:

Parameter block

↔	inAndOut	Integer	Input/output parameter.
←	output1	Ptr	Output parameter.
→	input1	Ptr	Input parameter.

The arrow in the far left column indicates whether the field is an input parameter, output parameter, or both. You must supply values for all input parameters and input/output parameters. The routine returns values in output parameters and input/output parameters.

The second column shows the field name as defined in the MPW Pascal interface files; the third column indicates the Pascal data type of that field. The fourth column provides a brief description of the use of the field. For a complete description of each field, see the discussion that follows the parameter block or the description of the parameter block in the reference section of the chapter.

Development Environment

The system software routines described in this book are available using Pascal, C, or assembly-language interfaces. How you access these routines depends on the development environment you are using. When showing system software routines, this book uses the Pascal interfaces available with the Macintosh Programmer's Workshop (MPW). However, the chapters "Sound Components" and "Audio Components" use C interfaces, because Pascal interfaces are not currently available.

All code listings in this book are shown in Pascal or C. They show methods of using various routines and illustrate techniques for accomplishing particular tasks. All code listings have been compiled and, in most cases, tested. However, Apple Computer, Inc. does not intend for you to use these code samples in your application.

This book occasionally illustrates concepts by referring to a sample application called SurfWriter. This application is not an actual product of Apple Computer, Inc. This book also uses the names SurfBoard and WaveMaker to refer to sample sound output and input devices. These devices are not actual products of Apple Computer, Inc.

For More Information

APDA is Apple's worldwide source for over three hundred development tools, technical resources, training products, and information for anyone interested in developing applications on Apple platforms. Customers receive the quarterly *APDA Tools Catalog* featuring all current versions of Apple and the most popular third-party development tools. Ordering is easy; there are no membership fees, and application forms are not required for most of our products. APDA offers convenient payment and shipping options, including site licensing.

To order products or to request a complimentary copy of the *APDA Tools Catalog*, contact

APDA
 Apple Computer, Inc.
 P.O. Box 319
 Buffalo, NY 14207-0319

Telephone	800-282-2732 (United States) 800-637-0029 (Canada) 716-871-6555 (International)
Fax	716-871-6511
AppleLink	APDA
America Online	APDAorder
CompuServe	76666,2405
Internet	APDA@applelink.apple.com

If you provide commercial products and services, call 408-974-4897 for information on the developer support programs available from Apple.

For information of registering signatures, file types, and other technical information, contact

Macintosh Developer Technical Support
 Apple Computer, Inc.
 20525 Mariani Avenue, M/S 303-2T
 Cupertino, CA 95014-6299

Introduction to Sound on the Macintosh

Contents

About Sound on Macintosh Computers	1-4
Sound Capabilities	1-4
Sound Production	1-9
Sound Recording	1-15
Sound Resources	1-17
Sound Files	1-18
Speech Generation	1-20
The User Interface for Sound	1-23
Using Sound on Macintosh Computers	1-24
Producing an Alert Sound	1-24
Playing a Sound Resource	1-25
Playing a Sound File	1-26
Checking For Sound-Recording Equipment	1-27
Recording a Sound Resource	1-28
Recording a Sound File	1-31
Checking For Speech Capabilities	1-31
Generating Speech From a String	1-32
Sound Reference	1-34
Routines	1-34
Playing Sounds	1-34
Recording Sounds	1-38
Generating and Stopping Speech	1-41
Summary of Sound	1-44
Pascal Summary	1-44
Constants	1-44
Routines	1-44
C Summary	1-45

CHAPTER 1

Constants	1-45
Routines	1-46
Result Codes	1-47

This chapter provides an introduction to managing sound on Macintosh computers. It's intended to help you quickly get started integrating sound into your application. This chapter introduces the concepts described in detail throughout the rest of this book and provides source code examples that show you how to use the most basic sound-related capabilities of Macintosh computers. These examples use the Sound Manager to play sounds, the Sound Input Manager to record sounds, and the Speech Manager to convert text strings into spoken words.

Even if your application is not specifically concerned with creating or playing sounds, you can often improve your application at very little programming expense by using these system software services to integrate sound or speech into its user interface. For example, you might use the techniques described in this chapter to

- play a sound to alert the user that a lengthy spreadsheet calculation is completed
- provide voice annotations for a word-processing document
- read aloud the text string that is displayed in a dialog box

If you want to use sound in these simple ways, this chapter will probably provide all the information you need. The Sound Manager, Sound Input Manager, and Speech Manager provide high-level routines that make it very easy to play or record sounds without knowing very much about how sounds are stored or produced electronically.

If, on the other hand, you are writing an application that is primarily concerned with sound, you should read this chapter and some of the remaining chapters in this book. You also need to read those chapters if you want to play computer-generated tones without using sound resources or sound files, play sounds asynchronously, play sounds at different pitches, record sounds without using the standard sound recording interface, or customize the quality of speech output to make it easier to understand.

To benefit most from this chapter, you should already be familiar with simple resource and file management, discussed in the chapters “Resource Manager” in *Inside Macintosh: More Macintosh Toolbox* and “Introduction to File Management” in *Inside Macintosh: Files*. In particular, this chapter does not explain how to open or close resource or data files, although it does provide source code examples that demonstrate how to play a sound from, or record a sound to, a resource or data file that is already open.

This chapter begins with an overview of sound on Macintosh computers. It describes the audio capabilities available on all Macintosh computers and some of the capabilities achievable by adding additional hardware and software to Macintosh computers. Then this chapter describes how you can use the available system software routines to

- play the system alert sound
- play sounds stored as resources
- play sampled sounds stored in sound files
- determine whether a particular Macintosh computer is capable of recording sounds
- record sounds into resources
- record sounds into sound files
- convert text strings into spoken words

For your convenience, this chapter also includes a reference section containing complete descriptions of the routines used to perform these tasks, and both Pascal and C language summaries. All of the routines in the reference section of this chapter are also in the reference sections of the chapter that describes the manager they are part of.

About Sound on Macintosh Computers


The Macintosh hardware and system software provide a standard and extensible set of capabilities for producing and recording sounds. No matter what kind of application you are developing, you can use these capabilities to enrich your application, often at very little programming expense. For example, you might allow users to attach voice annotations to documents or to other collections of data. Or, you might play a certain sound to signal that some operation has completed.

This section provides a general overview of the sound input and output capabilities available on Macintosh computers. It defines some of the concepts used throughout this book and describes how sounds can be stored by your application. This section also describes the standard ways of representing sounds in the Macintosh graphical user interface.

Sound Capabilities

The Macintosh family of computers provides sound input and output capabilities that far exceed the capabilities of most other personal computers. The principal reason for this is that the hardware and software aspects of creating or recording sounds are more tightly integrated with one another than they are on other personal computers. Figure 1-1 illustrates the basic audio hardware and the sound-related system software that are now standard on all Macintosh computers.

Figure 1-1 Basic sound capabilities on Macintosh computers



The audio hardware includes an internal speaker (for producing sounds), a microphone (for recording sounds), and one or more integrated circuits that convert digital data to analog signals, or analog signals to digital data. The actual integrated circuits that perform the conversion of digital to analog data (and vice versa) vary among different models of Macintosh computers. What's important is that, together with the available sound-related system software, the basic audio hardware provides a wide range of sound input and output capabilities, including

- playback of digitally recorded (that is, sampled) sounds
- playback of simple sequences of notes or of complex waveforms
- recording of sampled sounds
- conversion of text to spoken words
- mixing and synchronization of multiple channels of sampled sounds
- compression and decompression of sound data to minimize storage space

In general, you'll interact directly with the system software that provides these and other capabilities. The Macintosh sound architecture includes three principal system software services:


- **The Sound Manager** provides the ability to play sounds through the speaker. It also provides an extensive set of tools for manipulating sounds. You can use the Sound Manager to alter virtually any characteristic of a sound, such as its loudness, pitch, timbre, and duration. You can also use the Sound Manager to compress sounds so that they occupy less disk space. The Sound Manager can work with sounds stored in resources or in a file's data fork. It can also play sounds that are generated dynamically (and not necessarily stored on disk).
- **The Sound Input Manager** provides the ability to record sounds through a microphone or other sound input device. It manages the standard sound recording dialog box (shown in Figure 1-12 on page 1-17) and can record sounds into resources or into files.
- **The Speech Manager** provides the ability to convert written text into spoken words. You might use the Speech Manager to read aloud a block of text that for various reasons cannot be sampled (perhaps the amount of text is too large to be recorded and then replayed, or perhaps the text itself is generated dynamically by the user). The Speech Manager allows you to select from among a number of different voices, alter some of the readback characteristics (such as speech, pitch, and volume), and provide custom pronunciation dictionaries.

The basic sound hardware and system software also provide the ability to integrate and synchronize sound production with the display of other types of information, such as video and still images. For example, QuickTime uses the Sound Manager to handle all the sound data in a QuickTime movie.

It's very easy for users to enhance the quality of the sounds they play back or record by substituting different speakers or microphones for the ones built into a Macintosh computer. All current Macintosh computers include a stereo sound output jack that allows users to add high quality speakers (such as the AppleDesign Powered Speakers). A user can also substitute a higher quality microphone for the one supplied with the

computer. Figure 1-2 illustrates a slightly better audio configuration than the one shown in Figure 1-1.

Figure 1-2 Enhanced sound capabilities on Macintosh computers



Note that the enhanced sound input and output capabilities shown in Figure 1-2 are provided entirely by the improved hardware. The system software (in particular, the Sound Manager and the Sound Input Manager) can support both the built-in audio hardware and any external hardware connected to the built-in audio jacks.

It's possible to enhance the audio capabilities of a Macintosh computer even further. For example, a user can add a NuBus™ expansion card that contains very high quality digital signal processing (DSP) circuitry, together with sound input or output hardware. These cards typically bypass the standard Macintosh sound circuitry altogether and therefore require additional software (a device driver) to work with the Sound Manager or the Sound Input Manager. The system software is, however, designed to make it easy for developers to add software to drive their sound output or sound input devices.


A user can also enhance the audio capabilities of a Macintosh computer by adding a MIDI interface to one of its serial ports. **MIDI** (the Musical Instrument Digital Interface) is a standard protocol for sending audio data and commands to digital devices. A user can connect any MIDI devices (such as synthesizers, drum machines, or lighting controllers) to a Macintosh computer through the MIDI interface. Apple Computer supplies a software driver, the **MIDI Manager**, to control the flow of MIDI data and commands through the MIDI interface.

Note

The MIDI Manager is not documented in this book. For complete information about the MIDI Manager, contact APDA. ♦

Figure 1-3 illustrates a very high capability sound and music configuration built around a Macintosh computer. This enhanced hardware and system software configuration allows users to run digital sound editing or recording applications and MIDI sequencing applications.

Figure 1-3 High quality sound capabilities on Macintosh computers




It's possible to enhance the sound environment on a Macintosh computer by adding software alone, for example by adding custom sound **compression/decompression components (codecs)**. Apple Computer supplies codecs that can handle 3:1 and 6:1 compression and expansion, which are suitable for most audio requirements. For special purposes, however, it might be advantageous to use other compression and expansion ratios or algorithms. The Sound Manager can use any available codec to handle compression and expansion of audio data.


More generally, the Sound Manager supports arbitrary modifications on sound data using stand-alone code resources known as **sound components**. A sound component can

perform one or more signal-processing operations on sound data. For example, the Sound Manager includes sound components for compressing and decompressing sound data (as described in the previous paragraph) and for converting sample rates. Sound components have a standard programming interface and local storage, which allows them to be hooked together in series to perform complex tasks. For instance, to play an 11 kHz compressed sampled sound on a Macintosh II computer, the Sound Manager needs to expand the compressed data into audio samples, convert the samples from 11 kHz to 22 kHz, mix the samples with any other sounds that are playing, and then send the mixed samples to the available audio hardware (in this case, the Apple Sound Chip). The Sound Manager uses four different sound components to accomplish this task, as shown in Figure 1-4.

Figure 1-4 A sound component chain



Except for the lowest-level components that communicate directly with hardware (here, the Apple Sound Chip), the components of this chain operate solely on a stream of bytes. This allows Apple and other developers to create sound components that operate independently of the actual sound-producing hardware available on a particular Macintosh computer. This also allows the Sound Manager to modify the component chain used at any time according to the actual capabilities of the output hardware. For example, a digital signal processing card might be able to do rate conversion internally. In that case, the Sound Manager can bypass the rate conversion component and send the 11 kHz samples directly to the DSP card, as shown in Figure 1-5.

Figure 1-5 A sound component chain with a DSP board

In general, an application that wants to produce a sound is unaware of the sound component chain required to produce that sound on the current sound output device. The Sound Manager keeps track of which sound output device the user has selected and constructs a component chain suitable for producing the desired quality of sound on that device. As a result, even though the capabilities of the available sound output hardware can vary greatly from one Macintosh computer to another, the Sound Manager ensures that a given chunk of audio data always sounds as good as possible on the available sound hardware. This means that you can use the same code to play sounds, regardless of the actual sound-producing hardware that is available on a particular machine.

The Sound Manager provides sound components for modifying and producing sounds on the built-in audio hardware and on any hardware attached to the sound output jack. The Macintosh sound architecture currently allows you to add sound components for two special purposes: to support alternate compression and decompression algorithms and to support third-party audio hardware. See the chapter “Sound Components” in this book for information on developing codecs and sound output device components.

IMPORTANT

You don’t need to know how to develop sound components simply to play or record sounds on Macintosh computers using the available sound output or input devices. ▲

The following sections describe in greater detail the operations of the Sound Manager, the Sound Input Manager, and the Speech Manager. You’ll use the Sound Manager to produce sounds, the Sound Input Manager to record sounds, and the Speech Manager to generate speech from text.

Sound Production

A Macintosh computer produces sound when the Sound Manager sends some data through a sound channel to the available audio hardware, usually at the request of an application. The audio hardware is a **digital-to-analog converter (DAC)** that translates digital sound data into analog audio signals. Those signals are then sent to the internal speaker, to a sound output connector (to which the user can connect headphones, external speakers, or sound amplification equipment), or to other sound output hardware.

The DAC in Macintosh Plus and Macintosh SE computers is a Sony sound chip. The Macintosh II, Macintosh Portable, Macintosh PowerBook and Macintosh Quadra


Introduction to Sound on the Macintosh

families of computers contain two Sony sound chips (to provide stereo output capability) as well as the **Apple Sound Chip (ASC)**, a customized chip that provides enhanced audio output characteristics as well as emulation capabilities for the earlier sound hardware.

Some recent models of Macintosh computers contain built-in sound hardware that extends the Apple Sound Chip's features. For example, Macintosh computers with built-in microphones include the **Enhanced Apple Sound Chip (EASC)**. Some Macintosh computers contain DSP chips that provide very high-quality sound (16-bit stereo sound, at rates up to 44 kHz). There are also NuBus expansion cards available from third-party developers that provide other audio DAC hardware.

A user can select a sound output device or control characteristics of the selected device through the **Sound Out control panel**, shown in Figure 1-6. The available sound output devices are listed in the center of the panel. In this case, two sound output devices are attached to the computer, the built-in speaker and a speaker attached to the SurfBoard DSP card. The highlighted icon shows which device is the **current sound output device**. All sounds produced by the Sound Manager are sent to that device for playback, unless you specify some other device when creating a sound channel. (See the description of `SndNewChannel` in the chapter "Sound Manager" for details on specifying an output device explicitly.)

Figure 1-6 The Sound Out control panel



Note


This book shows the Sound control panels introduced with version 3.0 of the Sound Manager. Users can use the pop-up menu at the top of the panel to select one of four or more subpanels (Alert Sounds, Sound In, Sound Out, and Volumes). It's possible to add new subpanels to the Sound control panel. See the chapter on control panel extensions in the book *Inside Macintosh: Operating System Utilities*. ♦

You can play a sound by calling a Sound Manager routine such as `SysBeep` (to play the system alert sound), `SndPlay` (to play a sound stored in memory), or

`SndStartFilePlay` (to play a sound stored in a file). The Sound Manager then issues one or more sound commands to the audio hardware. A **sound command** is an instruction to produce sound, modify sound, or otherwise assist in the overall process of sound production.

To ensure that sound commands are issued in the correct order, the Sound Manager uses a structure called a sound channel to store commands. A **sound channel** is associated with a first-in, first-out (FIFO) queue of sound commands. Queued commands are sent to the sound hardware through a sound output device component, a component that manages the last stage of communication with the audio hardware. Figure 1-7 shows how your application communicates, through the Sound Manager and the sound output device component, with the current sound output device.

Figure 1-7 The relation of the Sound Manager to the audio hardware




Note

This chapter does not discuss sound commands or channels in detail, because you do not need to know about these details to play sound data stored in sound resources or sound files. This chapter describes only how to play and record sampled sounds. For more information on sound channels and sound commands, see the chapter “Sound Manager” in this book. ♦


You can play sounds either synchronously or asynchronously. When you play a sound **synchronously**, the Sound Manager alone has control over the CPU while it executes commands in a sound channel. Your application does not continue executing until the sound has finished playing. When you play a sound **asynchronously**, your application can continue other processing while the sound is playing. This chapter shows how to play sounds only synchronously. To learn how to play sounds asynchronously, see the chapter “Sound Manager” in this book.

Sometimes it is necessary to bypass the queue of sound commands. If, for example, you want to stop all sound production on a particular channel immediately, it would be counterproductive to put the command into the sound channel because that command wouldn't be processed until any others already in the queue were processed. You can send sound commands directly to the hardware component, as shown in Figure 1-8.

When you bypass the sound channel in this way, any commands that are already queued but not yet sent to the sound output device component remain queued. You can, however, flush the channel at any time by sending the Sound Manager the appropriate request.

Figure 1-8 Bypassing the command queue

It's possible to have several channels of sound open at one time. The Sound Manager (using a sound-mixing component called the **Apple Mixer component**) mixes together the data coming from all open sound channels and sends a single stream of sound data to the current sound output device. This allows a single application to play two or more sounds at once. It also allows multiple applications to play sounds at the same time, as illustrated in Figure 1-9.

Figure 1-9 Mixing multiple channels of sampled sound

The Sound Manager was first released for all Macintosh computers as part of system software version 6.0. System software versions 6.0.7 and later include an **enhanced Sound Manager** (that is, version 2.0) that provides routines for continuous play from disk, sound mixing, and audio compression and expansion. System software versions 6.0.7 and later also include the Sound Input Manager, which allows for recording sounds through either a built-in microphone or some other sound input device.

More recent versions of the Sound Manager significantly improve the performance of the Sound Manager's operations and extends its capabilities. Version 3.0 of the Sound Manager is as much as two to three times more efficient than previous versions, which allows your application to do more processing while a sound is playing. In addition, version 3.0 of the Sound Manager provides three important new capabilities:

- **Support for 16-bit audio samples.** Versions of the Sound Manager earlier than version 3.0 support only 8-bit monophonic or stereo audio samples with sample rates up to 22 kHz. The Sound Manager version 3.0 supports 16-bit stereo audio samples with sample rates up to 64 kHz, thereby allowing your application to produce CD-quality sound. Moreover, the Sound Manager version 3.0 automatically converts 16-bit samples into 8-bit samples on Macintosh computers that do not have the hardware to output 16-bit sounds.
- **Support for non-Apple audio hardware.** The Sound Manager version 3.0 and later use a sound architecture that allows support for third-party audio hardware. This allows a user to install audio hardware capable of recording and producing CD-quality sound. Versions 3.0 and later also include a new Sound control panel that allows the user to redirect sound output to any available audio hardware.
- **Support for plug-in codecs.** Versions of the Sound Manager earlier than version 3.0 support audio compression and expansion only at ratios of 3:1 and 6:1. The Sound Manager version 3.0 provides support for other compressed audio data formats by allowing plug-in audio compression and expansion components (or codecs).

You provide support for your own sound output devices or for your own compression and decompression algorithms by writing an appropriate sound component. See the chapter “Sound Components” later in this book for complete details.

The Sound Manager version 3.0 is supported only on Macintosh computers with an ASC or comparable hardware. In particular, the Sound Manager version 3.0 is not supported on Macintosh Classic, Macintosh Plus, or Macintosh SE computers. As a result, you should always test whether the specific capabilities you want to use are present before attempting to use them. You can use the `Gestalt` function to do this, as illustrated in “Checking For Sound-Recording Equipment” beginning on page 1-27 and in “Checking For Speech Capabilities” beginning on page 1-31.


This book describes the capabilities and programming interfaces of version 3.0 of the Sound Manager. Many of the techniques described here can also be used with earlier versions of the Sound Manager, but some cannot. Make sure to test your application thoroughly with all versions of the Sound Manager you want to run under.

Sound Recording

The Sound Input Manager provides the ability to record and digitally store sounds in a device-independent manner. You can create a resource or a file containing a recorded sound simply by calling either the `SndRecord` function or the `SndRecordToFile` function. You can then use the recorded sound in any way appropriate to your application.

The sound input and storage routines can be used with any available sound input hardware for which there is an appropriate device driver. A user can select from among the available sound input devices through the **Sound In control panel**, shown in Figure 1-10.


Figure 1-10 The Sound In control panel



The available sound input devices are listed in the center of the panel. The control panel lists a device if its driver has previously registered itself with the Sound Input Manager and has provided a name and device icon. In Figure 1-10, two sound input devices are available, a device named Built-in and a device named WaveMaker. The highlighted icon shows which device is the **current sound input device**.

The **Alert Sounds control panel** lists the available system alert sounds, as illustrated in Figure 1-11.

Figure 1-11 The Alert Sounds control panel




The Alert Sounds control panel also includes two buttons, Add and Remove. These buttons allow the user to add sounds to and remove sounds from the list of available system alert sounds. The Add button is used to record a new alert sound and add it to the list. Clicking the Add button causes the Sound Input Manager to display a sound recording dialog box (described later in this section). Clicking the Remove button causes the Sound Input Manager to remove the selected alert sound from the list. The user can achieve the same effect by selecting a sound and then choosing the Clear command in the Edit menu. If no sound input drivers are installed in the system, these two buttons do not appear.

If the user records a sound using the Alert Sounds control panel, the recorded sound is saved as a resource of type 'snd' in the System file. That sound then appears in the list of available alert sounds. Note that the Alert Sounds control panel supports the standard Edit menu commands on sounds stored in the System file. The Cut command copies the selected sound to the Clipboard and removes it from the list of system alert sounds. The Copy command just copies the selected sound to the Clipboard. The Paste command takes a sound copied from the Clipboard and places it in the list of available alert sounds. If your application allows users to manipulate sound resources, it should support the copying and pasting of sound resources through the Clipboard. However, the Undo command does not work with sound-related editing operations.

The Sound Input Manager provides two high-level routines that allow your application to record sounds from the user and store them in memory or in a file. When you call either `SndRecord` or `SndRecordToFile`, the Sound Input Manager presents a **sound recording dialog box** to the user, illustrated in Figure 1-12.

Figure 1-12 The sound recording dialog box



Using the controls in this dialog box, the user can start, pause, resume, and stop recording on the currently selected sound input device. The user can also play back the recorded sound. The time indicator bar provides an indication of the current length of the recorded sound.

When the user clicks the Save button after initiating a recording from the Sound control panel, another dialog box appears asking the user to give the sound a name. Unless the user cancels the save operation at that point, the Sound control panel saves the recorded sound into a sound resource in the System file. Note that if your application can save recorded sound resources, the `SndRecord` function does not present the dialog box that allows the user to name the sound and does not automatically save the recorded sound into a resource file. Your application must provide code to accomplish these tasks.

Sound Resources

Resources of type `'snd'` (also called **sound resources**) can contain both sound commands and sound data, and are widely used by sound-producing applications. These resources provide a simple and portable way for you to incorporate sounds into your application. For example, the sounds that a user can select in the Sound control panel as the system alert sound are stored in the System file as `'snd'` resources. The user can select the current system alert sound with the Alert Sounds control panel, as illustrated in Figure 1-11. More generally, you can load a sound resource into memory and then play it by calling the `SndPlay` function.

Note

If you do not use the sound-recording routines provided by the Sound Input Manager, you must know the structure of `'snd'` resources before you can create them. For information on this, see the chapter “Sound Manager” in this book. You can also use the `SetupSndHeader` function, described in the chapter “Sound Input Manager” in this book, to help you create an `'snd'` resource. ♦

The Sound Manager can read sound resources in two formats, format 1 or format 2. However, the format 2 'snd' resource is obsolete, so your application should use format 1 'snd' resources. For more information on the differences between format 1 and format 2 'snd' resources, see the chapter “Sound Manager” in this book.

The format 1 'snd' resource is the most general kind of sound resource. A format 1 'snd' resource can contain a sequence of Sound Manager commands and associated sound data (such as wave-table data or a sampled sound header that both describes a digitally recorded sound and includes the sampled-sound data itself). Your application can produce sounds simply by passing a handle to that resource to the `SndPlay` function, which opens a sound channel and sends the commands and data contained in the resource into the channel. Alternatively, a format 1 'snd' resource might contain a sequence of commands that describe a sound, without providing any other sound data. For example, such a resource could contain a command that alters the amplitude (or loudness) of sound playing on a channel. In this case, your application can use the `SndPlay` function to execute the commands on any channel.

Sound Files

Although most sampled sounds that you want your application to produce can be stored as sound resources, there are times when it is preferable to store sounds in **sound files**. For example, it is usually easier for different applications to share files than it is to share resources. So, if you want your application to play a sampled sound created by another application (or if you want other applications to be able to play a sampled sound created by your application), it might be better to store the sampled-sound data in a file, not in a resource. Similarly, if you are developing versions of your application that run on other operating systems, you might need a method of storing sounds that is independent of the Macintosh Operating System and its reliance on resources to store data. Generally, it is easier to transfer data stored in data files from one operating system to another than it is to transfer data stored in resources.

There are other reasons you might want to store some sampled sounds in files and not in resources. If you have a very large sampled sound, it might not be possible to create a resource large enough to hold all the audio data. Resources are limited in size by the structure of resource files (and in particular because offsets to resource data are stored as 24-bit quantities). Sound files, however, can be much larger because the only size limitations are those imposed by the file system on all files. If the sampled-sound data for some sound occupies more than about a half megabyte of space, you should probably store the sound as a file.

To address these various needs, Apple and several third-party developers have defined two sampled-sound file formats, known as the **Audio Interchange File Format (AIFF)** and the **Audio Interchange File Format Extension for Compression (AIFF-C)**. The names emphasize that the formats are designed primarily as data interchange formats. However, you should find both AIFF and AIFF-C flexible enough to use as data storage formats as well. Even if you choose to use a different storage format, your application should be able to convert to and from AIFF and AIFF-C if you want to facilitate sharing

of sound data among applications. AIFF format files have file type 'AIFF' and AIFF-C format files have file type 'AIFC'.

Note

Do not confuse AIFF and AIFF-C files (referred to in this chapter as *sound files*) with Finder sound files. Each **Finder sound file** contains a sound resource that plays when the user double clicks on the file in the Finder (or selects the file and chooses Open from the File menu). A user can create a Finder sound file by dragging a sound out of the System file, and a user can drag a Finder sound file into the System file to add the file's sound to the list of available system alert sounds. You can create a Finder sound file by creating a file of type 'sfil' with a creator of 'moVR' and placing in the file a single sound resource. You can play such a file by using Resource Manager routines to open the Finder sound file and then by using the `SndPlay` function to play the single sound resource contained in it. ♦

The main difference between the AIFF and AIFF-C formats is that AIFF-C allows you to store either compressed or noncompressed audio data, whereas AIFF allows you to store noncompressed audio data only. The AIFF-C format is more general than the AIFF format and is easier to modify. The AIFF-C format can be extended to handle new compression types and application-specific data. As a result, if your application reads or writes sound files, it should be able to handle both AIFF and AIFF-C files. Table 1-1 summarizes the capabilities of the AIFF and AIFF-C file formats.

Table 1-1 AIFF and AIFF-C capabilities

File type	Read sampled	Read compressed	Write sampled	Write compressed
AIFF	Yes	No	Yes	No
AIFF-C	Yes	Yes	Yes	Yes

The enhanced Sound Manager includes **play-from-disk** routines that allow you to play AIFF and AIFF-C files continuously from disk even while other tasks execute. You might think of the play-from-disk routines as providing you with the ability to install a “tape player” in a sound channel. Once the sound begins to play, it continues uninterrupted until it finishes or until an application pauses or stops it.

You can play a sampled sound stored in a file of type AIFF or AIFF-C by opening the file and passing its file reference number to the `SndStartFilePlay` function. If the file is of type AIFF-C and the data is compressed, then the data is automatically expanded during playback. The `SndStartFilePlay` function works like the `SndPlay` function but does not require the entire sound to be in RAM at one time. Instead, the Sound Manager uses two buffers, each of which is smaller than the sound itself. The Sound Manager plays one buffer of sound while filling the other with data from disk. After it finishes playing the first buffer, the Sound Manager switches buffers, and plays data in the second while refilling the first. This **double buffering** technique minimizes RAM usage at the expense

of additional disk overhead. As a result, `SndStartFilePlay` is ideal for playing very large sounds.

The disk overhead incurred when using `SndStartFilePlay` is relatively light, and most mass-storage devices currently available for Macintosh computers have response times that are good enough that `SndStartFilePlay` can retrieve audio data from disk and play a sound without audible gaps. There are no limits on the number of concurrent disk-based sampled-sound playbacks other than those imposed by processor speed and disk capability. On machines with sufficient CPU resources, several continuous playbacks can occur at once. Disk fragmentation can affect the performance of playing sampled-sound files from disk. In addition, playing multiple sounds from the same hard disk may degrade overall performance.


The Sound Manager currently supports continuous play from disk only on certain Macintosh computers. You should use the `Gestalt` function to determine whether a specific machine supports play from disk. Also, if a sound channel is being used for continuous play from disk, then no other sound commands can be sent to that channel.

Speech Generation

The Speech Manager converts text into sound data, which it passes to the Sound Manager to play through the current sound output device. The Speech Manager's interaction with the Sound Manager is transparent to your application, so you don't need to be familiar with the Sound Manager to take advantage of the Speech Manager's capabilities. This section provides an overview of the Speech Manager and outlines the process that the Speech Manager uses to convert text into speech.


Figure 1-13 illustrates the speech generation process. Your application can initiate speech generation by passing a string or a buffer of text to the Speech Manager. The Speech Manager is responsible for sending the text to a **speech synthesizer**, a component that contains executable code that manages all communication between the Speech Manager and the Sound Manager. A synthesizer is usually contained in a resource in a file within the System Folder. The synthesizer uses built-in dictionaries and pronunciation rules to help determine how to pronounce text. Your application can use the default system voice to generate speech; it can also specify that some other available voice be used for speech generation.

As Figure 1-13 suggests, the Speech Manager is a dispatching mechanism that allows your application to take advantage of the capabilities of whatever speech synthesizers, voices, and hardware are installed. The Speech Manager itself does not do any of the work of converting text into speech; it just provides a convenient programming interface that manages access to speech synthesizers and, indirectly, to the sound hardware. The Speech Manager uses the Component Manager to access whatever speech synthesizers are available and allows applications to take maximum advantage of a computer's speech facilities without knowing what those facilities are.

Figure 1-13 The speech generation process**Note**

The Component Manager is described in *Inside Macintosh: More Macintosh Toolbox*, but you do not need to be familiar with it to use the Speech Manager. ♦

A speech synthesizer can include one or more voices, as illustrated in Figure 1-14. Just as different people's voices have different tonal qualities, so too can different voices in a synthesizer. A synthesized voice might sound male or female, and might sound like an adult or child. Some voices sound distinctively synthetic, while others sound more like real people. As speech synthesizing technology develops, the voices that your application can access are likely to sound more and more human. Because the Speech Manager's routines work on all voices and synthesizers, you will not need to rewrite your application to take advantage of improvements in speech technology.

Figure 1-14 The Speech Manager and multiple voices

Any given person has only one voice, but can alter the characteristics of his or her speech in a number of different ways. For example, a person can speak slowly or quickly, and with a low or a high pitch. Similarly, the Speech Manager provides routines that allow you to modify these and other speech attributes, regardless of which voice is in use.

To indicate to the Speech Manager which voice or attributes you would like it to use in generating speech, your application must use a speech channel. A **speech channel** is a data structure that the Speech Manager uses when processing text; it can be associated with a particular voice and particular speech attributes. Because multiple speech channels can coexist, your application can create several different vocal environments (to simulate a conversation, for example). Because a synthesizer can be associated with only one language and region, your application would need to create a separate speech channel to process each language in bilingual or multilingual text. (Currently, however, only English-producing synthesizers are available.)

Different speech channels can even generate speech simultaneously, subject to processor capabilities and Sound Manager limitations. This capability should be used with restraint, however, because it can be hard for the user to understand any speech when more than one channel is generating speech at a time. Also, your application should in general generate speech only at the specific request of the user and should allow the user to turn off speech output. At the very least, your application should include an option that allows the user to view text instead of hearing it. Some users might have trouble understanding speech generated by the Speech Manager, and others might be hearing-impaired. Even users who are able to clearly understand computer-synthesized speech might prefer to read rather than hear.

In general, your application does not need to know which speech synthesizer it is using. You can obtain a list of all available voices, but in most cases, you do not need to be concerned with which speech synthesizer a voice is associated. Sometimes, however, a speech synthesizer may provide special capabilities beyond that provided by the Speech Manager. For example, a speech synthesizer might allow you to select an option to read numbers in a nonstandard way. The Speech Manager allows you to determine which synthesizer is associated with a voice for these circumstances, and provides hooks that allow your application to take advantage of synthesizer-specific capabilities.

In general, however, your application can achieve the best results by making no assumptions about which synthesizers might be available. The user of a 2 MB Macintosh Classic[®] might use a synthesizer with low RAM requirements, while the user of a 20 MB Macintosh Quadra 950 might take advantage of a synthesizer that provides better audio quality at the expense of memory usage. The Speech Manager makes it easy to accommodate both kinds of users.

The most basic use of the Speech Manager is to convert a text string into speech. The `SpeakString` function, described in “Generating Speech From a String” beginning on page 1-32, lets you do this even without allocating a speech channel. The chapter “Speech Manager” in this book describes how you can customize the quality of speech output to make it easier to understand and how you can obtain more control over speech by allocating speech channels and embedding commands within text strings.

The User Interface for Sound

As you have seen, the Macintosh system software provides you with a wide array of easy-to-use sound-input and sound-output services. With very little programming, you can

- play the user's system alert sound or any sound contained in a sound resource or file
- record sounds through the available sound-input hardware
- convert text into speech


The system software has already defined a set of user interface elements and metaphors that are designed to facilitate the integration of sound into the Macintosh graphical user interface. In general, you should use the existing system software services to present the standard interface elements designed by Apple. For example, if you want to have the user record through the available sound-input hardware, you can call the `SndRecord` function, which displays the sound recording dialog box (shown in Figure 1-12 on page 1-17). That dialog box contains controls that are modelled on the buttons typically found on an audio tape recorder or a video cassette recorder. In this way, the system software draws on the user's knowledge of how to operate a tape recorder and uses it as a metaphor for recording sounds on Macintosh computers.

The system software also provides visual representations of sounds themselves. In some cases, sounds are represented by their names only, as in the Alert Sounds control panel (shown in Figure 1-11 on page 1-16). In other cases, sounds are represented by icons. For example, the icon for a Finder sound looks like the one shown in Figure 1-15. All Finder sounds are represented by the same icon; they are distinguished from each other by their names.

Figure 1-15 An icon for a Finder sound



If the user copies or cuts a sound from the available system alert sounds and then pastes the sound into the Scrapbook, the sound is shown as in Figure 1-16.

Figure 1-16 A sound in the Scrapbook

As you can see, the metaphor in both cases is that of a speaker, a sound-producing device familiar to most computer users. If you need to design icons to represent sounds created by your application, you might want to use (or suitably adapt) these existing metaphors. For example, if your application supports document annotations with recorded voices or other sounds, you can display a speaker icon within the document. Clicking or double-clicking the icon should result in playing the sound.

Keep in mind that applications that play sound should allow users to turn off sound output, because there might be users who object to it or environments where it is inappropriate. Also, there might be cultural biases or preferences associated with certain sounds. Thus, if your application plays specific sounds, you should store them as resources, which can be easily modified for local regions, or if they are very large, in sound files, which you can replace easily during localization.

Using Sound on Macintosh Computers

This section describes the most basic ways of using the Sound Manager, the Sound Input Manager, and the Speech Manager. In particular, it provides source code examples that show how to produce an alert sound, play a sound resource, play a sound file, determine whether your application can access sound recording equipment, record a sound resource, record a sound file, and convert a text string to spoken words.

Producing an Alert Sound

You can produce a **system alert sound** to catch the user's attention by calling the `SysBeep` procedure. The `SysBeep` procedure is a Sound Manager routine that plays the alert sound selected by the user in the Alert Sounds control panel. Here's an example of calling `SysBeep`:

```
IF myErr <> noErr THEN
    SysBeep(30);
```

You must supply a parameter when you call the `SysBeep` procedure, even though the Sound Manager ignores that parameter in most cases. All system alert sounds are stored as format 1 'snd' resources in the System file and are played by the Sound Manager. There is one instance in which the number passed to `SysBeep` is not ignored: if the user has selected the Simple Beep as the system alert sound on some Macintosh computers (for example, a Macintosh Plus or Macintosh SE), the beep is generated by code stored in ROM rather than by the Sound Manager, and the duration parameter is interpreted in ticks (sixtieths of a second).

The `SysBeep` procedure has no effect if an application has disabled the system alert sound. You might do this to prevent the system alert sound from interrupting some other sound. For information on enabling and disabling the system alert sound, see the chapter “Sound Manager” in this book.

You should not call the `SysBeep` procedure at interrupt time, because doing so causes the Sound Manager to attempt to allocate memory and load a resource.

Note

If your primary use of the `SysBeep` procedure is to alert the user of important or abnormal occurrences, it might be preferable to use the Notification Manager. See the chapter “Notification Manager” in *Inside Macintosh: Processes* for complete details on alerting the user. ♦

Playing a Sound Resource

You can play a sound stored in a resource by calling the `SndPlay` function, which requires a handle to an existing 'snd' resource. An 'snd' resource contains sound commands that play the desired sound. The 'snd' resource might also contain sound data. If it does (as in the case of a sampled sound), that data might be either compressed or noncompressed. `SndPlay` decompresses the data, if necessary, to play the sound. Listing 1-1 illustrates how to play a sound resource.

Listing 1-1 Playing a sound resource with `SndPlay`

```
FUNCTION MyPlaySndResource (mySndID: Integer): OSErr;
CONST
    kAsync = TRUE;                                {for asynchronous play}
VAR
    mySndHandle: Handle;                          {handle to an 'snd' resource}
    myErr: OSErr;
BEGIN
    mySndHandle := GetResource('snd', mySndID);
    myErr := ResError;                            {remember any error}
    IF mySndHandle <> NIL THEN                   {check for a NIL handle}
```

Introduction to Sound on the Macintosh

```

BEGIN
    HLock(mySndHandle);           {lock the sound data}
    myErr := SndPlay(NIL, mySndHandle, NOT kAsync);
    HUnlock(mySndHandle);       {unlock the sound data}
    ReleaseResource(mySndHandle);
END;
MyPlaySndResource := myErr;     {return the result}
END;

```

When you pass `SndPlay` a `NIL` sound channel pointer in its first parameter, the Sound Manager automatically allocates a sound channel (in the application's heap) and then disposes of it when the sound has completed playing. Note, however, that when your application does pass `NIL` as the pointer to a sound channel, the third parameter to `SndPlay` is ignored; the sound plays synchronously even if you specify that you want it to play asynchronously.

IMPORTANT

The handle you pass to `SndPlay` must be locked for as long as the sound is playing. ▲

Playing a Sound File

You can initiate and control a playback of sampled sounds stored in a file using the `SndStartFilePlay`, `SndPauseFilePlay`, and `SndStopFilePlay` functions. You use `SndStartFilePlay` to initiate the playing of a sound file. If you allocate your own sound channel and specify that play be asynchronous, you can then use the `SndPauseFilePlay` and `SndStopFilePlay` functions to pause, resume, and stop sound files that are playing. The chapter "Sound Manager" in this book describes these two functions in detail.

To play a sampled sound that is contained in a file, you pass `SndStartFilePlay` the file reference number of the file to play. The sample should be stored in either AIFF or AIFF-C format. If the sample is compressed, it is automatically expanded during playback. If you specify `NIL` as the sound channel, then `SndStartFilePlay` allocates memory for a channel internally. Listing 1-2 defines a function that plays a file specified by its file reference number.

Listing 1-2 Playing a sound file with `SndStartFilePlay`

```

FUNCTION MyPlaySoundFile (myFileRefNum: Integer): OSErr;
CONST
    kAsync = TRUE;           {for asynchronous play}
    kBufferSize = 20480;    {20K play buffer}
VAR
    myErr:   OSErr;
BEGIN

```

```

myErr := SndStartFilePlay(NIL, myFileRefNum, 0, kBufferSize,
                          NIL, NIL, NIL, NOT kAsync);
MyPlaySoundFile := myErr;
END;

```

To allow the Sound Manager to handle all memory allocation automatically, you should pass `NIL` as the first and fifth parameters to `SndStartFilePlay`, as done in Listing 1-2. The first `NIL` specifies that you want `SndStartFilePlay` to allocate a sound channel itself. The `NIL` passed as the fifth parameter specifies that `SndStartFilePlay` should automatically allocate buffers to play the sound. The `SndStartFilePlay` function then allocates two buffers, each half the size specified in the fourth parameter; if the fourth parameter is 0, the Sound Manager chooses a default size for the buffers.

The third parameter passed to `SndStartFilePlay` here is set to 0. That parameter is used only when playing sound resources from disk.

The seventh parameter to `SndStartFilePlay` allows you to specify a routine to be executed when the sound finishes playing. This is useful only for asynchronous play. In Listing 1-2, the value `NOT kAsync` (that is, `FALSE`) is passed as the eighth parameter to `SndStartFilePlay` to request synchronous playback. `SndStartFilePlay` would return a `badChannel` result code if you request asynchronous playback because `MyPlaySoundFile` does not allocate a sound channel.

Checking For Sound-Recording Equipment

Before allowing a user to record a sound, you must ensure that sound-recording hardware and software are installed. You can record sound through the microphone built into several Macintosh models, or through third-party sound input devices. Because low-level sound input device drivers handle communication between your application and the sound recording hardware, you do not need to know what type of microphone is available. Listing 1-3 defines a function that determines whether sound recording hardware is available.

Listing 1-3 Determining whether sound recording equipment is available

```

FUNCTION MyHasSoundInput: Boolean;
VAR
    myFeature: LongInt;
    myErr: OSErr;
BEGIN
    myErr := Gestalt(gestaltSoundAttr, myFeature);
    IF myErr = noErr THEN {test sound input device bit}
        MyHasSoundInput := BTst(myFeature, gestaltHasSoundInputDevice)
    ELSE
        MyHasSoundInput := FALSE; {no sound features available}
END;

```

The `MyHasSoundInput` function defined in Listing 1-3 uses the `Gestalt` function to determine whether sound input hardware is available and usable on the current Macintosh computer. `MyHasSoundInput` tests the `gestaltHasSoundInputDevice` bit and returns `TRUE` if you can record sounds. `MyHasSoundInput` returns `FALSE` if you cannot record sounds (either because no sound input device exists or because the Sound Input Manager is not available).

Note

For more information on the `Gestalt` function, see *Inside Macintosh: Operating System Utilities*. ♦

Recording a Sound Resource

You can record sounds from the current input device by using the `SndRecord` function. The `SndRecord` function presents the sound recording dialog box. When calling `SndRecord`, you need to provide a handle to a block of memory where the incoming data should be stored. If you pass the address of a `NIL` handle, however, the Sound Input Manager allocates a large block of space in your application heap and resizes it when the recording stops. Listing 1-4 illustrates how to call `SndRecord`.

Listing 1-4 Recording through the sound recording dialog box

```
PROCEDURE MyRecordThruDialog (VAR mySndHandle: Handle);
VAR
    myErr:      OSErr;
    myCorner:   Point;
BEGIN
    MyGetTopLeftCorner(myCorner);
    mySndHandle := NIL;      {use default memory allocation}
    myErr := SndRecord(NIL, myCorner, siBestQuality, mySndHandle);
    IF (myErr <> noErr) AND (myErr <> userCanceledErr) THEN
        DoError(myErr);
END;
```

If the user cancels sound recording, then the `SndRecord` function returns the result code `userCanceledErr`. The `MyRecordThruDialog` procedure defined in Listing 1-4 returns a `NIL` sound handle if the user cancels recording.

If you pass a sound handle that is not `NIL` as the fourth parameter to the `SndRecord` function, the Sound Input Manager derives the maximum time of recording from the amount of space reserved by that handle. The handle is resized on completion of the recording.

The first parameter in the call to `SndRecord` is the address of a filter procedure that determines how user actions in the dialog box are filtered. In Listing 1-4, no filter procedure is desired, so the parameter is specified as `NIL`. For information

on filter procedures, see the chapter “Dialog Manager” in *Inside Macintosh: Macintosh Toolbox Essentials*.

The second parameter in the call to `SndRecord` is the desired location (in global coordinates) of the upper-left corner of the dialog box. For example, the Sound control panel displays the dialog box near the control panel. Your application might place the dialog box elsewhere (for example in the standard alert position on the main screen). For more information on centering dialog boxes, see the chapter “Dialog Manager” in *Inside Macintosh: Macintosh Toolbox Essentials*.

The third parameter in the call to `SndRecord` specifies the quality of the recording. Currently three values are supported:

```
CONST
    siBestQuality      = 'best';    {the best quality available}
    siBetterQuality    = 'betr';    {a quality better than good}
    siGoodQuality      = 'good';    {a good quality}
```

The precise meanings of these constants are defined by the current sound-input device driver. The constant `siBestQuality` indicates that you want the highest quality recorded sound, usually at the expense of increased storage space (possibly because no compression is performed on the sound data). The constant `siGoodQuality` indicates that you are willing to sacrifice audio quality if necessary to minimize the amount of storage space required (typically this means that 6:1 compression is performed on the sound data). For most voice recording, you should specify `siGoodQuality`. The constant `siBetterQuality` defines a quality and storage space combination that is between those provided by the other two constants.

You could play the sound recorded using the `MyRecordThruDialog` procedure defined in Listing 1-4 by calling `SndPlay` and passing it the sound handle `mySndHandle`. That handle refers to some data in memory that has the structure of an 'snd' resource, but it is not a handle to an existing resource. To save the recorded data as a resource, you can use the Resource Manager. Listing 1-5 calls the `MyRecordThruDialog` procedure and then uses the Resource Manager to save the recorded data as a resource in an open resource file.

Listing 1-5 Recording a sound resource

```
PROCEDURE MyRecordSndResource (resFileRefNum: Integer);
CONST
    kMinSysSndRes = 0;           {lowest reserved 'snd' resource ID}
    kMaxSysSndRes = 8191;       {highest reserved ID}
VAR
    myPrevResFile: Integer;     {current resource file}
    mySndHandle:   Handle;      {handle to resource data}
    myResID:       LongInt;     {ID of resource}
    myResName:     Str255;      {name of resource}
```

```

myErr:          OSErr;
BEGIN
myPrevResFile := CurResFile;      {remember current resource file}
UseResFile(resFileRefNum);        {temporarily switch resource files}
MyRecordThruDialog(mySndHandle);  {record via standard interface}
IF mySndHandle <> NIL THEN
BEGIN                                {recording finished successfully}
  REPEAT                              {find acceptable resource ID number}
    myResID := UniqueID('snd ');
  UNTIL (myResID < kMinSysSndRes) OR (myResID > kMaxSysSndRes);

  MyGetSoundName(myResName);        {get name for sound resource}
                                      {add resource to file}
  AddResource(mySndHandle, 'snd ', myResID, myResName);
  myErr := ResError;
  IF myErr = noErr THEN
  BEGIN
    UpdateResFile(resFileRefNum);    {update resource file}
    myErr := ResError;
  END;
  IF myErr <> noErr THEN
    DoError(myErr);
END;
UseResFile(myPrevResFile);        {restore previous resource file}
END;

```

The `MyRecordSndResource` procedure defined in Listing 1-5 takes as a parameter the reference number of an open resource file to which you wish to record. The procedure makes that resource file the current resource file and, after recording, reverts to what was previously the active resource file. Note that you should not record to your application's resource fork, because applications that write to their own resource forks cannot be used by multiple users at once over a network. For more information on reference numbers for resource files, see the chapter "Resource Manager" in *Inside Macintosh: More Macintosh Toolbox*.

The `MyRecordSndResource` procedure first presents the sound recording dialog box by calling the `MyRecordThruDialog` procedure defined in Listing 1-4 on page 1-28. If that procedure returns a valid sound handle, `MyRecordSndResource` finds an acceptable resource ID for the resource file and then calls a procedure that returns a name for the resource (perhaps by presenting a dialog box that asks the user to name the sound). Finally, `MyRecordSndResource` adds the resource to the specified resource file and updates that file by calling the Resource Manager procedure `UpdateResFile`.

Recording a Sound File

To record a sound directly into a file, you can call the `SndRecordToFile` function, which works exactly like `SndRecord` except that you pass it the file reference number of an open file instead of a handle to some memory. When `SndRecordToFile` exits successfully, that file contains the recorded audio data in AIFF or AIFF-C format. You can then play the recorded sound by passing that file reference number to the `SndStartFilePlay` function. (See Listing 1-2 on page 1-26 for a sample function that uses the `SndStartFilePlay` function.) Listing 1-6 defines a procedure that records a sound into a file using `SndRecordToFile`.

Listing 1-6 Recording a sound file

```
PROCEDURE MyRecordSoundFile (myFileRefNum: Integer);
VAR
    myErr:      OSErr;
    myCorner:   Point;
BEGIN
    MyGetTopLeftCorner(myCorner);
    myErr := SndRecordToFile(NIL, myCorner, siBestQuality, myFileRefNum);
    IF (myErr <> noErr) AND (myErr <> userCanceledErr) THEN
        DoError(myErr);
    END;
```

The `SndRecordToFile` function records the sound in the file specified in its fourth parameter. You must open the file before calling the `MyRecordSoundFile` procedure, and you must close the file after calling it. For more information on creating, opening, and closing files, see the chapter “Introduction to File Management” in *Inside Macintosh: Files*.

Checking For Speech Capabilities

Because the Speech Manager is not available in all system software versions, your application should always check for speech capabilities before attempting to use them. Listing 1-7 defines a function that determines whether the Speech Manager is available.

Listing 1-7 Checking for speech generation capabilities

```
FUNCTION MyHasSpeech: Boolean;
VAR
    myFeature:   LongInt;      {feature being tested}
    myErr:      OSErr;
BEGIN
    myErr := Gestalt(gestaltSpeechAttr, myFeature);
```

Introduction to Sound on the Macintosh

```

IF myErr = noErr THEN           {test Speech Manager-present bit}
  MyHasSpeech := BTst(myFeature, gestaltSpeechMgrPresent)
ELSE
  MyHasSpeech := FALSE;       {no speech features available}
END;

```

The `MyHasSpeech` function defined in Listing 1-7 uses the `Gestalt` function to determine whether the Speech Manager is available. The `MyHasSpeech` function tests the `gestaltSpeechMgrPresent` bit and returns `TRUE` if and only if the Speech Manager is present. If the `Gestalt` function cannot obtain the desired information and returns a result code other than `noErr`, the `MyHasSpeech` function assumes that the Speech Manager is not available and therefore returns `FALSE`.

Generating Speech From a String

It is easy to have the Speech Manager generate speech from a string stored as a variable of type `Str255`. The `SpeakString` function takes one parameter, the string to be spoken. `SpeakString` automatically allocates a speech channel, uses that channel to produce speech, and then disposes of the speech channel when speaking is complete. Speech generation is asynchronous, but because `SpeakString` copies the string you pass it into an internal buffer, you are free to release the memory you allocated for the string as soon as `SpeakString` returns.

Listing 1-8 show how you can use the `SpeakString` function to convert a string stored in a resource of type `'STR#'` into speech.

Listing 1-8 Using `SpeakString` to generate speech from a string

```

PROCEDURE MySpeakStringResource (myStrListID: Integer; myIndex: Integer);
VAR
  myString:      Str255;           {the string to speak}
  myErr:         OSErr;
BEGIN
  GetIndString(myString, myStrListID, myIndex);   {load the string}
  myErr := SpeakString(myString);                 {start speaking}
  IF myErr <> noErr THEN
    DoError(myErr);
END;

```

The `MySpeakStringResource` procedure defined in Listing 1-8 takes as parameters the resource ID of the `'STR#'` resource containing the string and the index of the string within that resource. `MySpeakStringResource` passes these values to the `GetIndString` procedure, which loads the string from the resource file into memory. `MySpeakStringResource` then calls the `SpeakString` function to convert the string into speech; if an error occurs, it calls an application-defined error-handling procedure.

The speech that the `SpeakString` function generates is asynchronous; that is, control returns to your application before the function finishes speaking the string. If you would like to generate speech synchronously, you can use `SpeakString` in conjunction with the `SpeechBusy` function, which returns the number of active speech channels, including the speech channel created by the `SpeakString` function.

Listing 1-9 illustrates how you can use `SpeechBusy` and `SpeakString` to generate speech synchronously.

Listing 1-9 Generating speech synchronously

```
PROCEDURE MySpeakStringResourceSync (myStrListID: Integer; myIndex: Integer);
VAR
    activeChannels: Integer;           {number of active speech channels}
BEGIN
    activeChannels := SpeechBusy;      {find number of active channels}
    MySpeakStringResource(myStrListID, myIndex);    {speak the string}

    {Wait until channel is no longer processing speech.}
    REPEAT
    UNTIL SpeechBusy = activeChannels;
END;
```

The `MySpeakStringResourceSync` procedure defined in Listing 1-9 uses the `MySpeakStringResource` procedure defined in Listing 1-8 to speak a string. However, before calling `MySpeakStringResource`, `MySpeakStringResourceSync` calls the `SpeechBusy` function to determine how many speech channels are active. After the speech has begun, the `MySpeakStringResourceSync` function does not return until the number of speech channels active again falls to this level.

Note

Ordinarily, you should play speech asynchronously, to allow the user to perform other activities while speech is being generated. You might play speech synchronously if other activities performed by your application should not occur while speech is being generated. ♦

You can use the `SpeakString` function to stop speech being generated by a prior call to `SpeakString`. You might do this, for example, if the user switches to another application or closes a document associated with speech being generated. To stop speech, simply pass a zero-length string to the `SpeakString` function (or if you are programming in C, pass `NULL`).

Listing 1-10 shows how your application can stop speech generated by a call to the `SpeakString` function.

Listing 1-10 Stopping speech generated by `SpeakString`

```

PROCEDURE MyStopSpeech;
VAR
    myString:      Str255;          {an empty string}
    myErr:         OSErr;
BEGIN
    myString[0] := Char(0);        {set length of string to 0}
    myErr := SpeakString(myString); {stop previous speech}
    IF myErr <> noErr THEN
        DoError(myErr);
END;

```

The `MyStopSpeech` procedure defined in Listing 1-10 sets the length byte of a string to 0 before calling the `SpeakString` function. To execute this code in some development systems, you need to ensure that range checking is disabled. Consult your development system's documentation for details on enabling and disabling range checking.

Sound Reference

This section describes the routines used in this chapter to illustrate basic sound producing and recording operations. These are high-level routines that you can use to play and record sound resources and sound files, and to convert text to speech. The routines described in this section also appear in the appropriate reference sections of the other chapters in this book.

For a description of sound-related data structures and other sound-related routines, see the chapters “Sound Manager,” “Sound Input Manager,” and “Speech Manager” in this book. For a detailed description of the formats of sound resources and sound files, see the chapter “Sound Manager” in this book.

Routines

This section describes the high-level system software routines that you can use to play and record sound resources and sound files, or to convert a text string to spoken words. These routines belong to the Sound Manager.

Playing Sounds

You can use the `SysBeep` procedure to play the system alert sound, the `SndPlay` function to play the sound stored in any 'snd' resource, and the `SndStartFilePlay` function to play a sound file.

SysBeep

You can use the `SysBeep` procedure to play the system alert sound.

```
PROCEDURE SysBeep (duration: Integer);
```

`duration` The duration (in ticks) of the resulting sound. This parameter is ignored except on a Macintosh Plus, Macintosh SE, or Macintosh Classic when the system alert sound is the Simple Beep. The recommended duration is 30 ticks, which equals one-half second.

DESCRIPTION

The `SysBeep` procedure causes the Sound Manager to play the system alert sound at its current volume. If necessary, the Sound Manager loads into memory the sound resource containing the system alert sound and links it to a sound channel. The user selects a system alert sound in the Alert Sounds subpanel of the Sound control panel.

The volume of the sound produced depends on the current setting of the system alert sound volume, which the user can adjust in the Alert Sounds subpanel of the Sound control panel. The system alert sound volume can also be read and set by calling the `GetSysBeepVolume` and `SetSysBeepVolume` routines. If the volume is set to 0 (silent) and the system alert sound is enabled, calling `SysBeep` causes the menu bar to blink once.

SPECIAL CONSIDERATIONS

Because the `SysBeep` procedure moves memory, you should not call it at interrupt time.

SEE ALSO

For information on enabling and disabling the system alert sound or for information on reading and adjusting the system alert sound volume, see the chapter “Sound Manager” in this book.

SndPlay

You can use the `SndPlay` function to play a sound resource that your application has loaded into memory.

```
FUNCTION SndPlay (chan: SndChannelPtr; sndHdl: Handle;
                 async: Boolean): OSErr;
```

`chan` A pointer to a valid sound channel. You can pass `NIL` instead of a pointer to a sound channel if you want the Sound Manager to internally allocate a sound channel in your application’s heap zone.

<code>sndHdl</code>	A handle to the sound resource to play.
<code>async</code>	A Boolean value that indicates whether the sound should be played asynchronously (<code>TRUE</code>) or synchronously (<code>FALSE</code>). This parameter is ignored (and the sound plays synchronously) if <code>NIL</code> is passed in the first parameter.

DESCRIPTION

The `SndPlay` function attempts to play the sound located at `sndHdl`, which is expected to have the structure of a format 1 'snd' resource. If the resource has not yet been loaded, the `SndPlay` function fails and returns the `resProblem` result code. The handle you pass in the `sndHdl` parameter must be locked for as long as the sound is playing asynchronously.

The `chan` parameter is a pointer to a sound channel. If `chan` is not `NIL`, it is used as a valid channel. If `chan` is `NIL`, an internally allocated sound channel is used. Commands and data contained in the sound handle are then sent to the channel. Note that you can pass `SndPlay` a handle to some data created by calling the Sound Input Manager's `SndRecord` function as well as a handle to an actual 'snd' resource that you have loaded into memory.

SPECIAL CONSIDERATIONS

Because the `SndPlay` function moves memory, you should not call it at interrupt time.

RESULT CODES

<code>noErr</code>	0	No error
<code>notEnoughHardwareErr</code>	-201	Insufficient hardware available
<code>resProblem</code>	-204	Problem loading the resource
<code>badChannel</code>	-205	Channel is corrupt or unusable
<code>badFormat</code>	-206	Resource is corrupt or unusable

SEE ALSO

For an example of how to play a sound resource using the `SndPlay` function, see "Playing a Sound Resource" on page 1-25. For more information on the `SndPlay` function, see the chapter "Sound Manager" in this book.

SndStartFilePlay

You can call the `SndStartFilePlay` function to initiate a play from disk.

```
FUNCTION SndStartFilePlay (chan: SndChannelPtr; fRefNum: Integer;
                           resNum: Integer; bufferSize: LongInt;
                           theBuffer: Ptr;
```



```

theSelection: AudioSelectionPtr;
theCompletion: ProcPtr;
async: Boolean): OSErr;

```

<code>chan</code>	A pointer to a valid sound channel. You can pass <code>NIL</code> instead of a pointer to a sound channel if you want the Sound Manager to internally allocate a sound channel in your application's heap zone.
<code>fRefNum</code>	The file reference number of the AIFF or AIFF-C file to play. To play a sound resource rather than a sound file, this field should be 0.
<code>resNum</code>	The resource ID number of a sound resource to play. To play a sound file rather than a sound resource, this field should be 0.
<code>bufferSize</code>	The number of bytes of memory that the Sound Manager is to use for input buffering while reading in sound data. For <code>SndStartFilePlay</code> to execute successfully on the slowest Macintosh computers, use a buffer of at least 20,480 bytes. You can pass the value 0 to instruct the Sound Manager to allocate a buffer of the default size.
<code>theBuffer</code>	A pointer to a buffer that the Sound Manager should use for input buffering while reading in sound data. If this parameter is <code>NIL</code> , the Sound Manager allocates two buffers, each half the size of the value specified in the <code>bufferSize</code> parameter. If this parameter is not <code>NIL</code> , the buffer should be a nonrelocatable block of size <code>bufferSize</code> .
<code>theSelection</code>	A pointer to an audio selection record that specifies which portion of a sound should be played. You can pass <code>NIL</code> to specify that the Sound Manager should play the entire sound.
<code>theCompletion</code>	A pointer to a completion routine that the Sound Manager calls when the sound is finished playing. You can pass <code>NIL</code> to specify that the Sound Manager should not execute a completion routine. This field is useful only for asynchronous play.
<code>async</code>	A Boolean value that indicates whether the sound should be played asynchronously (<code>TRUE</code>) or synchronously (<code>FALSE</code>). You can play sound asynchronously only if you allocate your own sound channel (using <code>SndNewChannel</code>). If you pass <code>NIL</code> in the <code>chan</code> parameter and <code>TRUE</code> for this parameter, the <code>SndStartFilePlay</code> function returns the <code>badChannel</code> result code.

DESCRIPTION

The `SndStartFilePlay` function begins a continuous play from disk on a sound channel. The `chan` parameter is a pointer to the sound channel. If `chan` is not `NIL`, it is used as a valid channel. If `chan` is `NIL`, an internally allocated sound channel is used for play from disk. This internally allocated sound channel is not passed back to you. Because `SndPauseFilePlay` and `SndStopFilePlay` (described in the chapter "Sound Manager") require a sound-channel pointer, you must allocate your own channel if you wish to use those routines.

The sounds you wish to play can be stored either in a file or in an 'snd' resource. If you are playing a file, then `fRefNum` should be the file reference number of the file to be played and the parameter `resNum` should be set to 0. If you are playing an 'snd' resource, then `fRefNum` should be set to 0 and `resNum` should be the resource ID number (not the file reference number) of the resource to play.

SPECIAL CONSIDERATIONS

Because the `SndStartFilePlay` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndStartFilePlay` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0D000008</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>notEnoughHardwareErr</code>	-201	Insufficient hardware available
<code>queueFull</code>	-203	No room in the queue
<code>resProblem</code>	-204	Problem loading the resource
<code>badChannel</code>	-205	Channel is corrupt or unusable
<code>badFormat</code>	-206	Resource is corrupt or unusable
<code>notEnoughBufferSpace</code>	-207	Insufficient memory available
<code>badFileFormat</code>	-208	File is corrupt or unusable, or not AIFF or AIFF-C
<code>channelBusy</code>	-209	Channel is busy
<code>buffersTooSmall</code>	-210	Buffer is too small
<code>siInvalidCompression</code>	-223	Invalid compression type

SEE ALSO

For an example of how to play a sound file using the `SndStartFilePlay` function, see “Playing a Sound File” on page 1-26. For information on completion routines, see the chapter “Sound Manager” in this book.

Recording Sounds

The Sound Input Manager provides two high-level sound input routines, `SndRecord` and `SndRecordToFile`, for recording sound. These input routines are analogous to the two Sound Manager functions `SndPlay` and `SndStartFilePlay`. By using these high-level routines, you can be assured that your application presents a user interface that is consistent with that displayed by other applications recording sounds. Both `SndRecord` and `SndRecordToFile` attempt to record sound data from the sound input hardware currently selected in the Sound In control panel.

SndRecord

You can use the `SndRecord` function to record sound resources into memory.

```
FUNCTION SndRecord (filterProc: ProcPtr; corner: Point;
                   quality: OSType; VAR sndHandle: Handle):
    OSErr;
```

filterProc

A pointer to an event filter function that determines how user actions in the sound recording dialog box are filtered (similar to the `filterProc` parameter specified in a call to the `ModalDialog` procedure). By specifying your own filter function, you can override or add to the default actions of the items in the dialog box. If `filterProc` isn't `NIL`, `SndRecord` filters events by calling the function that `filterProc` points to.

`corner` The horizontal and vertical coordinates of the upper-left corner of the sound recording dialog box (in global coordinates).

`quality` The desired quality of the recorded sound.

`sndHandle` On entry, a handle to some storage space or `NIL`. On exit, a handle to a valid sound resource (or unchanged, if the call did not execute successfully).

DESCRIPTION

The `SndRecord` function records sound into memory. The recorded data has the structure of a format 1 'snd' resource and can later be played using the `SndPlay` function or can be stored as a resource. `SndRecord` displays a sound recording dialog box and is always called synchronously. Controls in the dialog box allow the user to start, stop, pause, and resume sound recording, as well as to play back the recorded sound. The dialog box also lists the remaining recording time and the current microphone sound level.

The `quality` parameter defines the desired quality of the recorded sound. Currently, three values are recognized for the `quality` parameter:

CONST

```
siBestQuality      = 'best';    {the best quality available}
siBetterQuality    = 'betr';    {a quality better than good}
siGoodQuality      = 'good';    {a good quality}
```

The precise meanings of these parameters are defined by the sound input device driver. For Apple-supplied drivers, this parameter determines whether the recorded sound is to be compressed, and if so, whether at a 6:1 or a 3:1 ratio. The quality `siBestQuality` does not compress the sound and provides the best quality output, but at the expense of increased memory use. The quality `siBetterQuality` is suitable for most nonvoice recording, and `siGoodQuality` is suitable for voice recording.

Introduction to Sound on the Macintosh

The `sndHandle` parameter is a handle to some storage space. If the handle is `NIL`, the Sound Input Manager allocates a handle of the largest amount of space that it can find in your application's heap and returns this handle in the `sndHandle` parameter. The Sound Input Manager resizes the handle when the user clicks the Save button in the sound recording dialog box. If the `sndHandle` parameter passed to `SndRecord` is not `NIL`, the Sound Input Manager simply stores the recorded data in the location specified by that handle.

SPECIAL CONSIDERATIONS

Because the `SndRecord` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndRecord` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$08040014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>userCanceledErr</code>	-128	User canceled the operation
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siUnknownQuality</code>	-232	Unknown quality

SEE ALSO

For an example of how to record a sound resource using the `SndRecord` function, see "Recording a Sound Resource" on page 1-28. See the chapter "Dialog Manager" in *Inside Macintosh: Macintosh Toolbox Essentials* for a complete description of event filter functions.

SndRecordToFile

You can use `SndRecordToFile` to record sound data into a file.

```
FUNCTION SndRecordToFile (filterProc: ProcPtr; corner: Point;
                          quality: OSType;
                          fRefNum: Integer): OSErr;
```

`filterProc`

A pointer to a function that determines how user actions in the sound recording dialog box are filtered.

`corner`

The horizontal and vertical coordinates of the upper-left corner of the sound recording dialog box (in global coordinates).

quality	The desired quality of the recorded sound. The values you can use for this parameter are described on page 1-39.
fRefNum	The file reference number of an open file to save the audio data in.

DESCRIPTION

The `SndRecordToFile` function works just like `SndRecord` except that it stores the sound input data into a file. The resulting file is in either AIFF or AIFF-C format and contains the information necessary to play the file by using the Sound Manager's `SndStartFilePlay` function. The `SndRecordToFile` function is always called synchronously.

Your application must open the file specified in the `fRefNum` parameter before calling the `SndRecordToFile` function. Your application must close the file sometime after calling `SndRecordToFile`.

SPECIAL CONSIDERATIONS

Because the `SndRecordToFile` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndRecordToFile` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$07080014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>userCanceledErr</code>	-128	User canceled the operation
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siUnknownQuality</code>	-232	Unknown quality

SEE ALSO

For an example of how to record a sound file using the `SndRecordToFile` function, see “Recording a Sound File” on page 1-31. See the chapter “Dialog Manager” in *Inside Macintosh: Macintosh Toolbox Essentials* for a complete description of event filter functions.

Generating and Stopping Speech

Your application can use the `SpeakString` function to generate speech or stop speech currently being generated by `SpeakString`. By calling the `SpeechBusy` function before and after a call to `SpeakString`, your application can determine when speaking is complete. These routines belong to the Speech Manager.

SpeakString

You can use the `SpeakString` function to have the Speech Manager read a text string.

```
FUNCTION SpeakString (s: Str255): OSErr;
```

`s` The string to be spoken.

DESCRIPTION

The `SpeakString` function attempts to speak the Pascal-style text string contained in the string `s`. Speech is produced asynchronously using the default system voice. When an application calls this function, the Speech Manager makes a copy of the passed string and creates any structures required to speak it. As soon as speaking has begun, control is returned to the application. The synthesized speech is generated asynchronously to the application so that normal processing can continue while the text is being spoken. No further interaction with the Speech Manager is required at this point, and the application is free to release the memory that the original string occupied.

If `SpeakString` is called while a prior string is still being spoken, the sound currently being synthesized is interrupted immediately. Conversion of the new text into speech is then begun. If you pass a zero-length string (or, in C, a null pointer) to `SpeakString`, the Speech Manager stops any speech previously being synthesized by `SpeakString` without generating additional speech. If your application uses `SpeakString`, it is often a good idea to stop any speech in progress whenever your application receives a suspend event. (Note, however, that calling `SpeakString` with a zero-length string has no effect on speech channels other than the one managed internally by the Speech Manager for the `SpeakString` function.)

The text passed to the `SpeakString` function may contain embedded speech commands, which are described in the chapter “Speech Manager” in this book.

SPECIAL CONSIDERATIONS

Because the `SpeakString` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeakString` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0220000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>memFullErr</code>	-108	Not enough memory to speak
<code>synthOpenFailed</code>	-241	Could not open another speech synthesizer channel

SEE ALSO

For an example of how to read a text string using the `SpeakString` function, see “Generating Speech From a String” on page 1-32. See the chapter “Dialog Manager” in *Inside Macintosh: Macintosh Toolbox Essentials* for a complete description of event filter functions.

SpeechBusy

You can use the `SpeechBusy` function to determine whether any channels of speech are currently synthesizing speech.

```
FUNCTION SpeechBusy: Integer;
```

DESCRIPTION

The `SpeechBusy` function returns the number of speech channels that are currently synthesizing speech in the application. This is useful when you want to ensure that an earlier speech request has been completed before having the system speak again. Note that paused speech channels are counted among those that are synthesizing speech.

The speech channel that the Speech Manager allocates internally in response to calls to the `SpeakString` function is counted in the number returned by `SpeechBusy`. Thus, if you use just `SpeakString` to initiate speech, `SpeechBusy` always returns 1 as long as speech is being produced. When `SpeechBusy` returns 0, all initiated speech has finished.

SPECIAL CONSIDERATIONS

You can call the `SpeechBusy` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeechBusy` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$003C000C</code>

Summary of Sound

Pascal Summary

Constants

CONST

```
{Gestalt sound attributes selector and response bits}
gestaltSoundAttr      = 'snd ' ; {sound attributes selector}
gestaltStereoCapability = 0;    {built-in hw can play stereo sounds}
gestaltStereoMixing   = 1;    {built-in hw mixes stereo to mono}
gestaltSoundIOMgrPresent = 3;  {sound input routines available}
gestaltBuiltInSoundInput = 4;  {built-in input hw available}
gestaltHasSoundInputDevice = 5; {sound input device available}
gestaltPlayAndRecord  = 6;    {built-in hw can play while recording}
gestalt16BitSoundIO   = 7;    {built-in hw can handle 16-bit data}
gestaltStereoInput    = 8;    {built-in hw can record stereo sounds}
gestaltLineLevelInput = 9;    {built-in input hw needs line level}
gestaltSndPlayDoubleBuffer = 10; {play from disk routines available}
gestaltMultiChannels  = 11;   {multiple channels of sound supported}
gestalt16BitAudioSupport = 12; {16-bit audio data supported}

{Gestalt selector and response bits for speech attributes}
gestaltSpeechAttr      = 'ttsc' ; {speech attributes selector}
gestaltSpeechMgrPresent = 0;    {Speech Manager is present}

{recording qualities}
siBestQuality          = 'best' ; {the best quality available}
siBetterQuality        = 'betr' ; {a quality better than good}
siGoodQuality          = 'good' ; {a good quality}
```

Routines

Playing Sounds

```
PROCEDURE SysBeep      (duration: Integer);
FUNCTION SndPlay      (chan: SndChannelPtr; sndHdl: Handle;
                      async: Boolean): OSErr;
```



```

FUNCTION SndStartFilePlay (chan: SndChannelPtr; fRefNum: Integer;
                           resNum: Integer; bufferSize: LongInt;
                           theBuffer: Ptr;
                           theSelection: AudioSelectionPtr;
                           theCompletion: ProcPtr; async: Boolean): OSErr;

```

Recording Sounds

```

FUNCTION SndRecord (filterProc: ProcPtr; corner: Point;
                   quality: OSType; VAR sndHandle: Handle): OSErr;

FUNCTION SndRecordToFile (filterProc: ProcPtr; corner: Point;
                          quality: OSType; fRefNum: Integer): OSErr;

```

Generating and Stopping Speech

```

FUNCTION SpeakString (s: Str255): OSErr;

FUNCTION SpeechBusy : Integer;

```

C Summary

Constants

```

/*Gestalt sound attributes selector and response bits*/
#define gestaltSoundAttr 'snd' /*sound attributes selector*/

enum {
    gestaltStereoCapability = 0, /*built-in hw can play stereo sounds*/
    gestaltStereoMixing = 1, /*built-in hw mixes stereo to mono*/
    gestaltSoundIOMgrPresent = 3, /*sound input routines available*/
    gestaltBuiltInSoundInput = 4, /*built-in input hw available*/
    gestaltHasSoundInputDevice = 5, /*sound input device available*/
    gestaltPlayAndRecord = 6, /*built-in hw can play while recording*/
    gestalt16BitSoundIO = 7, /*built-in hw can handle 16-bit data*/
    gestaltStereoInput = 8, /*built-in hw can record stereo sounds*/
    gestaltLineLevelInput = 9, /*built-in input hw needs line level*/
    gestaltSndPlayDoubleBuffer = 10, /*play from disk routines available*/
    gestaltMultiChannels = 11, /*multiple channels of sound supported*/
    gestalt16BitAudioSupport = 12 /*16-bit audio data supported*/
};

```

```

/*Gestalt selector and response bits for speech attributes*/
#define gestaltSpeechAttr  'ttsc'  /*speech attributes selector*/
enum {
    gestaltSpeechMgrPresent  = 0  /*Speech Manager is present*/
};

/*recording qualities*/
#define siBestQuality      'best'  /*the best quality available*/
#define siBetterQuality   'betr'  /*a quality better than good*/
#define siGoodQuality     'good'  /*a good quality*/

```

Routines

Playing Sounds

```

pascal void SysBeep          (short duration);
pascal OSErr SndPlay        (SndChannelPtr chan, Handle sndHdl,
                             Boolean async);
pascal OSErr SndStartFilePlay
                             (SndChannelPtr chan, short fRefNum,
                             short resNum, long bufferSize, void *theBuffer,
                             AudioSelectionPtr theSelection,
                             FilePlayCompletionProcPtr theCompletion,
                             Boolean async);

```

Recording Sounds

```

pascal OSErr SndRecord      (ModalFilterProcPtr filterProc, Point corner,
                             OSType quality, Handle *sndHandle);
pascal OSErr SndRecordToFile
                             (ModalFilterProcPtr filterProc, Point corner,
                             OSType quality, short fRefNum);

```

Generating and Stopping Speech

```

pascal OSErr SpeakString    (StringPtr s);
pascal short SpeechBusy    (void);

```

Result Codes

noErr	0	No error
userCanceledErr	-128	User canceled the operation
noHardwareErr	-200	Required sound hardware not available
notEnoughHardwareErr	-201	Insufficient hardware available
queueFull	-203	No room in the queue
resProblem	-204	Problem loading the resource
badChannel	-205	Channel is corrupt or unusable
badFormat	-206	Resource is corrupt or unusable
notEnoughBufferSpace	-207	Insufficient memory available
badFileFormat	-208	File is corrupt or unusable, or not AIFF or AIFF-C
channelBusy	-209	Channel is busy
buffersTooSmall	-210	Buffer is too small
siBadSoundInDevice	-221	Invalid sound input device
siInvalidCompression	-223	Invalid compression type
siUnknownQuality	-232	Unknown quality
synthOpenFailed	-241	Could not open another speech synthesizer channel

Sound Manager

Contents

About the Sound Manager	2-6
Sound Data	2-7
Square-Wave Data	2-7
Wave-Table Data	2-8
Sampled-Sound Data	2-9
Sound Commands	2-11
Sound Channels	2-13
Sound Compression and Expansion	2-14
Using the Sound Manager	2-17
Managing Sound Channels	2-19
Allocating Sound Channels	2-20
Initializing Sound Channels	2-22
Releasing Sound Channels	2-24
Manipulating a Sound That Is Playing	2-25
Stopping Sound Channels	2-28
Pausing and Restarting Sound Channels	2-29
Synchronizing Sound Channels	2-30
Managing Sound Volumes	2-31
Obtaining Sound-Related Information	2-32
Obtaining Information About Available Sound Features	2-33
Obtaining Version Information	2-34
Testing for Multichannel Sound and Play-From-Disk Capabilities	2-35
Obtaining Information About a Single Sound Channel	2-37
Obtaining Information About All Sound Channels	2-39
Determining and Changing the Status of the System Alert Sound	2-40
Playing Notes	2-41
Installing Voices Into Channels	2-43
Looping a Sound Indefinitely	2-45
Playing Sounds Asynchronously	2-46
Using Callback Procedures	2-47

Synchronizing Sound With Other Actions	2-51
Managing an Asynchronous Play From Disk	2-52
Playing Selections	2-53
Managing Multiple Sound Channels	2-53
Parsing Sound Resources and Sound Files	2-56
Obtaining a Pointer to a Sound Header	2-57
Playing Sounds Using Low-Level Routines	2-61
Finding a Chunk in a Sound File	2-62
Compressing and Expanding Sounds	2-66
Using Double Buffers	2-68
Setting Up Double Buffers	2-70
Writing a Doubleback Procedure	2-72
Sound Storage Formats	2-73
Sound Resources	2-74
The Format 1 Sound Resource	2-75
The Format 2 Sound Resource	2-80
Sound Files	2-81
Chunk Organization and Data Types	2-82
The Form Chunk	2-83
The Format Version Chunk	2-84
The Common Chunk	2-85
The Sound Data Chunk	2-87
Format of Entire Sound Files	2-87
Sound Manager Reference	2-89
Constants	2-89
Gestalt Selector and Response Bits	2-90
Channel Initialization Parameters	2-91
Sound Command Numbers	2-92
Chunk IDs	2-98
Data Structures	2-99
Sound Command Records	2-99
Audio Selection Records	2-100
Sound Channel Status Records	2-101
Sound Manager Status Records	2-102
Sound Channel Records	2-103
Sound Header Records	2-104
Extended Sound Header Records	2-106
Compressed Sound Header Records	2-108
Sound Double Buffer Header Records	2-111
Sound Double Buffer Records	2-112
Chunk Headers	2-113
Form Chunks	2-113
Format Version Chunks	2-114
Common Chunks	2-115
Extended Common Chunks	2-115
Sound Data Chunks	2-117
Version Records	2-118

Leftover Blocks	2-119
State Blocks	2-119
Sound Manager Routines	2-119
Playing Sound Resources	2-120
Playing From Disk	2-123
Allocating and Releasing Sound Channels	2-127
Sending Commands to a Sound Channel	2-130
Obtaining Information	2-132
Controlling Volume Levels	2-139
Compressing and Expanding Audio Data	2-142
Managing Double Buffers	2-147
Performing Unsigned Fixed-Point Arithmetic	2-148
Linking Modifiers to Sound Channels	2-149
Application-Defined Routines	2-151
Completion Routines	2-151
Callback Procedures	2-152
Doubleback Procedures	2-153
Resources	2-154
The Sound Resource	2-154
Summary of the Sound Manager	2-157
Pascal Summary	2-157
Constants	2-157
Data Types	2-161
Sound Manager Routines	2-168
Application-Defined Routines	2-170
C Summary	2-170
Constants	2-170
Data Types	2-175
Sound Manager Routines	2-182
Application-Defined Routines	2-184
Assembly-Language Summary	2-184
Data Structures	2-184
Trap Macros	2-188
Result Codes	2-188

Sound Manager

This chapter describes the Sound Manager, the part of the Macintosh system software that controls the production and manipulation of sounds on Macintosh computers. You can use the Sound Manager to create a wide variety of sounds and to manipulate sounds in many ways. The Sound Manager is also used by other parts of the Macintosh system software that produce sounds, such as the Speech Manager and QuickTime.

To use this chapter, you should already be familiar with the information in the chapter “Introduction to Sound on the Macintosh” earlier in this book, especially with the portions of that chapter that describe the Macintosh sound architecture and the routines related to sound output. That chapter shows how your application can play a sound resource or a sound file synchronously (that is, with other processing suspended while the sound plays).

You should read this chapter if you need a greater degree of control over sound output than the routines described in that introductory chapter provide. For example, if you want to play sounds asynchronously or to exercise very fine control over the process of sound production, this chapter contains information you need.

This chapter begins by describing the capabilities of the Sound Manager and the role of sound commands and sound channels in producing sound. Then it explains how you can use the Sound Manager to

- create and manage sound channels
- obtain information about available sound features and sound channels
- play notes and other sounds at various frequencies and volumes
- play one or more sounds asynchronously
- parse sound resources and sound files to obtain information about them
- compress and expand sound data
- use double buffers to bypass the normal play-from-disk routines

You’re not likely to use all of these capabilities in a single application. In general, you should read the section “About the Sound Manager” and then turn to the parts of the section “Using the Sound Manager” that describe the features you want to use in your application. The section “Sound Storage Formats” beginning on page 2-73 explains in detail the format of sound resources and sound files. You can find a complete reference to the Sound Manager data structures and routines in the section “Sound Manager Reference” beginning on page 2-89.


IMPORTANT

This chapter describes the capabilities and programming interfaces of version 3.0 of the Sound Manager. See the chapter “Introduction to Sound on the Macintosh” for some information on how version 3.0 differs from earlier versions. The capabilities and performance of version 3.0 are significantly better than those of all previous Sound Manager versions, even though their programming interfaces are largely identical. This chapter occasionally warns you about techniques or routines that cannot be used in versions prior to 3.0, but it does not provide an exhaustive comparison of all available versions. ▲

About the Sound Manager

The Sound Manager is a collection of routines that your application can use to create sound without a knowledge of or dependence on the actual sound-producing hardware available on any particular Macintosh computer. More generally, the Sound Manager is responsible for managing all sound production on Macintosh computers. Other parts of the Macintosh system software that need to create or modify sounds use the Sound Manager to do so. Figure 2-1 shows the position of the Sound Manager in relation to sound-producing applications and to other parts of the system software, such as the Speech Manager and QuickTime.

Figure 2-1 The position of the Sound Manager



The Sound Manager was first introduced in system software version 6.0 and has been significantly enhanced since that time. Prior to system software version 6.0, applications could create sounds using the Sound Driver.

IMPORTANT

To ensure compatibility across all models of Macintosh computers, you should always use the Sound Manager rather than the Sound Driver, which is no longer documented or supported by Apple Computer, Inc. The Sound Manager is simpler and much more powerful than the Sound Driver. Moreover, Sound Driver code might not work on some Macintosh computers. ▲

This section describes the three basic ways of defining sounds, namely using wave-table data, square-wave data, or sampled-sound data. Usually, you'll use sampled data to define the sounds you want to create, because sampled data provides the greatest flexibility and variety of sounds. You might use wave-table or square-wave data for very simple sounds. For instance, the Simple Beep alert sound is defined using square-wave data. Most other alert sounds are defined using sampled-sound data.

This section also describes sound commands and sound channels, which you need to know about to be able to do anything more complex than play sound resources or files synchronously using high-level Sound Manager routines.

Sound Data

The Sound Manager can play sounds defined using one of three kinds of sound data:

- square-wave data
- wave-table data
- sampled-sound data

This section provides a brief description of each of these kinds of audio data and introduces some of the concepts that are used in the remainder of this chapter. A complete description of the nature and format of audio data is beyond the scope of this book. There are, however, numerous books available that provide complete discussions of digital audio data.

Square-Wave Data

Square-wave data is the simplest kind of audio data supported by the Sound Manager. You can use square-wave data to generate a sound based on a square wave. Your application can use square-wave data to play a simple sequence of sounds in which each sound is described completely by three factors: its frequency or pitch, its amplitude (or volume), and its duration.

The **frequency** of a sound is the number of cycles per second (or hertz) of the sound wave. Usually, you specify a sound's frequency by a MIDI value. **MIDI note values** correspond to frequencies for musical notes, such as middle C, which is defined to have a MIDI value of 60, which on Macintosh computers is equivalent to 261.625 hertz.

Pitch is a listener's subjective interpretation of the sound's frequency. The terms *frequency* and *pitch* are used interchangeably in this chapter.

A sound's **duration** is the length of time a sound takes to play. In the Sound Manager, durations are usually specified in half-milliseconds.

Sound Manager

The **amplitude** of a sound is the loudness at which it is being played. Two sounds played at the same amplitude might not necessarily sound equally loud. For example, one sound could be played at a lower volume (which the user may set with the Sound control panel). Or, a sampled sound of a fleeting whisper might sound softer than a sampled sound of continuous gunfire, even if your application plays them at the same amplitude.

Note

Amplitude is traditionally considered to be the height of a sound wave, so that two sounds with the same amplitude would always sound equally loud. However, the Sound Manager considers amplitude to be the adjustment to be made to an existing sound wave. A sound played at maximum amplitude still might sound soft if the wave amplitude is small. ♦

A sound's **timbre** is its clarity. A sound with a low timbre is very clear; a sound with a high timbre is buzzing. Only sounds defined using square-wave data have timbres.


Wave-Table Data

To produce more complex sounds than are possible using square-wave data, your applications can use **wave-table data**. As the name indicates, wave-table data is based on a description of a single wave cycle. This cycle is called a wave table and is represented as an array of bytes that describe the timbre (or tone) of a sound at any point in the cycle.

Your application can use any number of bytes to represent the wave, but 512 is the recommended number because the Sound Manager resizes a wave table to 512 bytes if the table is not exactly that long. Your application can compute the wave table at run time or load it from a resource.

A **wave table** is a sequence of wave amplitudes measured at fixed intervals. For instance, a sine wave can be converted into a wave table by taking the value of the wave's amplitude at every $1/512$ interval of the wave (see Figure 2-2).

A wave table is represented as a packed array of bytes. Each byte contains a value in the range \$00-\$FF. These values are interpreted as offset values, where \$80 represents an amplitude of 0. The largest negative amplitude is \$00 and the largest positive amplitude is \$FF. When playing a wave-table description of a sound, the Sound Manager loops through the wave table for the duration of the sound.

Figure 2-2 A graph of a wave table

Sampled-Sound Data

You can use **sampled-sound data** to play back sounds that have been digitally recorded (that is, **sampled sounds**) as well as sounds that are computed, possibly at run time. Sampled sounds are the most widely used of all the available sound types primarily because it is relatively easy to generate a sampled sound and because sampled-sound data can describe a wide variety of sounds. Sampled sounds are typically used to play back prerecorded sounds such as speech or special sound effects.

You can use the Sound Manager to store sampled sounds in one of two ways, either as resources of type 'snd' or as AIFF or AIFF-C format files. The structure of resources of type 'snd' is given in "Sound Resources" on page 2-74, and the structure of AIFF and AIFF-C files is given in "Sound Files" on page 2-81. If you simply want to play short prerecorded sampled sounds, you should probably include the sound data in 'snd' resources. If you want to allow the user to transfer recorded sound data from one application to another (or from one operating system to another), you should probably store the sound data in an AIFF or AIFF-C file. In certain cases, you must store sampled sounds in files and not in resources. For example, a sampled sound might be too large to be stored in a resource.

Regardless of how you store a sampled sound, you can use Sound Manager routines to play that sound. If you choose to store sampled sounds in files of type AIFF or AIFF-C,

Sound Manager

you can play those sounds by calling the `SndStartFilePlay` function, introduced in the chapter “Introduction to Sound on the Macintosh” in this book. If you store sampled sounds in resources, your application can play those sounds by passing the Sound Manager function `SndPlay` a handle to a resource of type `'snd'` that contains a sampled sound header. (The `SndStartFilePlay` function can also play `'snd'` resources directly from disk, but this is not recommended.)

There are three types of sampled-sound headers: the standard sound header, the extended sound header, and the compressed sound header. The **sound header** contains information about the sample (such as the original sampling rate, the length of the sample, and so forth), together with an indication of where the sample data is to be found. The **sampled sound header** can reference only buffers of monophonic, 8-bit sound. The **extended sound header** can be used for 8- or 16-bit stereo sound data as well as monophonic sound data. The **compressed sound header** can be used to describe compressed sound data, whether monophonic or stereo. Data can be stored in a buffer separate from the sound resource or as part of the sound resource as the last field of the sound header.


Note

The terminology *sampled sound header* can be confusing because in most cases the sound header (and hence the `'snd'` resource) contains the sound data as well as information describing the data. Also, do not confuse sampled sound headers with sound resource headers. Sampled sound headers contain information about sampled-sound data, but sound resource headers contain information on the format of an entire sound resource. ♦

You can play a sampled sound at its original rate or play it at some other rate to change its pitch. Once you install a sampled sound header into a channel, you can play it at varying rates to provide a number of pitches. In this way, you can use a sampled sound as a **voice** or **instrument** to play a series of sounds.

Sampled-sound data is made up of a series of **sample frames**, which are stored contiguously in order of increasing time. For noncompressed sound data, each sample frame contains one or more sample points. For compressed sound data, each sample frame contains one or more packets.

For multichannel sounds, a sample frame is an interleaved set of sample points or packets. (For monophonic sounds, a sample frame is just a single sample point or a single packet.) The sample points within a sample frame are interleaved by channel number. For example, the sound data for a stereo, noncompressed sound is illustrated in Figure 2-3.

Figure 2-3 Interleaving stereo sample points

Each **sample point** of noncompressed sound data in a sample frame is, for sound files, a linear, two's complement value, and, for sound resources, a binary offset value. Sample points are from 1 to 32 bits wide. The size is usually 8 bits, but a different size can be specified in the `sampleSize` field of the extended sound header (for sound resources) or in the `sampleSize` field of the Common Chunk (for sound files). Each sample point is stored in an integral number of contiguous bytes. Sample points that are from 1 to 8 bits wide are stored in 1 byte, sample points that are from 9 to 16 bits wide are stored in 2 bytes, and so forth. When the width of a sample point is less than a multiple of 8 bits, the sample point data is left aligned (using a shift-left instruction), and the low-order bits at the right end are set to 0.

For example, for 8-bit noncompressed sound data stored in a sound resource, each sample point is similar to a value in a wave-table description. These values are interpreted as offset values, where \$80 represents an amplitude of 0. The value \$00 is the most negative amplitude, and \$FF is the largest positive amplitude.

Each **packet** of 3:1 compressed sound data is 2 bytes; a packet of 6:1 compressed sound is 1 byte. These byte sizes are defined in bits by the constants `threeToOnePacketSize` and `sixToOnePacketSize`, respectively.

Sound Commands

The Sound Manager provides routines that allow you to create and dispose of sound channels. These routines allow you to manipulate sound channels, but they do not directly produce any sounds. To actually produce sounds, you need to issue sound commands. A **sound command** is an instruction to produce sound, modify sound, or otherwise assist in the overall process of sound production. For example, the `ampCmd` sound command changes the amplitude (or volume) of a sound.

You can issue sound commands in several ways. You can send sound commands one at a time into a sound channel by repeatedly calling the `SndDoCommand` function. The commands are held in a queue and processed in a first-in, first-out order. Alternatively, you can bypass a sound queue altogether by calling the `SndDoImmediate` function. You can also issue sound commands by calling the function `SndPlay` and specifying a sound resource of type 'snd' that contains the sound commands you want to issue. A sound

Sound Manager

resource can contain any number of sound commands. As a result, you might be able to accomplish all sound-related activity simply by creating sound resources and calling `SndPlay` in your application. See “Sound Resources” on page 2-74 for details on the format of an ‘snd’ resource.

Generally speaking, no matter how sound commands are issued, they are all eventually sent to the Sound Manager, which interprets the commands and plays the sound on the available audio hardware. The Sound Manager provides a rich set of sound commands. The structure of a sound command is defined by the `SndCommand` data type:

```
TYPE SndCommand =
PACKED RECORD
    cmd:      Integer;    {command number}
    param1:   Integer;    {first parameter}
    param2:   LongInt;    {second parameter}
END;
```

Commands are always 8 bytes in length. The first 2 bytes are the command number, and the next 6 make up the command’s options. The format of the last 6 bytes depends on the command in use, although typically those 6 bytes are interpreted as an integer followed by a long integer. For example, an application can install a wave table into a sound channel by using `SndDoCommand` with a sound command whose `cmd` field is the `waveTableCmd` constant. In that case, the `param1` field specifies the length of the wave table, and the `param2` field is a pointer to the wave-table data itself. Other sound commands may interpret the 6 parameter bytes differently or may not use them at all.

The sound commands available to your application are defined by constants.

```
CONST
    nullCmd      = 0;      {do nothing}
    quietCmd     = 3;      {stop a sound that is playing}
    flushCmd     = 4;      {flush a sound channel}
    reInitCmd    = 5;      {reinitialize a sound channel}
    waitCmd      = 10;     {suspend processing in a channel}
    pauseCmd     = 11;     {pause processing in a channel}
    resumeCmd    = 12;     {resume processing in a channel}
    callBackCmd  = 13;     {execute a callback procedure}
    syncCmd      = 14;     {synchronize channels}
    availableCmd = 24;     {see if initialization options are supported}
    versionCmd   = 25;     {determine version}
    totalLoadCmd = 26;     {report total CPU load}
    loadCmd      = 27;     {report CPU load for a new channel}
    freqDurationCmd = 40;  {play a note for a duration}
    restCmd      = 41;     {rest a channel for a duration}
    freqCmd      = 42;     {change the pitch of a sound}
    ampCmd       = 43;     {change the amplitude of a sound}
    timbreCmd    = 44;     {change the timbre of a sound}
```


Sound Manager

<code>getAmpCmd</code>	<code>= 45;</code>	<code>{get the amplitude of a sound}</code>
<code>volumeCmd</code>	<code>= 46;</code>	<code>{set volume}</code>
<code>getVolumeCmd</code>	<code>= 47;</code>	<code>{get volume}</code>
<code>waveTableCmd</code>	<code>= 60;</code>	<code>{install a wave table as a voice}</code>
<code>soundCmd</code>	<code>= 80;</code>	<code>{install a sampled sound as a voice}</code>
<code>bufferCmd</code>	<code>= 81;</code>	<code>{play a sampled sound}</code>
<code>rateCmd</code>	<code>= 82;</code>	<code>{set the pitch of a sampled sound}</code>
<code>getRateCmd</code>	<code>= 85;</code>	<code>{get the pitch of a sampled sound}</code>

For details on individual sound commands, see the relevant sections in “Using the Sound Manager” beginning on page 2-17. Also see “Sound Command Numbers” beginning on page 2-92 for a complete summary of the available sound commands, their parameters, and their uses.

Sound Channels

A **sound channel** is a queue of sound commands that is managed by the Sound Manager, together with other information about the sounds to be played in that channel. The commands placed into the channel might originate from an application or from the Sound Manager itself. The commands in the queue are passed one by one, in a first-in, first-out (FIFO) manner, to the Sound Manager for interpretation and processing.

The Sound Manager uses the `SndChannel` data type to define a sound channel.

```

TYPE SndChannel =
PACKED RECORD
    nextChan:    SndChannelPtr; {pointer to next channel}
    firstMod:    Ptr;           {used internally}
    callBack:    ProcPtr;       {pointer to callback procedure}
    userInfo:    LongInt;       {free for application's use}
    wait:        LongInt;       {used internally}
    cmdInProgress: SndCommand; {used internally}
    flags:       Integer;       {used internally}
    qLength:     Integer;       {used internally}
    qHead:       Integer;       {used internally}
    qTail:       Integer;       {used internally}
    queue:       ARRAY[0..stdQLength-1] OF SndCommand;
END;
```

Most of the fields of the **sound channel record** are used internally by the Sound Manager, and you should not access or change them. However, your application is free to use the `userInfo` field to store any information that you wish to associate with a sound channel. For example, you might store a handle to an application-defined record that contains information about how your application is using the channel.

Some applications do not need to worry about creating or disposing of sound channels because the high-level Sound Manager routines take care of these automatically.

Sound Manager

However, if you wish to customize sound output or play sounds asynchronously, you must create your own sound channels (with the `SndNewChannel` function).

The enhanced Sound Manager included in system software versions 6.0.7 and later provides the ability to have multiple channels of sampled sound produce output on the Macintosh audio hardware concurrently. (Previous versions of the Sound Manager could play only a single channel of sampled sound at a time.) This allows a layering of sound that can bring a touch of reality to a simulation or presentation and permits applications to incorporate synthesized speech output with any other kind of Macintosh-generated sound. Sound Manager version 3.0 extended this capability to allow multiple channels of any kind of sound data to play simultaneously.

Your application can open several channels of sound for concurrent output on the available audio hardware. Similarly, multiple applications can each open channels of sound. The number and quality of concurrent channels of sound are limited only by the abilities of the machine, particularly by the speed of the CPU. Different Macintosh computers have different CPU clock speeds and execute instructions at quite different rates. This means that some machines can manage more channels of sound and produce higher-quality sound than other machines. For example, a Macintosh Quadra might be able to support several channels of high-quality stereo sound without significant impact on other processing, whereas a Macintosh Plus might be able to support only a single channel of monophonic sound before other processing slows significantly.

The Sound Manager currently supports multiple channels of sound only on machines equipped with an Apple Sound Chip or equivalent hardware. To maintain maximum compatibility between machines for your applications, you should always check the operating environment to make sure that the ability to play multiple channels of sampled sound is present before attempting to do so. A technique for determining whether your application can play multiple channels of sound is described in “Testing for Multichannel Sound and Play-From-Disk Capabilities” on page 2-35.

Sound Compression and Expansion

One minute of monophonic sound recorded with the fidelity you would expect from a commercial compact disc occupies about 5.3 MB of disk space. One minute of sound digitized by the current low-fidelity digitizing peripherals for Macintosh computers occupies more than 1 MB of disk space. Even one minute of telephone-quality speech takes up more than half of a megabyte on a disk. Despite the increased capacities of mass-storage devices, disk space can be a problem if your application incorporates large amounts of sampled sound. The space problem is particularly acute for multimedia applications. Because a large portion of the space occupied by a multimedia application is likely to be taken up by sound data, the complexity and richness of the application's sound component are limited.

To help remedy this problem, the Sound Manager includes a set of routines known collectively as **Macintosh Audio Compression and Expansion (MACE)**. MACE enables you to provide more audio information in a given amount of storage space by allowing you to compress sound data and then expand it for playback. These enhancements are based entirely in software and require no specialized hardware.

Sound Manager

The audio compression and expansion features allow you to enhance your application by including more audio data. MACE also relieves some distribution problems by reducing the number of disks required for shipping an application that relies heavily on sound. MACE has made some kinds of applications, such as talking dictionaries and foreign language-instruction software, more feasible than before.

MACE adds three main kinds of capabilities to those already present in the Sound Manager: audio data compression, real-time expansion and playback of compressed audio data, and buffered expansion and playback of compressed audio data.

- **Compression.** The Sound Manager can compress a buffer of digital audio data either in the original buffer or in a separate buffer. If a segment of audio data is too large to fit into a single buffer, your application can make repeated calls to the compression routine.
- **Real-time expansion playback.** The Sound Manager can expand compressed audio data contained in a small internal buffer and play it back at the same time. Because the audio data expansion and playback occur at the same time, there is more of a strain on the CPU when using this method of sound expansion rather than buffered expansion.
- **Buffered expansion.** The Sound Manager can expand a specified buffer of compressed audio data and store the result in a separate buffer. The expanded buffer can then be played back using other Sound Manager routines with minimal processor overhead during playback. Applications that require screen updates or user interaction during playback (such as animation or multimedia applications) should use buffered expansion.

MACE provides audio data compression and expansion capabilities in ratios of either 3:1 or 6:1 for all currently supported Macintosh models, from the Macintosh Plus forward. The principal tradeoff when using MACE is that the expanded audio data suffers a loss of fidelity in comparison to the original data. A small amount of noise is introduced into a 3:1 compressed sound when it is expanded and played back, and a greater amount of noise for the 6:1 ratio. The 3:1 buffer-to-buffer compression and expansion option is well suited for high-fidelity sounds. The 6:1 buffer-to-buffer compression and expansion option provides greater compression at the expense of lower-fidelity results and is recommended for voice data only. This technique reduces the frequency bandwidth of the audio signal by a factor of two to achieve the higher compression ratio.

MACE allows for the compression of both monophonic and stereo sounds. However, some Macintosh computer models (such as the Macintosh Plus and Macintosh SE) cannot expand stereo sounds.

Note

With Sound Manager versions prior to 3.0, some Macintosh computers play only the right channel of stereo 'snd' data through the internal speaker. Certain Macintosh II models can play only a single channel through the internal speaker. Sound Manager version 3.0 removes both of these limitations. ♦

Existing applications that use the Sound Manager's `SndPlay` function to play digitized audio signals can play compressed audio signals without modification or recompilation.

Sound Manager

The MACE routines assume that each original sample consists of 8-bit sound in binary offset format. The compression techniques do not, however, depend on a particular **sample rate** (the rate at which samples are recorded). Table 2-1 shows some common sample rates, expressed both as hertz and as unsigned fixed-point values.

Table 2-1 Sample rates

Rate (Hz)	Sample rate value (Fixed)
44100.00000	\$AC440000
22254.54545	\$56EE8BA3
22050.00000	\$56EE8BA3
11127.27273	\$2B7745D1
11025.00000	\$2B110000
7418.1818	\$1CFA2E8B
5563.6363	\$15BBA2E8

The Sound Manager defines constants for the most common sample rates:

```
CONST
    rate44khz      = $AC440000;    {44100.00000 in fixed-point}
    rate22khz      = $56EE8BA3;    {22254.54545 in fixed-point}
    rate22050hz    = $56220000;    {22050.00000 in fixed-point}
    rate11khz      = $2B7745D1;    {11127.27273 in fixed-point}
    rate11025hz    = $2B110000;    {11025.00000 in fixed-point}
```

The compression techniques produce their best quality output when the sample rate is the same as the output rate of the sound hardware of the machine playing the audio data. The output rate used in most current Macintosh computers is 22.254 kilohertz (hereafter referred to as the 22 kHz rate). Because of speed limitations, the Macintosh Plus and Macintosh SE cannot perform sample-rate conversion during expansion playback. On those machines, all sounds are played back at a 22 kHz rate. To provide consistent quality in sounds that might be played on different machines, you should record all sounds at a 22 kHz sample rate.

The MACE algorithms are optimized to provide the best sound quality possible through the internal speaker in real time. However, the user who employs high-quality speakers might notice a high-frequency hiss for some sounds compressed at the 3:1 ratio. This hiss results from a design tradeoff between maintaining real-time operation on the Macintosh Plus and preserving as much frequency bandwidth of the signal as possible. If you think that your output might be played on high-quality speakers, you might want to filter out the hiss before compression by passing the audio output through an equalizer that removes frequencies above 10 kHz. When you use the 6:1 compression and expansion ratio, your frequency response is cut in half. For example, when you use the 22 kHz

sample rate, the highest frequency possible would normally be 11 kHz; however, after compressing and expanding the data at the 6:1 ratio, the highest frequency you could get would be only 5.5 kHz.

Note

The Sound Manager uses compressions and decompression components (codecs) to handle the MACE capabilities. You can provide custom codecs to use other compression and decompression algorithms. See the chapter “Sound Components” in this book for information on developing audio codecs. ♦

Using the Sound Manager

The Sound Manager provides a wide variety of methods for creating sound and manipulating audio data on Macintosh computers. Usually, your application needs to use only a few of the many routines or sound commands that are available.

The Sound Manager routines can be divided into high-level routines and low-level routines. The high-level routines (like `SndPlay` and `SysBeep`) give you the ability to produce very complex audio output at very little programming expense. The majority of applications interact with the Sound Manager using these high-level routines, which allow you to play sounds without knowing anything about the structure of sound commands or sampled-sound data. You can let the high-level routines automatically allocate channels, or, for increased control, you can allocate your own sound channels.

Applications that have more sophisticated sound capabilities use the low-level routines (like `SndDoCommand` and `SndDoImmediate`) to send sound commands to sound channels. For example, your application might send a sound command to alter the amplitude of a sound that is playing (or is about to play).

Finally, a few very specialized applications use the Sound Manager’s low-level sound playback routines, which allow fine-tuning of the algorithms the Sound Manager uses to manage the double buffering of sound for its play-from-disk routines.

In general, you should use the highest-level routines capable of producing the kind of sound you want. Many applications can simply play sounds stored in resources or files and do not need to customize the sounds or continue with other processing while those sounds are playing. In such cases, you can use the high-level Sound Manager routines, as illustrated in the chapter “Introduction to Sound on the Macintosh” in this book. If, however, you need to be able to exercise very fine control over sound output or to play sounds asynchronously, you must manage your own sound channels. See “Managing Sound Channels” on page 2-19 to learn how you can use the Sound Manager to

- allocate and dispose of sound channels manually by using the `SndNewChannel` and `SndDisposeChannel` functions
- manipulate sound that is playing (for example, by sending the `ampCmd` command to a sound channel to change the amplitude of sound playing)

Sound Manager

- stop sounds and flush sound channels by using the `quietCmd` and `flushCmd` commands
- pause and restart sound channels by using the `pauseCmd` and `resumeCmd` commands
- synchronize sound channels by using the `syncCmd` command

As you've learned, the capabilities of the Sound Manager vary greatly from one Macintosh computer to another, depending on which version of the Sound Manager is available on a particular computer and on what audio hardware is available. To create sounds effectively on all computers, you might need to obtain information about the available sound features. "Obtaining Sound-Related Information" on page 2-32 explains how you can

- use the `Gestalt` function to determine which basic sound features are available
- find the version number of the available Sound Manager or of the MACE compression and expansion routines
- determine whether your application can take advantage of multichannel sound and the play-from-disk routines
- obtain information about a single sound channel

Some applications need to be able to play computer-generated tones at different pitches. In addition, some applications need to play waveforms or sampled sounds at different pitches. For example, if you are writing an application that converts musical notes to sound, you might record the sound of a violin playing middle C and then replay the sound at a variety of pitches to simulate a violinist's playing a concerto. The Sound Manager allows you to do this by allocating a sound channel and sending sound commands to it. "Playing Notes" on page 2-41 explains how you can

- play simple sequences of notes by using the `freqCmd` and `freqDurationCmd` commands
- install waveforms or sampled sounds into channels by using the `soundCmd` and `waveTableCmd` commands so that you can play them at different frequencies
- set a sound resource's loop points so that the sound repeats if a `freqCmd` or `freqDurationCmd` command lasts longer than the sound

Although some applications do not need to do other processing while sounds are playing, others do. If your application allocates sound channels itself, it can request that the Sound Manager play sounds asynchronously. By using callback procedures and completion routines, your application can arrange for a sound channel to be disposed when a sound finishes playing. "Playing Sounds Asynchronously" on page 2-46 explains how you can

- play a sound resource asynchronously by defining a callback procedure
- use callback procedures to synchronize sounds you play asynchronously with other actions
- play a sound file asynchronously and pause, restart, or stop such an asynchronous playback

Sound Manager

- manage multiple channels of sound to play more than one sound asynchronously at the same time

The high-level Sound Manager routines automatically parse sound resources and sound files to determine the information the Sound Manager needs to play the sounds contained in the resources and files. However, you might need to obtain information about sound resources or sound files for some other reason. Or, you might need to locate a certain part of a sound resource or sound file. For example, to use the `bufferCmd` sound command to play a buffer of sampled sound, you must obtain a pointer to the sound header contained in that buffer. See the section “Parsing Sound Resources and Sound Files” on page 2-56 for information on how to

- parse sound resources containing sampled-sound data to obtain information from the sampled-sound data’s sound header
- use the `bufferCmd` command to play sampled-sound data stored within a sound resource
- parse sound files to find a particular chunk and to extract the data from that chunk

High-level Sound Manager routines automatically expand sound data in real time when playing compressed sounds. However, you might need to manually compress or expand sound data at a time when you are not playing sounds. “Compressing and Expanding Sounds” on page 2-66 explains how you can use the Sound Manager’s built-in sound compression and expansion routines to compress or expand sounds.

The Sound Manager’s high-level play-from-disk routines use highly optimized algorithms to manage the double buffering of data so that the play from disk is continuous and without audible gaps. However, if you wish to bypass the high-level Sound Manager play-from-disk routines, you may define your own double-buffering routines. This might be useful if you need to change the sound data on disk before the Sound Manager can process it. The section “Using Double Buffers” on page 2-68 explains how you can set up your own double buffers and use a `doubleback` procedure to bypass the normal play-from-disk routines.

Managing Sound Channels

To use most of the low-level Sound Manager routines, you must specify a sound channel that maintains a queue of commands. Also, to take advantage of the full capabilities of the high-level Sound Manager routines, including asynchronous sound play, you must allocate your own sound channels. This section explains how your application can allocate, dispose of, and use its own sound channels.

This section first describes how you can allocate and dispose of sound channels. Then it explains how you can manipulate sounds playing in sound channels, stop sounds playing in sound channels, and pause and restart the execution of sounds in sound channels.

Allocating Sound Channels

Usually, you do not need to worry about allocating memory for sound channels because the `SndNewChannel` function automatically allocates a sound channel record in the application's heap if passed a pointer to a `NIL` sound channel. `SndNewChannel` also internally allocates memory for the sound channel's queue of sound commands. For example, the following lines of code request that the Sound Manager open a new sound channel for playing sampled sounds:

```
mySndChan := NIL;
myErr := SndNewChannel(mySndChan, sampledSynth, 0, NIL);
```

If you are concerned with managing memory yourself, you can allocate your own memory for a sound channel record and pass the address of that memory as the first parameter to `SndNewChannel`. By allocating a sound channel record manually, you not only obtain control over the allocation of the sound channel record, but you can specify the size of the queue of sound commands that the Sound Manager internally allocates. Listing 2-1 illustrates one way to do this.

Listing 2-1 Creating a sound channel

```
FUNCTION MyCreateSndChannel (synth: Integer; initOptions: LongInt;
                           userRoutine: ProcPtr;
                           queueLength: Integer): SndChannelPtr;
VAR
  mySndChan: SndChannelPtr;    {pointer to a sound channel}
  myErr:     OSErr;
BEGIN
  {Allocate memory for sound channel.}
  mySndChan := SndChannelPtr(NewPtr(Sizeof(SndChannel)));
  IF mySndChan <> NIL THEN
    BEGIN
      mySndChan^.qLength := queueLength; {set number of commands in queue}
      {Create a new sound channel.}
      myErr := SndNewChannel(mySndChan, synth, initOptions, userRoutine);
      IF myErr <> noErr THEN
        BEGIN
          {couldn't allocate channel}
          DisposePtr(Ptr(mySndChan)); {free memory already allocated}
          mySndChan := NIL;          {return NIL}
        END
      ELSE
        mySndChan^.userInfo := 0;    {reset userInfo field}
      END;
      MyCreateSndChannel := mySndChan; {return new sound channel}
    END;
END;
```


Sound Manager

The `MyCreateSndChannel` function defined in Listing 2-1 first allocates memory for a sound channel record and then calls the `SndNewChannel` function to attempt to allocate a channel. Note that `MyCreateSndChannel` checks the result code returned by `SndNewChannel` to determine whether the function was able to allocate a channel. The `SndNewChannel` function might not be able to allocate a channel if there are so many channels open that allocating another would put too much strain on the CPU. Also, `SndNewChannel` might fail if memory is low. (In addition to the memory for a sound channel record that is passed in the first parameter to `SndNewChannel`, the function must internally allocate memory in which to store sound commands.)

If you allocate memory for a sound channel record, you should specify the size of the queue of sound commands by assigning a value to the `qLength` field of the sound channel record you allocate. You can use the constant `stdQLength` to obtain a standard queue of 128 sound commands, or you can provide a value of your own.

```
CONST
    stdQLength          = 128;    {default size of a sound channel}
```

If you know that your application will play only resources containing sampled sound, you might set the `qLength` field to a considerably lower value, because resources created with the `SndRecord` function (described in the chapter “Introduction to Sound on the Macintosh” in this book) contain only one sound command, the `bufferCmd` command, which specifies that a buffer of sound should be played. For example, if your application uses a sound channel only to play a single sampled sound asynchronously, you can set `qLength` to 2, to allow for the `bufferCmd` command and a `callbackCmd` command that your application issues manually, as described in “Playing Sounds Asynchronously” on page 2-46. By using a smaller than standard queue length, your application can conserve memory.

Note

The number of sound commands in a channel should be an integer greater than 0. If you open a channel with a 0-length queue, most of the Sound Manager routines will return a `badChannel` result code. ♦

IMPORTANT

In general, however, you should let the Sound Manager allocate sound channel records for you. The amount of memory you might save by allocating your own is usually negligible. ▲

The second parameter in the `SndNewChannel` function specifies the kind of data you want to play on that channel. You can specify one of the following constants:

```
CONST
    squareWaveSynth    = 1;      {square-wave data}
    waveTableSynth     = 3;      {wave-table data}
    sampledSynth       = 5;      {sampled-sound data}
```

In some versions of system software prior to system software version 7.0 (including system software version 6.0.7), high-level Sound Manager routines do not work properly

Sound Manager

with sound resources that specify the sound data type twice. This might happen if a resource specifies that a sound consists of sampled-sound data and an application does the same when creating a sound channel. This might also happen if an application uses the same sound channel to play several sound resources that contain different kinds of sound data. There are several solutions to this problem that you can use if you must maintain compatibility with old versions of system software:

- If your application plays only sampled-sound resources, then you need only ensure that none of the sound resources specifies that it contains sampled-sound data. Then, when you create a sound channel, pass `sampledSynth` as the second parameter to `SndNewChannel` so that the Sound Manager interprets the data in the sound resources correctly. Do not use the `SndPlay` routine.
- If your application must be able to play sampled-sound resources as well as resources that contain square-wave or wave-table data, ensure that all sound resources that your application uses specify their data type. (Sound resources created with the Sound Input Manager automatically specify that they contain sampled-sound data.) Then, when creating a channel in which you plan to play a sound resource, pass 0 as the second parameter to `SndNewChannel`, and then use the channel to play no more than one sound resource.
- If you do not wish to modify your application's sound resources, and your application plays only sampled-sound resources, then you can play sounds with low-level Sound Manager routines, a technique described in "Playing Sounds Using Low-Level Routines" on page 2-61.

Note that this problem does not occur with sound files, because sound files always contain sampled-sound data and thus do not explicitly declare their data type. As a result, when creating a channel in which you plan to play a sound file, pass `sampledSynth` as the second parameter to `SndNewChannel`.

The third parameter in the `SndNewChannel` function specifies the initialization parameters to be associated with the new channel. These are discussed in the following section. The fourth parameter in the `SndNewChannel` function is a pointer to a callback procedure. If your application produces sounds asynchronously or needs to be alerted when a command has completed, you can specify a callback procedure by passing the address of that procedure in the fourth parameter and then by installing a callback procedure into the sound channel. If you pass `NIL` as the fourth parameter, then no callback procedure is associated with the channel. See "Playing Sounds Asynchronously" on page 2-46 for more information on setting up and using callback procedures.

Initializing Sound Channels

When you first create a sound channel with `SndNewChannel`, you can request that the channel have certain characteristics as specified by a sound channel initialization parameter. For example, to indicate that you want to allocate a channel capable of producing stereo sound, you might use the following code:

```
myErr := SndNewChannel(mySndChan, sampledSynth, initStereo, NIL);
```

Sound Manager

These are the currently recognized constants for the sound channel initialization parameter.

```
CONST
    initChanLeft      = $0002;    {left stereo channel}
    initChanRight     = $0003;    {right stereo channel}
    waveInitChannel0  = $0004;    {wave-table channel 0}
    waveInitChannel1  = $0005;    {wave-table channel 1}
    waveInitChannel2  = $0006;    {wave-table channel 2}
    waveInitChannel3  = $0007;    {wave-table channel 3}
    initMono          = $0080;    {monophonic channel}
    initStereo        = $00C0;    {stereo channel}
    initMACE3         = $0300;    {3:1 compression}
    initMACE6         = $0400;    {6:1 compression}
    initNoInterp      = $0004;    {no linear interpolation}
    initNoDrop        = $0008;    {no drop-sample conversion}
```

See “Channel Initialization Parameters” beginning on page 2-91 for a complete description of these constants.

Note

Some Macintosh computers play *only* the left channel of stereo sounds out the internal speaker. Other machines (for example, the Macintosh SE/30 and Macintosh IIsx) mix both channels together before sending a signal to the internal speaker. You can use the `Gestalt` function to determine if a particular machine mixes both left and right channels to the internal speaker. All Macintosh computers except the Macintosh SE and the Macintosh Plus, however, play stereo signals out the headphone jack. ♦

The initialization parameters are additive. To initialize a channel for stereo sound with no linear interpolation, simply pass an initialization parameter that is the sum of the desired characteristics, as follows:

```
myErr := SndNewChannel(mySndChan, sampledSynth,
                      initStereo+initNoInterp, NIL);
```

A call to `SndNewChannel` is really only a request that the Sound Manager open a channel having the desired characteristics. It is possible that the parameters requested are not available. In that case, `SndNewChannel` returns a `notEnoughHardwareErr` error. In general, you should pass 0 as the third parameter to `SndNewChannel` unless you know exactly what kind of sound is to be played.

You can alter certain initialization parameters, even while a channel is actively playing a sound, by issuing the `reInitCmd` command. For example, you can change the output channel from left to right, as shown in Listing 2-2.

Listing 2-2 Reinitializing a sound channel

```

VAR
    mySndCmd:          SndCommand;
    mySndChan:         SndChannelPtr;
    myErr:             OSErr;
    .
    .
    .
mySndCmd.cmd := reInitCmd;
mySndCmd.param1 := 0;                               {unused}
mySndCmd.param2 := initChanRight;                   {new init parameter}
myErr := SndDoImmediate(mySndChan, mySndCmd);

```

The `reInitCmd` command accepts the `initNoInterp` constant to toggle **linear interpolation** on and off; it should be used with noncompressed sounds only. If a noncompressed sound is playing when you send a `reInitCmd` command with this constant, linear interpolation begins immediately. You can also pass `initMono`, `initChanLeft`, or `initChanRight` to pan to both channels, to the left channel, or to the right channel. This affects only monophonic sounds. The Sound Manager remembers the settings you pass and applies them to all further sounds played on that channel.

Releasing Sound Channels

To dispose of a sound channel that you have allocated with `SndNewChannel`, use the `SndDisposeChannel` function. `SndDisposeChannel` requires two parameters, a pointer to the channel that is to be disposed and a Boolean value that indicates whether the channel should be flushed before disposal. Here's an example:

```
myErr := SndDisposeChannel(mySndChan, TRUE);
```

Because the second parameter is `TRUE`, the Sound Manager sends both a `flushCmd` command and a `quietCmd` command to the sound channel (using `SndDoImmediate`). This removes all commands from the sound channel and stops any sound already in progress. Then the Sound Manager disposes of the channel.

If the second parameter is `FALSE`, the Sound Manager simply queues a `quietCmd` command (using `SndDoCommand`) and waits until `quietCmd` is received by the channel before disposing of the channel. In this case, the `SndDisposeChannel` function does not return until the channel has finished processing commands and the queue is empty.

▲ **WARNING**

If you dispose of a channel currently playing from disk, then your completion routine will still execute, but will receive a pointer to a sound channel that no longer exists. Thus, you should stop a play from disk before disposing of a channel. See “Managing an Asynchronous Play From Disk” on page 2-52 for more information on completion routines. ▲

Although the `SndDisposeChannel` function always releases memory reserved for sound commands, `SndDisposeChannel` cannot release memory associated with a sound channel record if you have allocated that memory yourself. For example, if you use the `MyCreateSndChannel` function defined in Listing 2-1 to create a sound channel, you must dispose first of the sound channel and then of the memory occupied by the sound channel record, as illustrated in Listing 2-3.

Listing 2-3 Disposing of memory associated with a sound channel

```
FUNCTION MyDisposeSndChannel (sndChan: SndChannelPtr; quietNow: Boolean):
                                OSErr;

VAR
    myErr:    OSErr;
BEGIN
    myErr := SndDisposeChannel(sndChan, quietNow); {dispose of channel}
    DisposePtr(Ptr(sndChan));                    {dispose of channel ptr}
    MyDisposeSndChannel := myErr;
END;
```

If you have played a sound resource through a channel, the `SndDisposeChannel` function does not free the memory taken by the resource. You must call the Resource Manager's `ReleaseResource` function to do so, or, if you have detached a resource from a resource file, you could free the memory by making the handle unlocked and purgeable. Note that if you play a sound resource asynchronously, you should not release the memory occupied by the resource until the sound finishes playing or the sound might not play properly. For information on releasing a sound resource after playing a sound asynchronously, see "Playing Sounds Asynchronously" on page 2-46.

IMPORTANT

In Sound Manager versions 3.0 and later, you can play sounds in any number of sound channels. In earlier Sound Manager versions, however, only one kind of sound can be played at one time. This results in several important restrictions on your application. In Sound Manager version 2 and earlier, you should create sound channels just before playing sounds. Once the sound is completed, you should dispose of the channel. If your application is switched out and does not release a sound channel, then other applications may be unable to open sound channels. In particular, the system alert sound might not be heard and the user might not be notified of important system occurrences. In general, while it is acceptable to issue a number of sound commands to the same sound channel, it's not a good idea to play more than one sampled sound on the same sound channel. ▲

Manipulating a Sound That Is Playing

The Sound Manager provides a number of sound commands that you can use to change some of the characteristics of sounds that are currently playing. For example, you can

Sound Manager

alter the rate at which a sampled sound is played back, thereby lowering or increasing the pitch of the sound. You can also pause or stop a sound that is currently in progress. See “Pausing and Restarting Sound Channels” on page 2-29 for information on how to pause the processing of a sound channel.

You can use the `getRateCmd` command to determine the rate at which a sampled sound is currently playing. If `SndDoImmediate` returns `noErr` when you pass `getRateCmd`, the current sample rate of the channel is returned as a `Fixed` value in the location that is pointed to by `param2` of the sound command. (As usual, the high bit of that value returned is not interpreted as a sign bit.) Values that specify sampling rates are always interpreted relative to the 22 kHz rate. That is, the `Fixed` value `$00010000` indicates a rate of 22 kHz. The value `$00020000` indicates a rate of 44 kHz. The value `$00008000` indicates a rate of 11 kHz.

To modify the pitch of a sampled sound currently playing, use the `rateCmd` command. The current pitch is set to the rate specified in the `param2` field of the sound command. Listing 2-4 illustrates how to halve the frequency of a sampled sound that is already playing. Note that sending the `rateCmd` command before a sound plays has no effect.

Listing 2-4 Halving the frequency of a sampled sound

```
FUNCTION MyHalveFreq (mySndChan: SndChannelPtr): OSErr;
VAR
    myRate:      LongInt;          {rate of sound play}
    mySndCmd:    SndCommand;      {a sound command}
    myErr:       OSErr;
BEGIN
    {Get the rate of the sample currently playing.}
    mySndCmd.cmd := getRateCmd;   {the command is getRateCmd}
    mySndCmd.param1 := 0;        {unused}
    mySndCmd.param2 := LongInt(@myRate);
    myErr := SndDoImmediate(mySndChan, mySndCmd);

    IF myErr = noErr THEN
    BEGIN
        {Halve the sample rate.}
        mySndCmd.cmd := rateCmd;  {the command is rateCmd}
        mySndCmd.param1 := 0;    {unused}
        mySndCmd.param2 := FixDiv(myRate, $00020000);
        myErr := SndDoImmediate(mySndChan, mySndCmd);
    END;
    MyHalveFreq := myErr;
END;
```

When you halve the frequency of a sampled sound using the technique in Listing 2-4, the sound will play one octave lower than before. In addition, the sound will play twice as

Sound Manager

slowly as before. Likewise, if you use the `rateCmd` command to double the frequency of a sound, it plays one octave higher and twice as fast. Using `rateCmd` in this way is like pressing the fast forward button on a tape player while the play button remains depressed.

You can also use `rateCmd` and `getRateCmd` to pause a sampled sound that is currently playing. To do this, read the rate at which it is playing, issue a `rateCmd` command with a rate of 0, and then issue a `rateCmd` command with the previous rate when you want the sound to resume playing.

To change the amplitude (or loudness) of the sound in progress, issue the `ampCmd` command. (See Listing 2-5 for an example.) If no sound is currently playing, `ampCmd` sets the amplitude of the next sound. Specify the desired new amplitude in the `param1` field of the sound command as a value in the range 0 to 255.

Listing 2-5 Changing the amplitude of a sound channel

```
PROCEDURE MySetAmplitude (chan: SndChannelPtr; myAmp: Integer);
VAR
    mySndCmd:    SndCommand;    {a sound command}
    myErr:       OSErr;
BEGIN
    IF chan <> NIL THEN
        BEGIN
            WITH mySndCmd DO
                BEGIN
                    cmd := ampCmd;           {the command is ampCmd}
                    param1 := myAmp;       {desired amplitude}
                    param2 := 0;           {ignored}
                END;
                myErr := SndDoImmediate(chan, mySndCmd);
                IF myErr <> noErr THEN
                    DoError(myErr);
                END;
            END;
        END;
    END;
```

If your application has an option that allows users to turn off sound output, you could call the `MySetAmplitude` procedure on all open channels to set the amplitude of all channels to 0. Note that the Sound control panel allows the user to adjust the sound from 0 (softest) to 7 (loudest). This value is independent of the values used for amplitudes of sounds playing in channels, and the Sound Manager uses the Sound control panel value jointly with the amplitude of a sound channel to determine how loudly to play a sound. Sounds with low frequencies sound softer than sounds with high frequencies even if the sounds play at the same amplitude. If the amplitude of a sound is 0, the sound hardware produces no sound; however, when the value set in the Sound control panel is 0, sound might still play, depending on the amplitude.

Sound Manager

You can use the `getAmpCmd` command to determine the current amplitude of a sound in progress. The `getAmpCmd` command is similar to `getRateCmd`, except that the value returned is an integer. The value returned in `param2` is in the range 0–255. Listing 2-6 shows an example:

Listing 2-6 Getting the amplitude of a sound in progress

```
VAR
    myAmp: Integer;
BEGIN
    mySndCmd.cmd := getAmpCmd;
    mySndCmd.param1 := 0;                               {unused}
    mySndCmd.param2 := LongInt(@myAmp);
    myErr := SndDoImmediate(mySndChan, mySndCmd);
END;
```

To modify the timbre of a sound defined using by square-wave data, use the `timbreCmd` command. A sine wave is specified as 0 in `param1` and produces a very clear sound. A value of 254 in `param1` represents a modified square wave and produces a buzzing sound. To avoid a bug in some versions of the Sound Manager, you should not use the value 255. You should change the timbre before playing the sound.

Stopping Sound Channels

The Sound Manager allows you both to stop a sound currently in progress in a channel and to remove all pending sound commands from a channel.

Note

If you have started a sound playing by using the `SndStartFilePlay` function, then you can stop play by using the `SndStopFilePlay` function. See “Managing an Asynchronous Play From Disk” on page 2-52 for more details. ♦

To cause the Sound Manager to stop playing the sound in progress, send the `quietCmd` command. Here’s an example:

```
mySndCmd.cmd := quietCmd;                               {the command is quietCmd}
mySndCmd.param1 := 0;                                   {unused}
mySndCmd.param2 := 0;                                   {unused}

{stop the sound now playing}
myErr := SndDoImmediate(mySndChan, mySndCmd, FALSE);
```

To bypass the command queue, you should issue `quietCmd` by using `SndDoImmediate`. Any sound commands that are already in the sound channel remain there, however, and further sound commands can be queued in that channel.

Sound Manager

If you wish to flush a sound channel without disturbing any sounds already in progress, issue the `flushCmd` command. Here's an example:

```
mySndCmd.cmd := flushCmd;           {the command is flushCmd}
mySndCmd.param1 := 0;               {unused}
mySndCmd.param2 := 0;               {unused}

{flush the channel}
myErr := SndDoImmediate(mySndChan, mySndCmd, FALSE);
```

If you want to stop all sound production by a particular sound channel immediately, you should issue a `flushCmd` command and then a `quietCmd` command. If you issue only a `flushCmd` command, the sound currently playing is not stopped. If you issue only a `quietCmd` command, the Sound Manager stops the current sound but continues with any other queued commands. (By calling `flushCmd` before `quietCmd`, you ensure that no other queued commands are processed.)

Note

The Sound Manager sends a `quietCmd` command when your application calls the `SndDisposeChannel` function. The `quietCmd` command is preceded by a `flushCmd` command if the `quietNow` parameter is `TRUE`. ♦

Pausing and Restarting Sound Channels

If you want to pause command processing in a particular channel, you can use either of two sound commands, `waitCmd` or `pauseCmd`.

Note

If you have started a sound playing by using the `SndStartFilePlay` function, then you can pause and resume play by using the `SndPauseFilePlay` function. See “Managing an Asynchronous Play From Disk” on page 2-52 for more details. ♦

The `waitCmd` command suspends all processing in a channel for a specified number of half-milliseconds. Here's an example:

```
mySndCmd.cmd := waitCmd;           {the command is waitCmd}
mySndCmd.param1 := 2000;           {1-second wait duration}
mySndCmd.param2 := 0;              {unused}

{pause the channel}
myErr := SndDoImmediate(mySndChan, mySndCmd, FALSE);
```

To pause the processing of commands in a sound channel for an unspecified duration, use the `pauseCmd` command. Unlike `waitCmd`, `pauseCmd` suspends processing for an undetermined amount of time. Processing does not resume until the Sound Manager receives a `resumeCmd` command for the specified channel.

Sound Manager

To issue `waitCmd` or `pauseCmd`, you can use either `SndDoImmediate` or `SndDoCommand`, depending on whether you want the suspension of sound channel processing to begin immediately or when the Sound Manager reaches that command in the normal course of reading commands from a sound channel. The `resumeCmd` command, which is simply the opposite of `pauseCmd`, should be issued by using `SndDoImmediate`. Neither `waitCmd` nor `pauseCmd` stops any sound that is currently playing; these commands simply stop further processing of commands queued in the sound channel.

Note

If no other commands are pending in the sound channel after a `resumeCmd` command, the Sound Manager sends an `emptyCmd` command. The `emptyCmd` command is sent only by the Sound Manager and should not be issued by your application. ♦

Synchronizing Sound Channels

You can synchronize several different sound channels by issuing `syncCmd` commands. The `param1` field of the sound command contains a count, and the `param2` field contains an arbitrary identifier. The Sound Manager keeps track of the count for each channel being synchronized. When the Sound Manager receives a `syncCmd` command for a certain channel, it decrements the count for each channel having the given identifier, including the newly synchronized channel. Command processing resumes on a channel when the count becomes 0. Thus, if you know how many channels you need to synchronize, you can synchronize them all by arranging for all of their counts to become zero simultaneously. Listing 2-7 illustrates the use of the `syncCmd` command.

Listing 2-7 Adding a channel to a group of channels to be synchronized

```
PROCEDURE MySync1Chan (chan: SndChannelPtr; count: Integer;
                      identifier: LongInt);

VAR
    mySndCmd: SndCommand;      {a sound command}
    myErr: OSErr;

BEGIN
    WITH mySndCmd DO
        BEGIN
            cmd := syncCmd;      {the command is syncCmd}
            param1 := count;
            param2 := identifier; {ID of group to be synchronized}
        END;
        myErr := SndDoImmediate(chan, mySndCmd);
        IF myErr <> noErr THEN
            DoError(myErr);
    END;
```

Sound Manager

For example, to synchronize three channels, first create the channels and then call the `MySync1Chan` procedure defined in Listing 2-7 for the first channel with a count equal to 4, for the second channel with a count equal to 3, and for the third channel with a count equal to 2, using the same arbitrary identifier for each call to `MySync1Chan`. Then fill all channels with appropriate sound commands. (For example, you might send commands that will cause the same sequence of notes to be produced on all three synchronized channels.) Finally, call the `MySync1Chan` procedure one final time, passing any of the three channels and a count of 1. By that time, all of the other channels will have counts of 1, and all counts will become 0 simultaneously, thus initiating synchronized play.

Note

The `syncCmd` command is intended to make it easy to synchronize sound channels. You can use the `syncCmd` command to start multiple channels of sampled sound playing simultaneously, but if you require precise synchronization of sampled-sound channels, you might achieve better results with the Time Manager, which is described in *Inside Macintosh: Processes*. ♦

Managing Sound Volumes

Versions of the Sound Manager prior to 3.0 allow you to set only one volume level, which applies to all sounds produced by the audio hardware. The Sound Manager versions 3.0 and later provide greatly improved control over the volumes of the sounds you ask it to create. You can use new facilities to

- set the volumes of the left and right channels of sound independently of each other
- set the volume of the system alert sound
- set the default volume of a particular sound output device

You can set the system alert sound volume to a different level than that of any other sounds you produce. For example, you can set the system alert sound to play at a lower volume than other sounds. This would allow a user to hear QuickTime movies at full volume and to hear system alert sounds at a lower volume.

You can use the `volumeCmd` and `getVolumeCmd` sound commands to set and get the right and left volumes of sound. You specify a channel's volume with 16-bit value, where 0 represents no volume and hexadecimal \$0100 represents full volume. The Sound Manager defines constants for silence and full volume.

```
CONST
```

```
    kFullVolume           = $0100;
    kNoVolume             = 0;
```

The `volumeCmd` sound command expects the right and left volumes to be encoded as the high word and low word, respectively, of `param2`. For example, to set the left channel to half volume and the right channel to full volume, you pass the value \$01000080 in `param2`, as illustrated in Listing 2-8.

Listing 2-8 Setting left and right volumes

```

FUNCTION MySetVolume (chan: SndChannelPtr): OSErr;
VAR
    mySndCmd:      SndCommand;
    myRightVol:    Integer;
    myLeftVol:     Integer;
    myErr:         OSErr;
BEGIN
    myRightVol := kFullVolume;
    myLeftVol := kFullVolume DIV 2;
    mySndCmd.cmd := volumeCmd;
    mySndCmd.param1 := 0;           {unused with volumeCmd}
    mySndCmd.param2 := BSL(myRightVol, 16) + myLeftVol;
    myErr := SndDoImmediate(chan, mySndCmd);
    MySetVolume := myErr;
END;

```

You can also use the `volumeCmd` sound command to pan a sound from one side to another. For example, to send the output signal entirely to the right channel, pass the value \$01000000 in `param2`. To send the output signal entirely to the left channel, pass the value \$00000100 in `param2`. You can overdrive a channel's volume by passing volume levels greater than \$0100. For example, to play the left channel of a stereo sound at twice full volume while playing the right channel at full volume, pass the value \$01000200.

You can use the `GetSysBeepVolume` and `SetSysBeepVolume` functions to get and set the output volume level of the system alert sound. Any calls to the `SysBeep` procedure use the volume set by the previous call to `SetSysBeepVolume`. As you've learned, this allows you to set a lower volume for the system alert sound than for your other sound output.

You can use the `GetDefaultOutputVolume` and `SetDefaultOutputVolume` functions to set the default output volumes for a particular output device. Each output device has its own current volume setting and its own default setting. If the user changes the output device (using the Sound control panel), the newly selected device will use its own default volume level.

Obtaining Sound-Related Information

Developments in the sound hardware available on Macintosh computers and in the Sound Manager routines that allow you to drive that hardware have made it imperative that your application pay close attention to the sound-related features of the operating environment. For example, some Macintosh computers do not have the sound input hardware necessary to allow sound recording. Similarly, some other Macintosh computers are not able to record sounds and play sounds simultaneously. Before taking

advantage of a sound-related feature that is not available on all Macintosh computers, you should check to make sure that the target machine provides the features you need.

To make appropriate decisions about the sound you want to produce, you might need to know some or all of the following types of information:

- whether a machine can produce stereophonic sounds
- what version of the Sound Manager is available
- whether a machine can play multiple channels of sound, and whether it can take advantage of the enhanced Sound Manager's play-from-disk capabilities
- whether a sound playing from disk is active or paused
- how many channels of sound are currently open
- whether the system beep has been disabled

The following sections describe how to use the `Gestalt` function and Sound Manager routines to determine these types of information.

Obtaining Information About Available Sound Features

You can use the `Gestalt` function to obtain information about a number of hardware- and software-related sound features. For instance, you can use `Gestalt` to determine whether a machine can produce stereophonic sounds and whether it can mix both left and right channels of sound on the internal speaker. Many applications don't need to call `Gestalt` to get this kind of information if they rely on the Sound Manager's ability to produce reasonable sounding output on whatever audio hardware is available. Other applications, however, do need to use `Gestalt` to get this information if they depend on specific hardware or software features that are not available on all Macintosh computers.

To get sound-related information from `Gestalt`, pass it the `gestaltSoundAttr` selector.

```
CONST
    gestaltSoundAttr    = 'snd ';    {sound attributes}
```

If `Gestalt` returns successfully, it passes back to your application a 32-bit value that represents a bit pattern. The following constants define the bits currently set or cleared by `Gestalt`:

```
CONST
    gestaltStereoCapability    = 0;    {built-in hw can play stereo sounds}
    gestaltStereoMixing        = 1;    {built-in hw mixes stereo to mono}
    gestaltSoundIOMgrPresent   = 3;    {sound input routines available}
    gestaltBuiltInSoundInput   = 4;    {built-in input hw available}
    gestaltHasSoundInputDevice = 5;    {sound input device available}
    gestaltPlayAndRecord       = 6;    {built-in hw can play while recording}
    gestalt16BitSoundIO        = 7;    {built-in hw can handle 16-bit data}
    gestaltStereoInput         = 8;    {built-in hw can record stereo sounds}
```

Sound Manager

```
gestaltLineLevelInput      = 9;      {built-in input hw needs line level}
gestaltSndPlayDoubleBuffer = 10;    {play from disk routines available}
gestaltMultiChannels      = 11;    {multiple channels of sound supported}
gestalt16BitAudioSupport  = 12;    {16-bit audio data supported}
```

If the bit `gestaltStereoCapability` is `TRUE`, the built-in hardware can play stereo sounds. The bit `gestaltStereoMixing` indicates that the sound hardware of the machine mixes both left and right channels of stereo sound into a single audio signal for the internal speaker. Listing 2-9 demonstrates the use of the `Gestalt` function to determine if a machine can play stereo sounds.

Listing 2-9 Determining if stereo capability is available

```
FUNCTION MyHasStereo: Boolean;
VAR
    myFeature:      LongInt;
    myErr:          OSErr;
BEGIN
    myErr := Gestalt(gestaltSoundAttr, myFeature);
    IF myErr = noErr THEN      {test stereo capability bit}
        MyHasStereo := BTst(myFeature, gestaltStereoCapability)
    ELSE
        MyHasStereo := FALSE;  {no sound features available}
END;
```

As shown in the chapter “Introduction to Sound on the Macintosh,” you can determine whether your application can record by testing the `gestaltHasSoundInputDevice` bit. To determine whether a built-in sound input device is available, you can test the `gestaltBuiltInSoundInput` bit. The `gestaltSoundIOMgrPresent` bit indicates whether the sound input routines are available. Because the `gestaltHasSoundInputDevice` bit is not set if the routines are not available, only sound input device drivers should need to use the `gestaltSoundIOMgrPresent` bit. For a complete description of the response bits set by `Gestalt`, see “Gestalt Selector and Response Bits” beginning on page 2-90.

Obtaining Version Information

The Sound Manager provides functions that allow you to determine the version numbers both of the Sound Manager itself and of the MACE compression and expansion routines. Generally, you should avoid trying to determine which features or routines are present by reading a version number. Usually, the `Gestalt` function (discussed in the previous section) provides a better way to find out if some set of features, such as sound input capability, is available. In some cases, however, you can use these version routines to overcome current limitations of the information returned by `Gestalt`.

Sound Manager

Both of these functions return a value of type `NumVersion` that contains the same information as the first 4 bytes of a resource of type `'vers'`. The first and second bytes contain the major and minor version numbers, respectively; the third and fourth bytes contain the release level and the stage of the release level. For most purposes, the major and minor release version numbers are sufficient to identify the version. (See the chapter “Finder Interface” of *Inside Macintosh: Macintosh Toolbox Essentials* for a complete discussion of the format of `'vers'` resources.)

You can use the `SndSoundManagerVersion` function to determine which version of the Sound Manager is present. Listing 2-10 shows how to determine if the enhanced Sound Manager is available.

Listing 2-10 Determining if the enhanced Sound Manager is present

```
FUNCTION MyHasEnhancedSoundManager: Boolean;
VAR
    myVersion:    NumVersion;
BEGIN
    IF MyTrapAvailable(_SoundDispatch) THEN
    BEGIN
        myVersion := SndSoundManagerVersion;
        MyHasEnhancedSoundManager := myVersion.majorRev >= 2;
    END
    ELSE
        MyHasEnhancedSoundManager := FALSE
    END;
END;
```

The `MyHasEnhancedSoundManager` function defined in Listing 2-10 relies on the `MyTrapAvailable` function, which is an application-defined routine provided in *Inside Macintosh: Operating System Utilities*. If the `_SoundDispatch` trap is not available, the `SndSoundManagerVersion` function is not available either, in which case the enhanced Sound Manager is certainly not available.

You can use the `MACEVersion` function to determine the version number of the available MACE routines (for example, `Comp3to1`).

Testing for Multichannel Sound and Play-From-Disk Capabilities

The ability to play multiple channels of sound simultaneously and the ability to initiate plays from disk were first introduced with the enhanced Sound Manager. Even with the enhanced Sound Manager, however, these capabilities are present only on computers equipped with suitable sound output hardware (such as an Apple Sound Chip). Sound Manager version 3.0 defines 2 additional bits in the `Gestalt` response parameter that allow you to test directly for these two capabilities.

Sound Manager

```
CONST
    gestaltSndPlayDoubleBuffer    = 10; {play from disk routines available}
    gestaltMultiChannels          = 11; {multiple channels of sound supported}
```

Ideally, it should be sufficient to test directly, using `Gestalt`, for either multichannel sound capability or play-from-disk capability. If your application happens to be running under the enhanced Sound Manager, however, the two new response bits are not defined. In that case, you'll need to test also whether the Apple Sound Chip is available, because multichannel sound and play from disk are supported by the enhanced Sound Manager only if the Apple Sound Chip is available. To test for the presence of the Apple Sound Chip, you can use the `Gestalt` function with the `gestaltHardwareAttr` selector and the `gestaltHasASC` bit. Listing 2-11 combines these two tests into a single routine that returns `TRUE` if the computer supports multichannel sound.

Listing 2-11 Testing for multichannel play capability

```
FUNCTION MyCanPlayMultiChannels: Boolean;
VAR
    myResponse:    LongInt;
    myResult:      Boolean;
    myErr:         OSErr;
    myVersion:     NumVersion;
BEGIN
    myResult := FALSE;
    myVersion := SndSoundManagerVersion;
    myErr := Gestalt(gestaltSoundAttr, myResponse);
    IF myVersion.majorRev >= 3 THEN
        IF (myErr = noErr) AND (BTst(myResponse, gestaltMultiChannels)) THEN
            myResult := TRUE
        ELSE
            BEGIN
                myErr := Gestalt(gestaltHardwareAttr, myResponse);
                IF (myErr = noErr) AND (BTst(myResponse, gestaltHasASC)) THEN
                    myResult := TRUE
            END;
        MyCanPlayMultiChannels := myResult;
    END;
```

The function `MyCanPlayMultiChannels` first tries to get the desired information by calling the `Gestalt` function with the `gestaltSoundAttr` selector. If `Gestalt` returns successfully and the `gestaltMultiChannels` bit is set in the response parameter, then multichannel play capability is present. Notice that the multichannel bit is checked only if the version of the Sound Manager is 3.0 or greater. If the version is not at least 3.0, then `MyCanPlayMultiChannels` calls the `Gestalt` function with the

Sound Manager

`gestaltHardwareAttr` selector. If the computer contains the Apple Sound Chip, then again multichannel play capability is present.

Note

The `gestaltHasASC` bit is set only on machines that contain an Apple Sound Chip. You should test for the presence of the Apple Sound Chip only in the circumstances described above. ♦

You could write a similar function to test for the ability to initiate a play from disk. Listing 2-12 shows an example.

Listing 2-12 Testing for play-from-disk capability

```

FUNCTION HasPlayFromDisk: Boolean;
VAR
    myResponse:    LongInt;
    myResult:      Boolean;
    myErr:         OSErr;
    myVersion:     NumVersion;
BEGIN
    myResult := FALSE;
    myVersion := SndSoundManagerVersion;
    myErr := Gestalt(gestaltSoundAttr, myResponse);
    IF myVersion.majorRev >= 3 THEN
        IF (myErr = noErr) AND
            (BTst(myResponse, gestaltSndPlayDoubleBuffer)) THEN
            myResult := TRUE
        ELSE
            BEGIN
                myErr := Gestalt(gestaltHardwareAttr, myResponse);
                IF (myErr = noErr) AND (BTst(myResponse, gestaltHasASC)) THEN
                    myResult := TRUE
            END;
        HasPlayFromDisk := myResult;
    END;
END;

```

Obtaining Information About a Single Sound Channel

You can use the `SndChannelStatus` function to obtain information about a single sound channel and about the status of a disk-based playback on that channel, if one exists. For example, you can use `SndChannelStatus` to determine if a channel is being used for play from disk, how many seconds of the sound have been played, and how many seconds remain to be played.

Sound Manager

One of the parameters required by the `SndChannelStatus` function is a pointer to a sound channel status record, which you must allocate before calling `SndChannelStatus`. A sound channel status record has this structure:

```

TYPE SCStatus =
RECORD
    scStartTime:      Fixed;      {starting time for play from disk}
    scEndTime:       Fixed;      {ending time for play from disk}
    scCurrentTime:   Fixed;      {current time for play from disk}
    scChannelBusy:   Boolean;    {TRUE if channel is processing cmds}
    scChannelDisposed: Boolean;  {reserved}
    scChannelPaused: Boolean;    {TRUE if channel is paused}
    scUnused:        Boolean;    {unused}
    scChannelAttributes: LongInt; {attributes of this channel}
    scCPULoad:       LongInt;    {CPU load for this channel}
END;
```

The `scStartTime`, `scEndTime`, and `scCurrentTime` fields are 0 unless the Sound Manager is currently playing from disk through the specified channel. If a play from disk is occurring, the `scStartTime` and `scEndTime` fields reflect the starting and ending points of the play, defined in seconds; the `scCurrentTime` field indicates the number of seconds between the beginning of the sound on disk and the part of the sound currently being played. The Sound Manager sets the values of the `scStartTime` and `scEndTime` fields based on the values you set in an audio selection record. (See page 2-100 for a description of the audio selection record.)

Note that because the Sound Manager might be playing only a selection of a sound, the `scCurrentTime` field does not reflect the number of seconds of sound play that have elapsed. To compute the number of seconds of sound play elapsed, you can subtract the value in the `scStartTime` field from that in the `scCurrentTime` field. However, because the Sound Manager updates the value of the `scCurrentTime` field only periodically, you should not rely on the accuracy of its value.

The `scChannelBusy` and `scChannelPaused` fields reflect whether a channel is processing commands and whether a channel is paused, respectively. After issuing a series of sound commands, you can use these fields to determine if the channel has finished processing all of the commands. If both `scChannelBusy` and `scChannelPaused` are `FALSE`, the Sound Manager has processed all of the channel's commands.

You can mask out certain values in the `scChannelAttributes` field to determine how a channel has been initialized.

```

CONST
    initPanMask      = $0003;    {mask for right/left pan values}
    initSRateMask    = $0030;    {mask for sample rate values}
    initStereoMask   = $00C0;    {mask for mono/stereo values}
```

Sound Manager

The `scCPULoad` field previously reflected the percentage of CPU processing power used by the sound channel. However, this field is obsolete, and you should not rely on its value.

Listing 2-13 illustrates the use of the `SndChannelStatus` function. It defines a function that takes a sound channel pointer as a parameter and determines whether a disk-based playback on that channel is paused.

Listing 2-13 Determining whether a sound channel is paused

```
FUNCTION MyChannelIsPaused (chan: SndChannelPtr): Boolean;
VAR
    myErr:      OSErr;
    mySCStatus: SCStatus;
BEGIN
    MyChannelIsPaused := FALSE;
    myErr := SndChannelStatus(chan, Sizeof(SCStatus), @mySCStatus);
    IF myErr = noErr THEN
        MyChannelIsPaused := mySCStatus.scChannelPaused;
    END;
```

The function defined in Listing 2-13 simply reads the `scChannelPaused` field to see if the playback is currently paused.

Note

In Sound Manager versions earlier than 3.0, pausing a sound channel by issuing a `pauseCmd` command does not change the `scChannelPaused` field. The `scChannelPaused` field is `TRUE` only if the Sound Manager is executing a disk-based playback on the channel and that playback is paused by the `SndPauseFilePlay` function. This problem is fixed in Sound Manager versions 3.0 and later. ♦

Obtaining Information About All Sound Channels

You can use the `SndManagerStatus` function to determine information about all the sound channels that are currently allocated by all applications. For example, you can use this function to determine how many channels are currently allocated. One of the parameters required by the `SndManagerStatus` function is a pointer to a Sound Manager status record, which you must allocate before calling `SndManagerStatus`. A Sound Manager status record has this structure:

```
TYPE SMStatus =
PACKED RECORD
    smMaxCPULoad:      Integer;      {maximum load on all channels}
    smNumChannels:    Integer;      {number of allocated channels}
    smCurCPULoad:     Integer;      {current load on all channels}
END;
```

Sound Manager

The `smNumChannels` field contains the number of sound channels currently allocated. This does not mean that the channels are actually being used, only that they have been created with the `SndNewChannel` function and not yet disposed.

The Sound Manager uses information that it returns in the `smMaxCPULoad` and `smCurCPULoad` fields to help it determine whether it can allocate a new channel when your application calls the `SndNewChannel` function. The Sound Manager sets `smMaxCPULoad` to a default value of 100 at startup time, and the `smCurCPULoad` field reflects the approximate percentage of CPU processing power currently taken by allocated sound channels.

▲ **WARNING**

Your application should not rely on the values returned in the `smMaxCPULoad` and `smCurCPULoad` fields. To determine if it is safe to allocate a channel, simply try to allocate it with the `SndNewChannel` function. That function returns the appropriate result code if allocating the channel would put too much of a strain on CPU processing. ▲

Listing 2-14 illustrates the use of `SndManagerStatus`. It defines a function that returns the number of sound channels currently allocated by all applications.

Listing 2-14 Determining the number of allocated sound channels

```
FUNCTION MyGetNumChannels: Integer;
VAR
    myErr:      OSErr;
    mySMStatus: SMStatus;
BEGIN
    MyGetNumChannels := 0;
    myErr := SndManagerStatus (Sizeof(SMStatus), @mySMStatus);
    IF myErr = noErr THEN
        MyGetNumChannels := mySMStatus.smNumChannels;
    END;
```

Determining and Changing the Status of the System Alert Sound

The enhanced Sound Manager includes two routines—`SndGetSysBeepState` and `SndSetSysBeepState`—that allow you to determine and alter the status of the system alert sound. You might wish to disable the system alert sound if you are playing sound and need to ensure that the sound you are playing is not interrupted. Currently, two states are defined:

```
CONST
    sysBeepDisable      = $0000;    {system alert sound disabled}
    sysBeepEnable       = $0001;    {system alert sound enabled}
```

You can determine the status of the system alert sound like this:

Sound Manager

```
SndGetSysBeepState(currentState);
```

And you can disable the system alert sound like this:

```
myErr := SndSetSysBeepState(sysBeepDisable);
```

When the system alert sound is disabled, the Sound Manager effectively ignores all calls to the `SysBeep` procedure. No sound is created and the menu bar does not flash. Also, no resources are loaded into memory.

Note

Even when the system alert sound is enabled, it's possible that the system alert sound will not play; for example, the speaker volume might be set to 0, or playing the requested system alert sound might require too much CPU time. In such a case, the menu bar flashes. ♦

By default, the system alert sound is enabled. If you disable the system alert sound so that your application can play a sound without being interrupted, be sure to enable the sound when your application receives a suspend event or when the user quits your application.

Playing Notes

You can play notes one at a time by using the `SndDoCommand` or `SndDoImmediate` function to issue `freqDurationCmd` sound commands. A sound plays for a specified duration at a specified frequency. You can play sounds defined by any of the three sound data formats. If you play wave-table data or sampled-sound data, then a voice must previously have been installed in the channel. (See “Installing Voices Into Channels” on page 2-43 for instructions on installing wave tables and sampled sounds as voices.)

You can also play notes by issuing the `freqCmd` command, which is identical to the `freqDurationCmd` command, except that no duration is specified when you issue `freqCmd`.

Note

A `freqDurationCmd` command might in certain cases continue playing until another command is available in the sound channel. Therefore, to play a single note for a specified duration, you should issue `freqDurationCmd` followed immediately by `quietCmd`. See “Stopping Sound Channels” on page 2-28 for further details on `quietCmd`. ♦

The structure of a `freqDurationCmd` command is slightly different from that of most other sound commands. The `param1` field contains the duration of the sound, specified in half-milliseconds. A value of 2000 represents a duration of 1 second. The maximum duration is 32,767, or about 16 seconds, in Sound Manager versions 2.0 and earlier; the maximum duration in Sound Manager version 3.0 and later is 65,536, or about 32 seconds. The `param2` field specifies the frequency of the sound. The frequency is specified as a MIDI note value (that is, a value defined by the established MIDI

Sound Manager

standard). Listing 2-15 uses the `freqDurationCmd` command in a way that ensures the sound stops after the specified duration.

Listing 2-15 Using the `freqDurationCmd` command

```

PROCEDURE MyPlayFrequencyOnce (mySndChan: SndChannelPtr;
                               myMIDIValue: Integer;
                               milliseconds: Integer);

CONST
    kNoWait = TRUE;           {add now to full queue?}
VAR
    mySndCmd: SndCommand;    {a sound command}
    myErr: OSErr;
BEGIN
    {Start the sound playing.}
    WITH mySndCmd DO
        BEGIN
            cmd := freqDurationCmd;    {play for period of time}
            param1 := milliseconds * 2; {half-milliseconds}
            param2 := myMIDIValue;    {MIDI value to play}
        END;
        myErr := SndDoCommand(mySndChan, mySndCmd, NOT kNoWait);
        IF myErr <> noErr THEN
            DoError(myErr)
        ELSE
            BEGIN
                {ensure that sound stops}
                WITH mySndCmd DO
                    BEGIN
                        cmd := quietCmd;    {stop playing sound}
                        param1 := 0;        {unused with quietCmd}
                        param2 := 0;        {unused with quietCmd}
                    END;
                    myErr := SndDoCommand(mySndChan, mySndCmd, NOT kNoWait);
                    IF myErr <> noErr THEN
                        DoError(myErr);
                END;
            END;
    END;
END;

```

Table 2-2 shows the decimal values that can be sent with a `freqDurationCmd` or `freqCmd` command. Middle C is represented by a value of 60 and is defined by a special Sound Manager constant.

```

CONST
    kMiddleC = 60;           {MIDI note value for middle C}

```

Other specifiable frequencies correspond to MIDI note values.

Table 2-2 Frequencies expressed as MIDI note values

	A	A#	B	C	C#	D	D#	E	F	F#	G	G#
Octave 1				0	1	2	3	4	5	6	7	8
Octave 2	9	10	11	12	13	14	15	16	17	18	19	20
Octave 3	21	22	23	24	25	26	27	28	29	30	31	32
Octave 4	33	34	35	36	37	38	39	40	41	42	43	44
Octave 5	45	46	47	48	49	50	51	52	53	54	55	56
Octave 6	57	58	59	60	61	62	63	64	65	66	67	68
Octave 7	69	70	71	72	73	74	75	76	77	78	79	80
Octave 8	81	82	83	84	85	86	87	88	89	90	91	92
Octave 9	93	94	95	96	97	98	99	100	101	102	103	104
Octave 10	105	106	107	108	109	110	111	112	113	114	115	116
Octave 11	117	118	119	120	121	122	123	124	125	126	127	

You can play square-wave and wave-table data at these frequencies only. If you are playing a sampled sound, however, you can modify the `sampleRate` field of the sound header to play a sound at an arbitrary frequency. To do so, use the following formula:

$$\text{new sample rate} = (\text{new frequency} / \text{original frequency}) * \text{original sample rate}$$

where the new and original frequencies are measured in hertz. To convert a MIDI value to hertz for use in this formula, note that middle C is defined as 261.625 Hz and that the ratio between the frequencies of consecutive MIDI values equals the twelfth root of 2, defined by the constant `twelfthRootTwo`.

```
CONST
    twelfthRootTwo          = 1.05946309434;
```

IMPORTANT

When calculating with numbers of type `Fixed`, pay attention to possible overflows. The maximum value of a number of type `Fixed` is 65,535.0.

As a result, some sample rates and pitches cannot be specified. Sound Manager version 3.0 fixes these overflow problems. ▲

You can rest a channel for a specified duration by issuing a `restCmd` command. The duration, specified in half-milliseconds, is passed in the `param1` field of the sound command.

Installing Voices Into Channels

You can play frequencies defined by any of the three sound data types. By playing a frequency defined by wave-table or sampled-sound data, you can achieve a different

Sound Manager

sound than by playing that same frequency using square-wave data. For example, you might wish to play the sound of a dog's barking at a variety of frequencies. To do that, however, you need to install a voice of the barking into the sound channel to which you want to send `freqCmd` or `freqDurationCmd` commands.

You can install a wave table into a channel as a voice by issuing the `waveTableCmd` command. The `param1` field of the sound command specifies the length of the wave table, and the `param2` field is a pointer to the wave-table data itself. Note that the Sound Manager resamples the wave table so that it is exactly 512 bytes long.

You can install a sampled sound into a channel as a voice by issuing the `soundCmd` command. You can either issue this command from your application or put it into an 'snd' resource. If your application sends this command, `param2` is a pointer to the sampled sound locked in memory. If `soundCmd` is contained within an 'snd' resource, the high bit of the command must be set. To use a sampled-sound 'snd' as a voice, first obtain a pointer to the sampled sound header locked in memory. Then pass this pointer in `param2` of a `soundCmd` command. After using the sound, your application is expected to unlock this resource and allow it to be purged.

Listing 2-16 demonstrates how you can use the `soundCmd` command to install a sampled sound in memory as a voice in a channel.

Listing 2-16 Installing a sampled sound as a voice in a channel

```

FUNCTION MyInstallSampledVoice (mySndHandle: Handle;
                               mySndChan: SndChannelPtr): OSErr;
VAR
  mySndCmd:      SndCommand;      {a sound command}
  mySndHeader:   SoundHeaderPtr;   {sound header from resource}
BEGIN
                               {get pointer to sound header}
  mySndHeader := MyGetSoundHeader(mySndHandle);
  WITH mySndCmd DO
  BEGIN
    cmd := soundCmd;           {install sampled voice}
    param1 := 0;               {ignored with soundCmd}
    param2 := LongInt(mySndHeader); {store sound header location}
  END;
  IF mySndHeader = NIL THEN    {check for defective handle}
    MyInstallSampledVoice := badFormat
  ELSE                          {install sound as voice}
    MyInstallSampledVoice := SndDoImmediate(mySndChan, mySndCmd);
END;

```

Listing 2-16 relies on the `MyGetSoundHeader` function to obtain a pointer to the sound header within the sound handle. That function is defined in “Obtaining a Pointer to a

Sound Header” on page 2-57 and returns `NIL` if the sound handle does not include a sound header. Note that the `MyGetSoundHeader` function locks the sound handle in memory so that the pointer to the sound header remains valid. When you are done with the sound channel in which you have installed the sampled sound, you should unlock the sound handle and make it purgeable so that it does not waste memory.

Looping a Sound Indefinitely

If you install a sampled sound as a voice in a channel and then play the sound using a `freqCmd` or `freqDurationCmd` command that lasts longer than the sound, the sound will ordinarily stop before the end of the time specified by the `freqCmd` or `freqDurationCmd` command. Sometimes, however, this might not be what you’d like to have happen. For example, you might have recorded the sound of a violin playing and then stored that sound in a resource so that you could play the sound of a violin at a number of different frequencies. Although you could record the sound so that it is long enough to continue playing through the longest `freqCmd` or `freqDurationCmd` command that your application might require, this might not be practical. Fortunately, the Sound Manager provides a mechanism that allows you to repeat sections of sampled sound after the sound has finished playing once completely.

When you use the `freqDurationCmd` command with a sampled sound as the voice, `freqDurationCmd` starts at the beginning of the sampled sound. If necessary to achieve the desired duration of sound, the command replays that part of the sound that is between the loop points specified in the sampled sound header. Note that any sound preceding or following the loop points will not be replayed. There must be an ending point for the loop specified in the header in order for `freqDurationCmd` to work properly.

Listing 2-17 Looping an entire sampled sound

```
PROCEDURE MyDoLoopEntireSound (sndHandle: Handle);
VAR
  mySndHeader:   SoundHeaderPtr;           {sound header from resource}
  myTotalBytes: LongInt;                   {bytes of data to loop}
BEGIN
  mySndHeader := MyGetSoundHeader(sndHandle);
  IF mySndHeader <> NIL THEN
    BEGIN
      {compute bytes of sound data}
      CASE mySndHeader^.encode OF
        stdSH:                                     {standard sound header}
          WITH mySndHeader^ DO
            myTotalBytes := mySndHeader^.length;
        extSH:                                     {extended sound header}
          WITH ExtSoundHeaderPtr(mySndHeader)^ DO
            myTotalBytes := numChannels * numFrames * (sampleSize DIV 8);
        cmpSH:                                     {compressed sound header}
```

Sound Manager

```

    WITH CmpSoundHeaderPtr(mySndHeader)^ DO
        myTotalBytes := numChannels * numFrames * (sampleSize DIV 8);
END;
WITH mySndHeader^ DO
BEGIN
    loopStart := 0;           {set loop points}
    loopEnd := myTotalBytes - 1; {start with first byte}
                                {end with last byte}
END;
END;
END;

```

Listing 2-17 uses the `MyGetSoundHeader` function defined in “Obtaining a Pointer to a Sound Header” on page 2-57. Note that the formula for computing the length of a sound depends on the type of sound header. Also, while the formula is the same for both an extended and a compressed sound header, you must write code that differentiates between the two types of sound headers because the `sampleSize` field is not stored in the same location in both sound headers.

Playing Sounds Asynchronously

The Sound Manager currently allows you to play sounds asynchronously only if you allocate sound channels yourself, using techniques described in “Managing Sound Channels” on page 2-19. But if you use such a technique, your application will need to dispose of a sound channel whenever the application finishes playing a sound. In addition, your application might need to release a sound resource that you played on a sound channel.

To avoid the problem of not knowing when to dispose of a sound channel playing a sound asynchronously, your application could simply allocate a single sound channel when it starts up (or receives a resume event) and dispose of the channel when the user quits (or the application receives a suspend event). However, this solution will not work if you need to release a resource when a sound finishes playing. Also, you might not want to keep a sound channel allocated when you are not using it. For instance, you might want to use the memory taken up by a sound channel for other tasks when no sound is playing.

Your application could call the `SndChannelStatus` function once each time through its main event loop to determine if a channel is still making sound. When the `scBusy` field of the sound channel status record becomes `FALSE`, your application could then dispose of the channel. This technique is easy, but calling `SndChannelStatus` frequently uses up processing time unnecessarily.

The Sound Manager provides other mechanisms that allow your application to find out when a sound finishes playing, so that your application can arrange to dispose of sound channels no longer being used and of other data (such as a sound resource) that you no longer need after disposing of a channel. If you are using the `SndPlay` function or low-level commands to play sound in a channel, then you can use callback procedures. If you are using the `SndStartFilePlay` function to play sound in a channel, then you

can use completion routines. The following sections illustrate how to use callback procedures and completion routines.

Note

Callback procedures are a form of completion routine. However, for clarity, this section uses the terminology “completion routine” only for the routines associated with the `SndStartFilePlay` function. ♦

Using Callback Procedures

This section shows how you can use callback procedures to play one sound asynchronously at a given time. “Managing Multiple Sound Channels” on page 2-53 expands the techniques in this section to show how you can play several asynchronous sounds simultaneously.

The `SndNewChannel` function allows you to associate a callback procedure with a sound channel. For example, the following code opens a new sound channel for which memory has already been allocated and associates it with the callback procedure `MyCallback`:

```
myErr := SndNewChannel(gSndChan, sampledSynth, initMono, @MyCallback);
```

After filling a channel created by `SndNewChannel` with various commands to create sound, you can then issue a `callbackCmd` command to the channel. When the Sound Manager encounters a `callbackCmd` command, it executes your callback procedure. Thus, by placing the `callbackCmd` command last in a channel, you can ensure that the Sound Manager executes your callback procedure only after it has processed all of the channel’s other sound commands.

Note

Be sure to issue `callbackCmd` commands with the `SndDoCommand` function and not the `SndDoImmediate` function. If you issue a `callbackCmd` command with `SndDoImmediate`, your callback procedure might be called before other sound commands you have issued finish executing. ♦

A callback procedure has the following syntax:

```
PROCEDURE MyCallback (chan: SndChannelPtr; cmd: SndCommand);
```

Because the callback procedure executes at interrupt time, it cannot access its application global variables unless the application’s A5 world is set correctly. (For more information on the A5 world, see the chapter “Memory Management Utilities” in *Inside Macintosh: Memory*.) When called, the callback procedure is passed two parameters: a pointer to the sound channel that received the `callbackCmd` command and the sound command that caused the callback procedure to be called. Applications can use `param1` or `param2` of the sound command as flags to pass information or instructions to the callback procedure. If your callback procedure is to use your application’s global data storage, it must first reset A5 to your application’s A5 and then restore it on exit. For example, Listing 2-18 illustrates how to set up a `callbackCmd` command that contains the

Sound Manager

required A5 information in the `param2` field. The `MyInstallCallback` function defined there must be called at a time when your application's A5 world is known to be valid.

Listing 2-18 Issuing a callback command

```
FUNCTION MyInstallCallback (mySndChan: SndChannelPtr): OSErr;
CONST
    kWaitIfFull = TRUE;           {wait for room in queue}
VAR
    mySndCmd: SndCommand;        {a sound command}
BEGIN
    WITH mySndCmd DO
    BEGIN
        cmd := callBackCmd;       {install the callback command}
        param1 := kSoundComplete; {last command for this channel}
        param2 := SetCurrentA5;    {pass the callback the A5}
    END;
    MyInstallCallback := SndDoCommand(mySndChan, mySndCmd, kWaitIfFull);
END;
```

In this function, `kSoundComplete` is an application-defined constant that indicates that the requested sound has finished playing. You could define it like this:

```
CONST
    kSoundComplete = 1;          {sound is done playing}
```

Because `param2` of a sound command is a long integer, Listing 2-18 uses it to pass the application's A5 to the callback procedure. That allows the callback procedure to gain access to the application's A5 world.

Note

You can also pass information to a callback routine in the `userInfo` field of the sound channel. ♦

The sample callback procedure defined in Listing 2-19 can thus set A5 to access the application's global variables.

Listing 2-19 Defining a callback procedure

```
PROCEDURE MyCallback (theChan: SndChannelPtr; theCmd: SndCommand);
VAR
    myA5: LongInt;
BEGIN
    IF theCmd.param1 = kSoundComplete THEN
```

Sound Manager

```

BEGIN
    myA5 := SetA5(theCmd.param2);      {set my A5}
    gCallbackPerformed := TRUE;       {set a global flag}
    myA5 := SetA5(myA5);              {restore the original A5}
END;
END;

```

▲ **WARNING**

Callback procedures are called at interrupt time and therefore must not attempt to allocate, move, or dispose of memory, dereference an unlocked handle, or call other routines that do so. Also, assembly-language programmers should note that a callback procedure is a Pascal procedure and must preserve all registers other than A0–A1 and D0–D2. ▲

Callback procedures cannot dispose of channels themselves, because that involves disposing of memory. To circumvent this restriction, the callback procedure in Listing 2-19 simply sets the value of a global flag variable that your application defines. Then, once each time through its main event loop, your application must call a routine that checks to see if the flag is set. If the flag is set, the routine should dispose of the channel, release any other memory allocated specifically for use in the channel, and reset the flag variable. Listing 2-20 defines such a routine. Your application should call it once each time through its main event loop.

Listing 2-20 Checking whether a callback procedure has executed

```

PROCEDURE MyCheckSndChan;
CONST
    kQuietNow = TRUE;                {need to quiet channel?}
VAR
    myErr:    OSErr;
BEGIN
    IF gCallbackPerformed THEN       {check global flag}
    BEGIN                             {channel is done}
        gCallbackPerformed := FALSE; {reset global flag}
        IF gSndChan^.userInfo <> 0 THEN
        BEGIN                          {release sound data}
            HUnlock(Handle(gSndChan^.userInfo));
            HPurge(Handle(gSndChan^.userInfo));
        END;
        myErr := MyDisposeSndChannel(gSndChan, kQuietNow);
        gSndChan := NIL;              {set pointer to NIL}
    END;
END;

```

Sound Manager

The `MyCheckSndChan` procedure defined in Listing 2-20 checks the `userInfo` field of the sound channel to see if it contains the address of a handle. Thus, if you would like the `MyCheckSndChan` procedure to release memory associated with a sound handle, you need only put the address of the handle in the `userInfo` field of the sound channel. (If you do not want the `MyCheckSndChan` procedure to release memory associated with a handle, then you should set the `userInfo` field to 0 when you allocate the channel. The `MyCreateSndChannel` function defined in Listing 2-1 on page 2-20 automatically sets this field to 0.) After releasing the memory associated with the sound handle, the `MyCheckSndChan` procedure calls the `MyDisposeSndChannel` function (defined in Listing 2-3 on page 2-25) to release the memory occupied by both the sound channel and the sound channel record.

To ensure that the `MyCheckSndChan` procedure defined in Listing 2-20 does not attempt to dispose a channel before you have created one, you should initialize the `gCallbackPerformed` variable to `FALSE`. Also, you should initialize the `gSndChan` variable to `NIL`, so that other parts of your application can check to see if a sound is playing simply by checking this variable. For example, if your application must play a sound but another sound is currently playing, you might ensure that the application gives priority to the newer sound by stopping the old one. Listing 2-21 defines a procedure that stops the sound that is playing.

Listing 2-21 Stopping a sound that is playing asynchronously

```
PROCEDURE MyStopPlaying;
BEGIN
    IF gSndChan <> NIL THEN           {is sound really playing?}
        gCallbackPerformed := TRUE;  {set global flag}
        MyCheckSndChan;              {call routine to do disposing}
    END;
```

Once you have defined a callback procedure, a routine that installs the callback procedure, a routine that checks the status of the callback procedure, and a routine that can stop sound play, you need only allocate a sound channel, call the `SndPlay` function, and install your callback procedure to start an asynchronous sound play. Listing 2-22 defines a procedure that starts an asynchronous play.

Listing 2-22 Starting an asynchronous sound play

```
PROCEDURE MyStartPlaying (mySndID: Integer);
CONST
    kAsync = TRUE;                  {play is asynchronous}
VAR
    mySndHandle: Handle;           {handle to an 'snd ' resource}
    myErr: OSErr;
BEGIN
```

Sound Manager

```

IF gSndChan <> NIL THEN                                {check if channel is active}
    MyStopPlaying;
gSndChan := MyCreateSndChannel(0, 0, @MyCallbackProc, stdQLength);
mySndHandle := GetResource('snd ', mySndID);
IF (mySndHandle <> NIL) AND (gSndChan <> NIL) THEN
BEGIN                                                {start sound playing}
    DetachResource(mySndHandle);                      {detach resource from file}
                                                    {remember to release sound handle}
    gSndChan^.userInfo := LongInt(mySndHandle);
    HLock(mySndHandle);                              {lock the resource data}
    myErr := SndPlay(gSndChan, mySndHandle, kAsync);
    IF myErr = noErr THEN
        myErr := MyInstallCallback(gSndChan);
    IF myErr <> noErr THEN
        DoError(myErr);
END;
END;

```

The `MyStartPlaying` procedure uses the `MyCreateSndChannel` function defined in Listing 2-1 to create a sound channel, requesting that the function allocate a standard-sized sound channel command queue. By using such a queue, you can be sure that your application can play any sound resource that contains up to 127 sound commands. If you are sure that your application will play only sampled-sound resources created by the Sound Input Manager, you should request a queue of only two sound commands, thereby leaving enough room for just the `bufferCmd` command contained within the sound resource and the `callBackCmd` command that your application issues.

Before playing the sound, the `MyStartPlaying` procedure defined in Listing 2-22 detaches the sound resource from its resource file after loading it. This is important if the resource file could close while the sound is still playing, or if your application might create another sound channel to play the same sound resource while the sound is still playing.

Synchronizing Sound With Other Actions

If your application uses callback procedures to play sound asynchronously, you might wish to synchronize sound play with other activity, such as an onscreen animation.

Callback procedures allow your application to do that by using different constant values in the `param1` field of the callback command. For example, you could define a constant `kFirstSoundFinished` to signal to your application that the first of a series of sounds has finished playing. Then, your callback procedure could set an appropriate global flag depending on whether the `param1` field equals `kFirstSoundFinished`, `kSoundComplete`, or some other constant that your application defines. Finally, a procedure that you call once each time through your application's event loop could check to see which of the various global flag variables are set and respond appropriately. Meanwhile, sound continues to play.

Managing an Asynchronous Play From Disk

The Sound Manager allows you to play a sound file asynchronously with the `SndStartFilePlay` function by defining a completion routine that sets a global flag to alert the application to dispose of the sound channel when the sound is done playing. Completion routines are thus similar to callback procedures, but they are easier to use in that you do not need to install them. The Sound Manager automatically executes them when a play from disk ends, whether it has ended because the application called the `SndStopFilePlay` function, because the application disposed of the sound channel in which the sound was playing, or because the sound has finished playing.

You define a completion routine like this:

```
PROCEDURE MySoundCompletionRoutine (chan: SndChannelPtr);
```

Note that unlike callback procedures, completion routines have only one parameter, a pointer to a sound channel. Thus, for the completion routine to set the application's A5 world properly, you should pass the value of the application's A5 in the `userInfo` field of the sound channel, like this:

```
gSndChan^.userInfo := SetCurrentA5;
```

Then your completion routine can look in the `userInfo` field of the sound channel to set A5 correctly before it can access any application global variables. Listing 2-23 defines a completion routine that sets A5 correctly.

Listing 2-23 Defining a completion routine

```
PROCEDURE MySoundCompletionRoutine (chan: SndChannelPtr);
VAR
    myA5:    LongInt;
BEGIN
    myA5 := SetA5(chan^.userInfo);      {set my A5}
    gCompletionPerformed := TRUE;      {set a global flag}
    myA5 := SetA5(myA5);                {restore the original A5}
END;
```

The completion routine defined in Listing 2-23 sets a global flag variable to indicate that the completion routine has been called. To start a sound file playing, you can use a routine analogous to that defined in Listing 2-22, but when allocating a sound channel, you need only allocate a queue of a single sound command. You can then use a procedure analogous to that defined in Listing 2-20 to check the flag once each time through the application's event loop and dispose of the sound channel if the flag is set.

If you do use the `SndStartFilePlay` function to play sounds asynchronously, then you can pause, restart, and stop play simply by using the `SndPauseFilePlay` and `SndStopFilePlay` functions.

You use `SndPauseFilePlay` to temporarily suspend a sound from playing. If a sound is playing and you call `SndPauseFilePlay`, then the sound is paused. If the sound is paused and you call `SndPauseFilePlay` again, then the sound resumes playing. Hence, the `SndPauseFilePlay` routine acts like a pause button on a tape player, which toggles the tape between playing and pausing. (You can determine the current state of a play from disk by using the `SndChannelStatus` function. See “Obtaining Information About a Single Sound Channel” on page 2-37 for more details.) Finally, you can use `SndStopFilePlay` to stop the file from playing.

Playing Selections

The sixth parameter passed to the `SndStartFilePlay` function is a pointer to an **audio selection record**, which allows you to specify that only part of the sound be played. If that parameter has a value different from `NIL`, then `SndStartFilePlay` plays only a specified selection of the entire sound. You indicate which part of the entire sound to play by giving two offsets from the beginning of the sound, a time at which to start the selection and a time at which to end the selection. Currently, both time offsets must be specified in seconds.

Here is the structure of an audio selection record:

```
TYPE AudioSelection =
PACKED RECORD
    unitType:    LongInt;    {type of time unit}
    selStart:    Fixed;      {starting point of selection}
    selEnd:      Fixed;      {ending point of selection}
END;
```

To play a selection, you should specify in the `selStart` and `selEnd` fields the starting and ending point in seconds of the sound to play. Also, you must set the `unitType` field to the constant `unitTypeSeconds`.

If you wish to play an entire sound, you can simply pass `NIL` to the `SndStartFilePlay` function. Alternatively, you can set the `unitType` field to the constant `unitTypeNoSelection`, in which case the values in the `selStart` and `selEnd` fields are ignored.

Managing Multiple Sound Channels

If you are writing an application that can play multiple channels of sound on Macintosh computers that support that feature, you can use the Sound Manager’s asynchronous playing abilities, but you might encounter some special obstacles. The technique for playing sounds asynchronously described in “Playing Sounds Asynchronously” on page 2-46 has a limitation if you are using multiple sound channels. Using that technique without modification, you would need to define each separate sound channel in a different global variable, and you would need to use several global flags in your callback procedure to signal which sound channels have finished processing sound commands.

Sound Manager

Although it is easy to modify the code in “Playing Sounds Asynchronously” to use several flags, this solution might not be satisfactory for an application in which the number of sound channels open can vary. For example, suppose that you are writing entertainment software with dozens of sound effects that correspond to actions on the screen and you wish to use the Sound Manager asynchronously so that several sound effects can be played at once. It would be cumbersome to associate a separate global sound channel variable with each sound and create a flag variable for each of these sound channels. Also, you might wish to play the same sound simultaneously in two separate channels. It would be better to write code that manages a global list of sound channels and then provides a simple routine that allows you to add a channel to the list. This section shows how you might implement such a list of sound channels. Listing 2-24 defines a data structure that you could use to track multiple sound channels.

Listing 2-24 Defining a data structure to track many sound channels

```

CONST
    kMaxNumSndChans = 20;           {max number of sound channels}
TYPE
    SCInfo =
    RECORD
        sndChan:      SndChannelPtr; {NIL or pointer to channel}
        mustDispose: Boolean;       {flag to dispose channel}
        itsData:      Handle;       {data to dispose with channel}
    END;
    SCList = ARRAY[1..kMaxNumSndChans] OF SCInfo;
VAR
    gSndChans:      SCList;

```

The `SCInfo` data structure defined in Listing 2-24 allows you to keep track of which channels in the collection are being used and which were being used but currently need disposal; it also allows you to associate data with a sound channel so that you can dispose of the data when you dispose of the sound channel. Note that the value of the `kMaxNumSndChans` constant might vary from application to application. Having defined the data structure, you must initialize it (so that the `sndChan` and `itsData` fields are `NIL` and the `mustDispose` field is `FALSE`). You must also write a procedure that finds an available channel. You might declare such a procedure like this:

```
PROCEDURE DoTrackChan (chanToTrack: SndChannelPtr; associatedData: Handle);
```

Using such a procedure, you could simply create sound channels by using local variables and then add them to the tracking list so that your application disposes of them when they finish executing. The exact implementation of such a procedure would depend on the needs of your application. For example, if there are no channels available in the global list of sound channels, your application might report an error, stop sound on all active channels, or stop sound on the channel that has been playing the longest. If you want your application to be compatible with computers that do not support

Sound Manager

multichannel sound, this procedure could check whether multichannel sound is supported, and if not, would stop any sound playing on other channels. This is particularly useful if your application plays sound effects in response to actions on the screen; overlapping sound effects sound best, but if this is unattainable, the newest sound should have the highest priority.

One advantage of maintaining a list of sound channels is that you can use it in conjunction with both callback procedures and completion routines. Listing 2-25 defines a procedure that either your callback procedure or completion routine could call after setting the application's A5 world correctly.

Listing 2-25 Marking a channel for disposal

```
PROCEDURE MySetTrackChanDispose (mySndChannel: SndChannelPtr);
VAR
    index:      Integer;      {channel index}
    found:      Boolean;      {flag variable}
BEGIN
    index := 1;                {start at first spot}
    found := FALSE;           {initialize flag variable}
    WHILE (index <= kMaxNumSndChans) AND (NOT found) DO
        IF gSndChans[index].sndChan = mySndChannel THEN
            found := TRUE      {proper channel found}
        ELSE
            index := index + 1; {move to next spot}
    IF found THEN
        gSndChans[index].mustDispose := TRUE;
END;
```

The final thing you need to do is to define a procedure that your application calls once each time through its main event loop. This procedure must dispose of sound channels that are marked for disposal. Listing 2-26 defines such a routine.

Listing 2-26 Disposing of channels that have been marked for disposal

```
PROCEDURE MyCleanUpTrackedChans;
CONST
    kQuietNow = TRUE;        {need to quiet channel?}
VAR
    index:      Integer;
    myErr:      OSErr;
BEGIN
    FOR index := 1 TO kMaxNumSndChans DO      {go through all channels}
        WITH gSndChans[index] DO
```

Sound Manager

```

IF mustDispose THEN                                {check global flag}
BEGIN                                              {channel needs disposal}
  IF gSndChans[index].itsData <> NIL THEN
  BEGIN                                           {release other data}
    HUnlock(gSndChans[index].itsData);
    HPurge(gSndChans[index].itsData);
  END;
                                                    {free channel-related memory}
  myErr := MyDisposeSndChannel(sndChan, kQuietNow);
  sndChan := NIL;                                {set pointer to NIL}
  mustDispose := FALSE;                          {reset global flag}
  IF myErr <> noErr THEN
    DoError(myErr);
END;
END;

```

The `MyCleanUpTrackedChans` procedure defined in Listing 2-26 works just like the `MyCheckSndChan` procedure defined in Listing 2-20, but instead of checking a single global flag, it checks the flag associated with each allocated sound channel. Now that you have defined such a procedure, you can easily write a routine to stop sound in all active channels (for example, if your application receives a suspend event). Simply set the `mustDispose` flag on all sound channels that are allocated (that is for all channels that are not `NIL`) and then call `MyCleanUpTrackedChans`. Note, however, that when the `MyCleanUpTrackedChans` procedure disposes of a sound channel processing a play from disk, the completion routine will be called and will thus set the `mustDispose` flag to `TRUE`. Thus, the `mustDispose` flag must be reset to `FALSE` *after* the sound channel has been disposed. Otherwise, the `MyCleanUpTrackedChans` procedure would try to dispose of the same sound channel again when the application called it from its main event loop.

Parsing Sound Resources and Sound Files

This section explains how you can parse sound resources and sound files to find the component of a sound resource or sound file that contains information about the sound. For sound resources, this information is stored in the sound header. In addition to obtaining information about a sound from a sound header, you might need a pointer to a sound header to use any of several low-level sound commands. For sound files, information is stored in the Form and Common Chunks. This section shows how you can find those chunks and extract information from them.

Note

The techniques shown in this section assume that you are familiar with the format of sound resources and sound files. See “Sound Storage Formats” beginning on page 2-73 for complete information on sound storage formats. ♦

Obtaining a Pointer to a Sound Header

This section shows how you can obtain a pointer to a sound header stored in a sound resource. You can use this pointer to obtain information about the sound. You also need a pointer to a sound header to install a sampled sound as a voice in a channel (as described in “Installing Voices Into Channels” on page 2-43) and to play sounds using low-level sound commands (as described below and in the next section). You can use a technique similar to the one described in this section if you wish to obtain a pointer to wave-table data that is stored in a sound resource.

Sound Manager versions 3.0 and later include the `GetSoundHeaderOffset` function that you can use to locate a sound header embedded in a sound resource. Listing 2-27 shows how to call the `GetSoundHeaderOffset` function and then pass the returned offset to the `bufferCmd` sound command, to play a sampled sound using low-level Sound Manager routines.

Listing 2-27 Playing a sound resource

```

FUNCTION MyPlaySampledSound (chan: SndChannelPtr; sndHandle: Handle): OSErr;
VAR
    myOffset:      LongInt;
    mySndCmd:      SndCommand;          {a sound command}
    myErr:         OSErr;
BEGIN
    myErr := GetSoundHeaderOffset(sndHandle, myOffset);
    IF myErr = noErr THEN
        BEGIN
            HLock(sndHandle);
            mySndCmd.cmd := bufferCmd;          {command is bufferCmd}
            mySndCmd.param1 := 0;              {unused with bufferCmd}
            mySndCmd.param2 := LongInt(ORD4(sndHandle^) + myOffset);
            myErr := SndDoImmediate(chan, mySndCmd);
        END;
    MyPlaySampledSound := myErr;
END;

```

If the `GetSoundHeaderOffset` function is not available but you still need to obtain a pointer to a sound header, you can use the function `MyGetSoundHeaderOffset` defined in Listing 2-28. The function defined there traverses a sound resource until it reaches the sound data. It returns, in the `offset` parameter, the offset in bytes from the beginning of a sound resource to the sound header.

Sound Manager

IMPORTANT

The `GetSoundHeaderOffset` function is available in Sound Manager versions 3.0 and later. As a result, you'll need to use the techniques illustrated in Listing 2-28 only if you want your application to find a sound header when earlier versions of the Sound Manager are available. ▲

Listing 2-28 Obtaining the offset in bytes to a sound header

```

FUNCTION MyGetSoundHeaderOffset (sndHdl: Handle; VAR offset: LongInt): OSErr;
TYPE
  Snd1Header =                               {format 1 'snd ' resource header}
  RECORD
    format:      Integer;                     {format of resource}
    numSynths:   Integer;                     {number of data types}
                                                    {synths, init option follow}
  END;
  Snd1HdrPtr = ^Snd1Header;
  Snd2Header =                               {format 2 'snd ' resource header}
  RECORD
    format:      Integer;                     {format of resource}
    refCount:   Integer;                     {for application use}
  END;
  Snd2HdrPtr = ^Snd2Header;
  IntPtr = ^Integer;                          {for type coercion}
  SndCmdPtr = ^SndCommand;                    {for type coercion}
VAR
  myPtr:      Ptr;                            {to navigate resource}
  myOffset:   LongInt;                        {offset into resource}
  numSynths:  Integer;                        {info about resource}
  numCmds:    Integer;                        {info about resource}
  isDone:     Boolean;                        {are we done yet?}
  myErr:      OSErr;
BEGIN
  {Initialize variables.}
  myOffset := 0;                              {return 0 if no sound header found}
  myPtr := Ptr(sndHdl^);                       {point to start of resource data}
  isDone := FALSE;                             {haven't yet found sound header}
  myErr := noErr;

  {Skip everything before sound commands.}
  CASE Snd1HdrPtr(myPtr)^.format OF
    firstSoundFormat:                          {format 1 'snd ' resource}
      BEGIN                                     {skip header start, synth ID, etc.}

```

Sound Manager

```

    numSynths := Snd1HdrPtr(myPtr)^.numSynths;
    myPtr := Ptr(ORD4(myPtr) + SizeOf(Snd1Header));
    myPtr := Ptr(ORD4(myPtr) +
                numSynths * (SizeOf(Integer) + SizeOf(LongInt)));
END;
secondSoundFormat:           {format 2 'snd ' resource}
    myPtr := Ptr(ORD4(myPtr) + SizeOf(Snd2Header));
OTHERWISE                     {unrecognized resource format}
BEGIN
    myErr := badFormat;
    isDone := TRUE;
END;
END;

{Find number of commands and move to start of first command.}
numCmds := IntPtr(myPtr)^;
myPtr := Ptr(ORD4(myPtr) + SizeOf(Integer));

{Search for bufferCmd or soundCmd to obtain sound header.}
WHILE (numCmds >= 1) AND (NOT isDone) DO
BEGIN
    IF (IntPtr(myPtr)^ = bufferCmd + dataOffsetFlag) OR
        (IntPtr(myPtr)^ = soundCmd + dataOffsetFlag) THEN
    BEGIN
        {bufferCmd or soundCmd found}
        {copy offset from sound command}
        myOffset := SndCmdPtr(myPtr)^.param2;
        isDone := TRUE;           {get out of loop}
    END
    ELSE
    BEGIN
        {soundCmd or bufferCmd not found}
        {move to next command}
        myPtr := Ptr(ORD4(myPtr) + SizeOf(SndCommand));
        numCmds := numCmds - 1;
    END;
END; {WHILE}

offset := myOffset;           {return offset}
MyGetSoundHeaderOffset := myErr; {return result code}
END;

```

The `MyGetSoundHeaderOffset` function defined in Listing 2-28 begins by initializing several variables, including a pointer that it sets to point to the beginning of the data contained in the sound resource. Then, after determining whether the sound resource is

Sound Manager

format 1 or format 2, the function skips data contained in the format 1 'snd' resource header or in the format 2 'snd' resource header, as appropriate.

Note

Do not confuse the format 1 or format 2 'snd' header with the sound header the `MyGetSoundHeaderOffset` function defined in Listing 2-28 is designed to find. A sound header contains information about the sampled-sound data stored in a sound resource; a sound resource header contains information about the format of the sound resource. ♦

After skipping information in the sound resource header, `MyGetSoundHeaderOffset` simply looks through all sound commands in the resource for a `bufferCmd` or `soundCmd` command, either of which must contain the offset from the beginning of the resource to the sound header in its `param2` field. If the given sound resource contains no sound header (and thus no sampled-sound data), the `MyGetSoundHeaderOffset` function returns an error and sets the `offset` variable parameter to 0.

After using the `MyGetSoundHeaderOffset` function to obtain an offset to the sound header, you can easily obtain a pointer to a sound header. Note, however, that because a handle to a sound resource is contained in a relocatable block, you must lock the relocatable block before you obtain a pointer to a sound header, and you must not unlock it until you are through using the pointer. Listing 2-29 demonstrates how you can convert an offset to a sound header into a pointer to a sound header after locking a relocatable block.

Listing 2-29 Converting an offset to a sound header into a pointer to a sound header

```
FUNCTION MyGetSoundHeader (sndHandle: Handle): SoundHeaderPtr;
VAR
  myOffset:   LongInt;           {offset to sound header}
  myErr:      OSErr;
BEGIN
  HLockHi(sndHandle);           {lock data in high memory}
                                {compute offset to sound header}
  myErr := MyGetSoundHeaderOffset(sndHandle, myOffset);
  IF myErr <> noErr THEN
    MyGetSoundHeader := NIL      {no sound header in resource}
  ELSE
                                {compute address of sound header}
    MyGetSoundHeader := SoundHeaderPtr(ORD4(sndHandle^) + myOffset);
END;
```

The `MyGetSoundHeader` function defined in Listing 2-29 locks the sound handle you pass it in high memory and then attempts to find an offset to the sound header in the sound handle. If the `MyGetSoundHeaderOffset` function defined in Listing 2-28 returns an offset of 0, then `MyGetSoundHeader` returns a `NIL` pointer to a sound

header; otherwise, it returns a pointer that remains valid as long as you do not unlock the sound handle.

The `MyGetSoundHeader` function returns a pointer to a sampled sound header even if the sound header is actually an extended sound header or a compressed sound header. Thus, before accessing any other fields of the sound header, you should test the `encode` field of the sound header to determine what type of sound header it is. Then, if the sound header is, for example, an extended sound header, cast the sampled sound header to an extended sound header. Then you can access any of the fields of the extended sound header. For an example of this technique, see Listing 2-16 on page 2-44.

Playing Sounds Using Low-Level Routines

Once you obtain a pointer to a sampled sound header, you can use the `bufferCmd` sound command to play a sound without using the high-level Sound Manager routines. Many sampled-sound resources include `bufferCmd` commands, so the high-level Sound Manager routines often issue the `bufferCmd` command indirectly. Thus, you might in some cases be able to make your application slightly more efficient by issuing the `bufferCmd` command directly. Also, you might issue a `bufferCmd` command directly if you want the Sound Manager to ignore other parts of a sound resource.

Finally, you might issue `bufferCmd` commands directly if you want your application to be able to play a large sound resource without loading the entire resource at once. By issuing several successive `bufferCmd` commands, you can play a large sound resource using a small buffer. In this case, each buffer must contain a sampled sound header. In most cases, the sound will play smoothly, without audible gaps. It's generally easier, however, to play large sampled sounds from disk by using the play-from-disk routines or the `SndPlayDoubleBuffer` function. See "Managing Double Buffers" on page 2-147 for complete details.

Note

Using the `bufferCmd` command to play several consecutive compressed samples on the Macintosh Plus, the Macintosh SE, or the Macintosh Classic is not guaranteed to work without an audible pause or click. ♦

The pointer in the `param2` field of a `bufferCmd` command is the location of a sampled sound header. A `bufferCmd` command is queued in the channel until the preceding commands have been processed. If the `bufferCmd` command is contained within an `'snd'` resource, the high bit of the command must be set. If the sound was loaded in from an `'snd'` resource, your application is expected to unlock this resource and allow it to be purged after using it. Listing 2-30 shows how your application can play a sampled sound stored in a resource using the `bufferCmd` command.

Listing 2-30 Playing a sound using the `bufferCmd` command

```

FUNCTION MyLowLevelSampledSndPlay (chan: SndChannelPtr; sndHandle: Handle):
                                OSErr;

CONST
    kWaitIfFull = TRUE;           {wait for room in queue?}
VAR
    mySndHeader:   SoundHeaderPtr;
    mySndCmd:      SndCommand;    {a sound command}
BEGIN
    mySndHeader := MyGetSoundHeader(sndHandle);
    WITH mySndCmd DO
    BEGIN
        cmd := bufferCmd;         {command is bufferCmd}
        param1 := 0;              {unused with bufferCmd}
        param2 := LongInt(mySndHeader); {pointer to sound header}
    END;
    IF mySndHeader <> NIL THEN
        MyLowLevelSampledSndPlay :=
            SndDoCommand(chan, mySndCmd, NOT kWaitIfFull)
    ELSE
        MyLowLevelSampledSndPlay := badFormat;
    END;
END;

```

For the `MyLowLevelSampledSndPlay` function defined in Listing 2-30 to play a sound, the channel passed to it must already be configured to play sampled-sound data. Otherwise, the function returns a `badChannel` result code. Also, because the `bufferCmd` command works asynchronously, you might want to associate a callback procedure with the sound channel when you create the channel. For more information on playing sounds asynchronously, see “Playing Sounds Asynchronously” on page 2-46.

You can use the `bufferCmd` command to handle compressed sound samples in addition to sounds that are not compressed. To expand and play back a buffer of compressed samples, you pass the Sound Manager a `bufferCmd` command where `param2` points to a compressed sound header.

To play sampled sounds that are not compressed, pass `bufferCmd` a standard or extended sound header. The extended sound header can be used for stereo sampled sounds. The standard sampled sound header is used for all other noncompressed sampled sounds.

Finding a Chunk in a Sound File

Sound files are not as tightly structured as sound resources. As explained in “Sound Files” on page 2-81, the chunks in a sound file can appear in any order, except that the Form Chunk is always first. Most information about a sampled sound stored in a sound file is contained in the Common Chunk. Thus, to be able to access this information, you

Sound Manager

must be able to find a particular kind of chunk in a sound file. Listing 2-31 defines a procedure that you can use to find the location of the first chunk of a specified type beginning at the chunk you specify.

IMPORTANT

The techniques illustrated in this section are provided primarily to help you understand the structure of sound files. Most sound-producing applications don't need to parse sound files. ▲

Listing 2-31 Finding a chunk in a sound file

```

FUNCTION MyFindChunk (myFile: Integer;           {file reference number}
                    myChunkSought: ID;         {ID of chunk sought}
                    startPos: LongInt;        {file position to start at}
                    VAR chunkFPos: LongInt) {file position of found chunk}
                    : OSErr;

VAR
    myLength:           LongInt;           {number of bytes to read}
    myChunkHeader:     ChunkHeader;       {characteristics of chunk}
    found:             Boolean;           {flag variable}
    myErr:             OSErr;             {error from File Manager calls}
BEGIN
    found := FALSE;                       {initialize flag variable}
                                           {set file mark at start}
    myErr := SetFPos(myFile, fsFromStart, startPos);

    {Search file's chunks for desired chunk ID.}
    WHILE (NOT found) AND (myErr = noErr) DO
    BEGIN                                  {check current chunk}
        myLength := SizeOf(myChunkHeader);
        {Load chunk header.}
        myErr := FSRead(myFile, myLength, @myChunkHeader);
        IF myErr = noErr THEN              {chunk header loaded okay}
            IF myChunkHeader.ckID = myChunkSought THEN
            BEGIN
                found := TRUE;             {chunk has been found}
                                           {find position in file}
                myErr := GetFPos(myFile, chunkFPos);
                                           {compute chunk's start position}
                chunkFPos := chunkFPos - SizeOf(myChunkHeader);
            END
        ELSE
        BEGIN                               {move to next chunk}
            IF myChunkHeader.ckID = ID(FormID) THEN

```

Sound Manager

```

        {Adjust Form Chunk's size to size of formType field.}
        myChunkHeader.ckSize := SizeOf(ID);
    IF myChunkHeader.ckSize MOD 2 = 1 THEN
        {Compensate for pad byte.}
        myChunkHeader.ckSize := myChunkHeader.ckSize + 1;
        myErr := SetFPos(myFile, fsFromMark, myChunkHeader.ckSize);
    END;
END; {WHILE}
MyFindChunk := myErr;
END;
```

The `MyFindChunk` function defined in Listing 2-31 accepts four parameters. The `myFile` parameter is the file reference number of an open sound file. (For information on file reference numbers, see *Inside Macintosh: Files*.) In the `myChunkSought` parameter, you pass the ID of the type of chunk you wish to find. For example, you might pass `ID(FormID)` to find the Form Chunk. The third parameter, `startPos`, is the file position at which `MyFindChunk` should start searching for a chunk. This file position must be the beginning of a chunk. To start at the beginning of a file, specify 0. Finally, if the `MyFindChunk` function is successful, it returns in the `chunkFPos` parameter the file position of the first chunk of the specified type that it found. If the function is unsuccessful, it returns the appropriate File Manager result code (such as an end-of-file error) and the `chunkFPos` parameter is undefined.

The `MyFindChunk` function works by looking at each chunk of the sound file, beginning at the file position `startPos` and checking to see if the chunk is of the type sought. If a chunk matches, the `MyFindChunk` function returns the file position of the start of the chunk; otherwise, the function moves onto the next chunk. For each chunk, the `MyFindChunk` function reads in the chunk header, checks for a match, and then moves to the next chunk.

The `MyFindChunk` function moves from one chunk to the next by identifying the size of the current chunk, not including the chunk header, from the `ckSize` field of the chunk header. Whenever you parse sound files, you should always use the `ckSize` field of the chunk header to determine the size of a chunk if the size of the chunk could vary in size. The `MyFindChunk` function adjusts the value in the `ckSize` field before advancing to the next chunk in two cases. First, the `ckSize` field for the Form Chunk reflects the size of the entire sound file, so this function changes it to the size of the `formType` field so that the function does not skip the file's local chunks. Second, if the `ckSize` field is odd, 1 byte is added because the number of bytes in a chunk is always even.

After using the `MyFindChunk` function defined in Listing 2-31, you might still need to read the data contained in a chunk into memory. For example, you might read in the Form and Common Chunks to obtain information about a sound file. Listing 2-32 uses the `MyFindChunk` function to find a chunk in a sound file, allocates an appropriately sized block of memory for that chunk, and reads the chunk into that block.

Listing 2-32 Loading a chunk from a sound file

```

FUNCTION MyGetChunkData (myFile: Integer;           {file reference number}
                        myChunkSought: ID;         {ID of chunk sought}
                        startPos: LongInt);        {file position to start at}
                        Ptr;                       {pointer to data or NIL}

VAR
  myFPos:           LongInt;           {position in file}
  myLength:         LongInt;           {number of bytes to read}
  myChunkHeader:   ChunkHeader;       {characteristics of a chunk}
  myChunkData:     Ptr;                {pointer to chunk data}
  myErr:           OSErr;

BEGIN
  myChunkData := NIL;                  {initialize variable}
  myErr := MyFindChunk(myFile, myChunkSought, startPos, myFPos);
  IF myErr = noErr THEN
    {move to start of chunk}
    myErr := SetFPos(myFile, fsFromStart, myFPos);
  IF myErr = noErr THEN
    BEGIN                               {determine how much data to copy}
      myLength := SizeOf(ChunkHeader);
      myErr := FSRead(myFile, myLength, @myChunkHeader);
      IF myChunkHeader.ckID = ID(FormID) THEN
        myChunkHeader.ckSize := SizeOf(ID);   {don't return local chunks}
      myLength := myChunkHeader.ckSize + SizeOf(ChunkHeader);
      IF myErr = noErr THEN
        {return to chunk's start}
        myErr := SetFPos(myFile, fsFromStart, myFPos);
    END;
  IF myErr = noErr THEN
    BEGIN                               {read chunk data into RAM}
      myChunkData := NewPtr(myLength);
      IF myChunkData <> NIL THEN
        myErr := FSRead(myFile, myLength, myChunkData);
    END;
  IF myErr <> noErr THEN
    IF myChunkData <> NIL THEN
      DisposePtr(myChunkData);
  MyGetChunkData := myChunkData;
END;

```

The `MyGetChunkData` function defined in Listing 2-32 attempts to find a chunk in a file. If it finds the chunk, it reads the chunk header to determine the chunk's size, and if the chunk is the Form Chunk, adjusts the chunk size so that the sound file's local chunks are

Sound Manager

not included in the chunk size. Then the function attempts to allocate memory for the chunk and read the chunk into the memory. If a problem occurs at any time, the function simply returns `NIL`.

Note

The format of a sound file might not be the same as its operating-system type. In particular, a file might have an operating-system type `'AIFC'` but be formatted as an AIFF file because the sampled-sound data contained in the file is noncompressed. ♦

Compressing and Expanding Sounds

Some of the capabilities provided by MACE are transparently available to your application. For example, if you pass the `SndPlay` function a handle to an `'snd'` resource that contains a compressed sampled sound, the Sound Manager automatically expands the sound data for playback in real time. Your application does not need to know whether the `'snd'` resource contains compressed or noncompressed samples when it calls `SndPlay`. This is because sufficient information is in the resource itself to allow the Sound Manager to determine whether it should expand the data samples.

However, aside from expansion playback, all of the MACE capabilities need to be specifically requested by your application. For example, you can use the procedure `Comp3to1` or `Comp6to1` if you want to compress a sampled sound (for example, to create an `'snd'` resource containing compressed audio data). You can use the procedures `Exp1to3` and `Exp1to6` to expand compressed audio data.

All of these procedures require you to specify both an input and an output buffer, from and to which the sampled-sound data to be converted is read and written. Your application must allocate the appropriate amount of storage for each buffer. For example, if you want to expand a buffer of compressed monophonic sampled-sound data by using `Exp1to6`, the output buffer must be at least six times the size of the input buffer.

The MACE compression and expansion routines can work on only one channel of sound. The `numChannels` parameter of all four procedures allows you to specify how many channels are in the original sample, and the `whichChannel` parameter allows you to specify which channel you wish to compress or expand. Because the MACE routines can compress or expand only one channel of sound, you must make adjustments when allocating an output buffer for stereo sound. For example, if you are compressing two-channel sound using the `Comp3to1` procedure, your output buffer need only be one-sixth the size of your input buffer.

Often when compressing polyphonic sound, being able to compress only one channel is not a problem, because you lose sound quality during compression anyway. However, you might at times wish to maintain more than one channel of a multichannel sound even after compression and expansion. For example, two channels of a stereo sound might be quite different and might both be necessary to achieve a full sound after expansion. In these cases, you can compress each channel of a multichannel sound individually and then manually interleave the samples on a packet basis. When you

expand polyphonic compressed sound data, you must interleave the channels of sound on a sample frame basis.

The MACE routines work only with sampled-sound data in offset binary format. If you are compressing data in a sound file, you must convert that data from linear, two's complement format to binary offset format before compression.

When calling the MACE routines, you can also specify addresses of two small buffers (128 bytes each) that the Sound Manager uses to maintain state information about the compression or expansion process. When you first call a MACE routine, the state buffers should be filled with zeros to initialize the state information. When you subsequently call another MACE routine, you can use the same state buffers. You can pass `NIL` for both buffers if you do not want to save state information across calls to the MACE routines. Listing 2-33 illustrates the use of the `Comp3to1` procedure when using state buffers.

Listing 2-33 Compressing audio data

```
PROCEDURE MyCompressBy3 (inBuf: Ptr; outBuf: Ptr; numSamp: LongInt);
CONST
    kStateBufferSize = 128;
VAR
    myInState:      Ptr;      {input state buffer}
    myOutState:    Ptr;      {output state buffer}
BEGIN
    myInState := NewPtrClear(kStateBufferSize);
    myOutState := NewPtrClear(kStateBufferSize);
    IF (myInState <> NIL) AND (myOutState <> NIL) THEN
        Comp3to1(inBuf, outBuf, numSamp, myInState, myOutState, 1, 1);
    END;
```

Because the last two parameters (`numChannels` and `whichChannel`) are both set to 1, `MyCompressBy3` compresses monophonic audio data.

In practice, compressing a sound resource or sound file is considerably more complex than calling the `MyCompressBy3` procedure defined in Listing 2-33. To compress a sound resource containing monophonic sampled-sound data, you would need to

- load the data into a handle and lock the handle
- ensure that the data in the handle is not already compressed by examining the sound header
- find a pointer to the sampled-sound data by examining the `samplePtr` field of the sound header
- allocate an output buffer of the appropriate size, taking into account that only one channel of the original data can be compressed
- compress the sampled-sound data by calling the `Comp3To1` procedure

Sound Manager

- determine the size that the header information (including, for example, sound commands and the sampled sound header excluding the sampled-sound data itself) will take in the resource by using the Sound Input Manager's `SetupSndHeader` function to create a sound resource header and sampled sound header with the same sample rate, base frequency, and other characteristics as the original sampled-sound data
- resize the handle so that it is large enough to contain both the non-sampled-sound data information and the compressed sound data
- fill this handle by first calling `SetupSndHeader` once again and by then copying the compressed sound data to the end of the header information
- update the resource file

Techniques for compressing sound files and for expanding both sound resources and sound files are analogous to that sketched here. Remember that after compressing or expanding each channel of polyphonic sampled-sound data, you must interleave frames of sound data, on a packet basis after compression or on a sample basis after expansion.

Using Double Buffers

The play-from-disk routines make extensive use of the `SndPlayDoubleBuffer` function. You can use this function in your application directly if you wish to bypass the normal play-from-disk routines. You might want to do this to maximize the efficiency of your application while maintaining compatibility with the Sound Manager. Or, you might define your own double-buffering routines so that your application can convert 16-bit sound data on disk to 8-bit data that all versions of the Sound Manager can play. By using `SndPlayDoubleBuffer` instead of the normal play-from-disk routines, you can specify your own doubleback procedure (that is, the algorithm used to switch back and forth between buffers) and customize several other buffering parameters.

IMPORTANT

`SndPlayDoubleBuffer` is a very low-level routine and is not intended for general use. In most cases, you should use the high-level Sound Manager routines (such as `SndPlay` or `SndStartFilePlay`) or standard sound commands (such as `bufferCmd`) to play sounds. You should use `SndPlayDoubleBuffer` only if you require very fine control over double buffering. Remember also that the `SndPlayDoubleBuffer` function is not always available. You'll need to ensure that it's available in the current operating environment before calling it. See "Testing for Multichannel Sound and Play-From-Disk Capabilities" beginning on page 2-35 for details. ▲

You call `SndPlayDoubleBuffer` by passing it a pointer to a sound channel (into which the double-buffered data is to be written) and a pointer to a sound double buffer header record. Here's an example:

```
myErr := SndPlayDoubleBuffer(mySndChan, @myDoubleHeader);
```

A sound double buffer header record has the following structure:

Sound Manager

```

TYPE SndDoubleBufferHeader =
PACKED RECORD
    dbhNumChannels: Integer;    {number of sound channels}
    dbhSampleSize: Integer;    {sample size, if noncompressed}
    dbhCompressionID: Integer; {ID of compression algorithm}
    dbhPacketSize: Integer;    {number of bits per packet}
    dbhSampleRate: Fixed;      {sample rate}
    dbhBufferPtr: ARRAY[0..1] OF SndDoubleBufferPtr;
                                {pointers to SndDoubleBuffer}
    dbhDoubleBack: ProcPtr;    {pointer to doubleback procedure}
END;

```

The values for the `dbhCompressionID`, `dbhNumChannels`, and `dbhPacketSize` fields are the same as those for the `compressionID`, `numChannels`, and `packetSize` fields of the compressed sound header, respectively.

The `dbhBufferPtr` array contains pointers to two records of type `SndDoubleBuffer`. These are the two buffers between which the Sound Manager switches until all the sound data has been sent into the sound channel. When the call to `SndPlayDoubleBuffer` is made, the two buffers should both already contain a nonzero number of frames of data.

IMPORTANT

The Sound Manager defines the data type `SndDoubleBufferHeader2` that is identical to the `SndDoubleBufferHeader` data type except that it contains the `dbhFormat` field (of type `OSType`) that defines a custom codec to be used to decompress the sound data. The `dbhFormat` field is used only if the `dbhCompressionID` field contains the value `fixedCompression`. See “Sound Double Buffer Header Records” beginning on page 2-111 for details. ▲

Here is the structure of a sound double buffer:

```

TYPE SndDoubleBuffer =
PACKED RECORD
    dbNumFrames: LongInt;      {number of frames in buffer}
    dbFlags: LongInt;         {buffer status flags}
    dbUserInfo: ARRAY[0..1] OF LongInt;
                                {for application's use}
    dbSoundData: PACKED ARRAY[0..0] OF Byte;
                                {array of data}
END;

```

The buffer status flags field for each of the two buffers might contain either of these values:

Sound Manager

```
CONST
    dbBufferReady      = $00000001;
    dbLastBuffer       = $00000004;
```

All other bits in the `dbFlags` field are reserved by Apple; your application should not modify them.

The following two sections illustrate how to fill out these data structures, create your two buffers, and define a doubleback procedure to refill the buffers when they become empty.

Setting Up Double Buffers

Before you can call `SndPlayDoubleBuffer`, you need to allocate two buffers (of type `SndDoubleBuffer`), fill them both with data, set the flags for the two buffers to `dbBufferReady`, and then fill out a record of type `SndDoubleBufferHeader` with the appropriate information. Listing 2-34 illustrates how you can accomplish these tasks.

Listing 2-34 Setting up double buffers

```
CONST
    kDoubleBufferSize = 4096;      {size of each buffer (in bytes)}
TYPE
    LocalVars =                    {variables used by the doubleback procedure}
    RECORD
        bytesTotal:    LongInt;    {total number of samples}
        bytesCopied:   LongInt;    {number of samples copied to buffers}
        dataPtr:       Ptr;        {pointer to sample to copy}
    END;
    LocalVarsPtr = ^LocalVars;

{This function uses SndPlayDoubleBuffer to play the sound specified.}
FUNCTION MyDBSndPlay (chan: SndChannelPtr; sndHeader: SoundHeaderPtr): OSErr;
VAR
    myVars:          LocalVars;
    myDblHeader:     SndDoubleBufferHeader;
    myDblBuffer:     SndDoubleBufferPtr;
    myStatus:        SCStatus;
    myIndex:         Integer;
    myErr:           OSErr;
BEGIN
    {Set up myVars with initial information.}
    myVars.bytesTotal := sndHeader^.length;
    myVars.bytesCopied := 0;          {no samples copied yet}
    myVars.dataPtr := Ptr(@sndHeader^.sampleArea[0]);
```

Sound Manager

```

                                                                    {pointer to first sample}
{Set up SndDoubleBufferHeader.}
WITH myDblHeader DO
BEGIN
    dbhNumChannels := 1;                {one channel}
    dbhSampleSize := 8;                {8-bit samples}
    dbhCompressionID := 0;            {no compression}
    dbhPacketSize := 0;                {no compression}
    dbhSampleRate := sndHeader^.sampleRate;
    dbhDoubleBack := @MyDoubleBackProc;
END;

FOR myIndex := 0 TO 1 DO                {initialize both buffers}
BEGIN
    {Get memory for double buffer.}
    myDblBuffer := SndDoubleBufferPtr(NewPtr(Sizeof(SndDoubleBuffer) +
                                                kDoubleBufferSize));

    IF myDblBuffer = NIL THEN
    BEGIN
        MyDBSndPlay := MemError;
        Exit(MyDBSndPlay);
    END;

    myDblBuffer^.dbNumFrames := 0;      {no frames yet}
    myDblBuffer^.dbFlags := 0;         {buffer is empty}
    myDblBuffer^.dbUserInfo[0] := LongInt(@myVars);

    {Fill buffer with samples.}
    MyDoubleBackProc(sndChan, myDblBuffer);

    {Store buffer pointer in header.}
    myDblHeader.dbhBufferPtr[myIndex] := myDblBuffer;
END;

{Start the sound playing.}
myErr := SndPlayDoubleBuffer(sndChan, @myDblHeader);
IF myErr <> noErr THEN
BEGIN
    MyDBSndPlay := myErr;
    Exit(MyDBSndPlay);
END;

{Wait for the sound's end by checking the channel status.}
REPEAT

```

Sound Manager

```

    myErr := SndChannelStatus(chan, sizeof(myStatus), @status);
UNTIL NOT myStatus.scChannelBusy;

{Dispose double buffer memory.}
FOR myIndex := 0 TO 1 DO
    DisposePtr(Ptr(myDblHeader.dbhBufferPtr[myIndex]));

MyDBSndPlay := noErr;
END;
```

The function `MyDBSndPlay` takes two parameters, a pointer to a sound channel and a pointer to a sound header. For information about obtaining a pointer to a sound header, see “Obtaining a Pointer to a Sound Header” on page 2-57. The `MyDBSndPlay` function reads the sound header to determine the characteristics of the sound to be played (for example, how many samples are to be sent into the sound channel). Then `MyDBSndPlay` fills in the fields of the double buffer header, creates two buffers, and starts the sound playing. The doubleback procedure `MyDoubleBackProc` is defined in the next section.

Writing a Doubleback Procedure

The `dbhDoubleBack` field of a double buffer header specifies the address of a doubleback procedure, an application-defined procedure that is called when the double buffers are switched and the exhausted buffer needs to be refilled. The doubleback procedure should have this format:

```

PROCEDURE MyDoubleBackProc (chan: SndChannelPtr;
                             exhaustedBuffer: SndDoubleBufferPtr);
```

The primary responsibility of the doubleback procedure is to refill an exhausted buffer of samples and to mark the newly filled buffer as ready for processing. Listing 2-35 illustrates how to define a doubleback procedure. Note that the sound channel pointer passed to the doubleback procedure is not used in this procedure.

This doubleback procedure extracts the address of its local variables from the `dbUserInfo` field of the double buffer record passed to it. These variables are used to keep track of how many total bytes need to be copied and how many bytes have been copied so far. Then the procedure copies at most a bufferfull of bytes into the empty buffer and updates several fields in the double buffer record and in the structure containing the local variables. Finally, if all the bytes to be copied have been copied, the buffer is marked as the last buffer.

Note

Because the doubleback procedure is called at interrupt time, it cannot make any calls that move memory either directly or indirectly. (Despite its name, the `BlockMove` procedure does not cause blocks of memory to move or be purged, so you can safely call it in your doubleback procedure, as illustrated in Listing 2-35.) ♦

Listing 2-35 Defining a doubleback procedure

```

PROCEDURE MyDoubleBackProc (chan: SndChannelPtr;
                             doubleBuffer: SndDoubleBufferPtr);

VAR
    myVarsPtr:          LocalVarsPtr;
    myNumBytes:         LongInt;
BEGIN
    {Get pointer to my local variables.}
    myVarsPtr := LocalVarsPtr(doubleBuffer^.dbUserInfo[0]);

    {Get number of bytes left to copy.}
    myNumBytes := myVarsPtr^.bytesTotal - myVarsPtr^.bytesCopied;

    {If the amount left is greater than double buffer size, limit the number }
    { of bytes to copy to the size of the buffer.}
    IF myNumBytes > kDoubleBufferSize THEN
        myNumBytes := kDoubleBufferSize;

    {Copy samples to double buffer.}
    BlockMove(myVarsPtr^.dataPtr, @doubleBuffer^.dbSoundData[0], myNumBytes);

    {Store number of samples in buffer and mark buffer as ready.}
    doubleBuffer^.dbNumFrames := myNumBytes;
    doubleBuffer^.dbFlags := BOR(doubleBuffer^.dbFlags, dbBufferReady);

    {Update data pointer and number of bytes copied.}
    myVarsPtr^.dataPtr := Ptr(ORD4(myVarsPtr^.dataPtr) + myNumBytes);
    myVarsPtr^.bytesCopied := myVarsPtr^.bytesCopied + myNumBytes;

    {If all samples have been copied, then this is the last buffer.}
    IF myVarsPtr^.bytesCopied = myVarsPtr^.bytesTotal THEN
        doubleBuffer^.dbFlags := BOR(doubleBuffer^.dbFlags, dbLastBuffer);
END;

```

Sound Storage Formats

This section describes in detail the formats of sound resources and sound files, which are the two principal storage formats for sound data on Macintosh computers. In general, an application that uses the services provided by the Sound Manager and the Sound Input Manager to play and record sounds does not need to know how the sound data is

Sound Manager


organized in memory or on disk. For some special purposes, however, you might need the information in this section.

Sound Resources

A **sound resource** is a resource of type 'snd ' that contains sound commands and possibly also sound data. Sound resources are widely used by Macintosh applications that produce sounds. These resources provide a simple and portable way for you to incorporate sounds into your application. For example, the sounds that a user can select in the Sound control panel as the system alert sound are stored in the System file as 'snd ' resources.

There are two types of 'snd ' resources, known as format 1 and format 2. Figure 2-4 illustrates the structures of both kinds of 'snd ' resources.

Figure 2-4 The structure of 'snd ' resources



IMPORTANT


The format 2 'snd ' resource is obsolete. Your application should create only format 1 'snd ' resources. The format 2 'snd ' resource was designed for use by HyperCard and can be used with sampled-sound data only. ▲

Sound Manager

Resource IDs for 'snd' resources in the range 0 to 8191 are reserved for use by Apple Computer, Inc. The 'snd' resources numbered 1 through 4 are defined to be the standard system alert sounds, although more recent versions of system software have included more standard system alert sounds.

When a sound command contained in an 'snd' resource has associated sound data, the high bit of the command is set. This changes the meaning of the param2 field of the command from a pointer to a location in RAM to an offset value that specifies the offset in bytes from the resource's beginning to the location of the associated sound data (such as a sampled sound header). Figure 2-5 illustrates the location of this data offset bit.

Figure 2-5 The location of the data offset bit



The offset bit is used only by sound commands that are stored in sound resources of type 'snd' and that have associated sound data (that is, sampled-sound or wave-table data).

You can use a constant to access that flag.

```
CONST
    dataOffsetFlag    = $8000; {sound command data offset bit}
```

If the dataOffsetFlag bit is not set, param2 is interpreted instead as a pointer to the location in memory (outside the sound resource) where the data is located.

The first few bytes of the resource contain 'snd' header information and are a different size for each format. An audio data type specified in a format 1 'snd' requires 6 bytes. The number of data types multiplied by 6 is added to this offset. The number of commands multiplied by 8 bytes, the size of a sound command, is added to the offset.

The Format 1 Sound Resource

Figure 2-4 shows the fields of a format 1 'snd' resource. A format 1 'snd' resource header contains information about the format of the resource (namely, 1), the data type, and the initialization options for that data type. A format 1 'snd' resource contains sound commands and might also contain the actual sound data for wave-table sounds or sampled sounds. Note that if a sound resource includes sampled-sound data, then part of the sound data section is devoted to a sound header that describes the sampled-sound data in the remainder of the sound data section.

Sound Manager

If an 'snd' resource specifies a data type, it can supply an initialization option in the field immediately following the type. You specify the number of commands in the resource in the number of sound commands field. The sound commands follow, in the order in which they should be sent to the sound channel.

The format 1 'snd' resource might contain only a sequence of commands describing a sound. In this case, the number of data types should be 0, and there should be no data type specification or initialization option in the 'snd' resource. This allows the 'snd' resource to be used with any kind of sound data.

Listing 2-36 shows the output of the MPW tool DeRez when applied to the 'snd' resource with resource ID 1 contained in the System file.

Listing 2-36 A format 1 'snd' resource

```
data 'snd' (1, "Simple Beep", purgeable) {
    /*the sound resource header*/
    $"0001" /*format type*/
    $"0001" /*number of data types*/
    $"0001" /*square-wave data*/
    $"00000000" /*initialization option*/
    /*the sound commands*/
    $"001B" /*number of sound commands (27)*/
    $"002C" /*command 1--timbreCmd 090 000*/
    $"005A00000000"
    $"002B" /*command 2--ampCmd 224 000*/
    $"00E000000000"
    $"002A" /*command 3--freqCmd 000 069*/
    $"000000000045"
    $"000A" /*command 4--waitCmd 040 000*/
    $"002800000000"
    $"002B" /*command 5--ampCmd 200 000*/
    $"00C800000000"
    /*commands 6 through 26 are omitted; they are */
    /* alternating pairs of waitCmd and ampCmd commands */
    /* where the first parameter of ampCmd has the */
    /* values 192, 184, 176, 168, 160, 144, 128, 96, */
    /* 64, and 32*/
    $"002B" /*command 27--ampCmd 000 000*/
    $"000000000000"
};
```

As you can see, the Simple Beep is actually a rather sophisticated sound, in which the loudness (or amplitude) of the beep gradually decreases from an initial value of 224 to 0.

Notice that the sound shown in Listing 2-36 is defined using square-wave data and is completely determined by a sequence of specific commands. (“Play an A at loudness 224, wait 20 milliseconds, play it at loudness 200....”) Often, an 'snd' resource consists only of a single sound command (usually the `bufferCmd` command) together with data that describes a sampled sound to be played. Listing 2-37 shows an example like this.

Listing 2-37 A format 1 'snd' resource containing sampled-sound data

```
data 'snd' (19068, "hello daddy", purgeable) {
    /*the sound resource header*/
    "$0001" /*format type*/
    "$0001" /*number of data types*/
    "$0005" /*sampled-sound data*/
    "$00000080" /*initialization option: initMono*/
    /*the sound commands*/
    "$0001" /*number of sound commands that follow (1)*/
    "$8051" /*command 1--bufferCmd*/
    "$0000" /*param1 = 0*/
    "$00000014" /*param2 = offset to sound header (20 bytes)*/
    /*the sampled sound header*/
    "$00000000" /*pointer to data (it follows immediately)*/
    "$00000BB8" /*number of bytes in sample (3000 bytes)*/
    "$56EE8BA3" /*sampling rate of this sound (22 kHz)*/
    "$000007D0" /*starting of the sample's loop point*/
    "$00000898" /*ending of the sample's loop point*/
    "$00" /*standard sample encoding*/
    "$3C" /*baseFrequency at which sample was taken*/
    /*the sampled-sound data*/
    "$80 80 81 81 81 81 81 81 80 80 80 80 80 81 82 82"
    "$82 83 82 82 81 80 80 7F 7F 7F 7E 7D 7D 7D 7C 7C"
    "$7C 7C 7D 7D 7D 7D 7E 7F 80 80 81 81 82 82 83 83"
    "$83 83 82 81 81 80 80 81 81 81 81 81 82 81 81 80"
    "$80 80 81 81 81 83 83 83 82 81 81 80 7F 7E 7D 7D"
    "$7F 7F 7F 7F 7E 7F 7F 7F 7F 7F 7F 7F 7F 7F 80"
    /*rest of data omitted in this example*/
};
```

This 'snd' resource indicates that the sound is defined using sampled-sound data. The resource includes a call to a single sound command, the `bufferCmd` command. The offset bit of the command number is set to indicate that the sound data is contained in the resource itself. Following the command and its two parameters is the sampled sound header, the first part of which contains important information about the sample. The second parameter to the `bufferCmd` command indicates the offset from the beginning of the resource to the sampled sound header, in this case 20 bytes. After the sound

Sound Manager

commands, this resource includes a sampled sound header, which includes the sampled-sound data. The format of a sampled sound header is described in “Sound Header Records” on page 2-104.

For compressed sound data, the sampled sound header is replaced by a compressed sampled sound header. Listing 2-38 illustrates the structure of an 'snd ' resource that contains compressed sound data.

Listing 2-38 An 'snd ' resource containing compressed sound data

```
data 'snd ' (9004, "Raisa's Cry", purgeable) {
    /*the sound resource header*/
    $"0001"      /*format type*/
    $"0001"      /*number of data types*/
    $"0005"      /*first data type*/
    $"00000380" /*initialization option: initMACE3 + initMono*/
    /*the sound command*/
    $"0001"      /*number of sound commands that follow (1)*/
    $"8051"      /*cmd: bufferCmd*/
    $"0000"      /*param1: unused*/
    $"00000014" /*param2: offset to sound header (20 bytes)*/
    /*the compressed sampled sound header*/
    $"00000000" /*pointer to data (it follows immediately)*/
    $"00000001" /*number of channels in sample*/
    $"56EE8BA3" /*sampling rate of this sound (22 kHz)*/
    $"00000000" /*starting of the sample's loop point; not used*/
    $"00000000" /*ending of the sample's loop point; not used*/
    $"FE"       /*compressed sample encoding*/
    $"00"       /*baseFrequency; not used*/
    $"00006590" /*number of frames in sample (26,000)*/
    $"400DADDD1745D145826B"
                /*AIFFSampleRate (22 kHz in extended type)*/
    $"00000000" /*markerChunk; NIL for 'snd ' resource*/
    $"4D414333" /*format; MACE 3:1 compression*/
    $"00000000" /*futureUse2; NIL for 'snd ' resource*/
    $"00000000" /*stateVars; NIL for 'snd ' resource*/
    $"00000000" /*leftOverBlockPtr; not used here*/
    $"FFFF"     /*compressionID, -1 means use format field*/
    $"0010"     /*packetSize, packetSize for 3:1 is 16 bits*/
    $"0000"     /*snthID is 0*/
    $"0008"     /*sampleSize, sound was 8-bit before processing*/
    $"2F 85 81 32 64 87 33 86" /*the compressed sound data*/
    $"6F 48 6D 65 72 6B 82 88"
    $"91 FE 8D 8E 86 4E 7C E9"
```

Sound Manager

```

    $"6F 6D 71 70 7E 79 4F 83"
    $"59 8F 8F 65" /*rest of data omitted in this example*/
};

```

This resource has the same general structure as the 'snd' resource illustrated in Listing 2-36. The principal difference is that the standard sound header is replaced by the compressed sound header. This example resource specifies a monophonic sound compressed by using the 3:1 compression algorithm. A multichannel compressed sound's data would be interleaved on a packet basis. See “Compressed Sound Header Records” beginning on page 2-108 for a complete explanation of the compressed sound header.

As you've seen, it is not always necessary to specify 'snd' resources by listing the raw data stream contained in them; indeed, for certain types of format 1 'snd' resources, it can be easier to supply a resource specification like the one given in Listing 2-39.

Listing 2-39 A resource specification

```

resource 'snd' (9000, "Nathan's Beep", purgeable) {
    FormatOne {
        { /*array of data types: 1 element*/
            /*[1]*/
            squareWaveSynth, 0
        }
    },
    { /*array SoundCmds: 3 elements*/
        /*[1]*/ noData, timbreCmd {90},
        /*[2]*/ noData, freqDurationCmd {480, $00000045},
        /*[3]*/ noData, quietCmd {},
    },
    { /*array DataTables: 0 elements*/
    };
};

```

When you pass a handle to this resource to the `SndPlay` function, three commands are executed by the Sound Manager: a `timbreCmd` command, a `freqDurationCmd` command, and a `quietCmd` command. The sound specified in Listing 2-39 is just like the Simple Beep, except that there is no gradual reduction in the loudness. Listing 2-40 shows a resource specification for the Simple Beep.

Listing 2-40 A resource specification for the Simple Beep

```

resource 'snd' (9001, "Copy of Simple Beep", purgeable) {
    FormatOne {
        { /*array of data types: 1 element*/

```

Sound Manager

```

        /*[1]*/
        squareWaveSynth, 0
    }
},
{ /*array SoundCmds: 27 elements*/
    /*[1]*/      nodata, timbreCmd {90},
    /*[2]*/      nodata, ampCmd {224},
    /*[3]*/      nodata, freqCmd {69},
    /*[4]*/      nodata, waitCmd {40},
    /*[5]*/      nodata, ampCmd {200},
    /*[6]*/      nodata, waitCmd {40},
    /*[7]*/      nodata, ampCmd {192},
    /*[8]*/      nodata, waitCmd {40},
    /*[9]*/      nodata, ampCmd {184},
    /*[10]*/     nodata, waitCmd {40},
    /*[11]*/     nodata, ampCmd {176},
    /*[12]*/     nodata, waitCmd {40},
    /*[13]*/     nodata, ampCmd {168},
    /*[14]*/     nodata, waitCmd {40},
    /*[15]*/     nodata, ampCmd {160},
    /*[16]*/     nodata, waitCmd {40},
    /*[17]*/     nodata, ampCmd {144},
    /*[18]*/     nodata, waitCmd {40},
    /*[19]*/     nodata, ampCmd {128},
    /*[20]*/     nodata, waitCmd {40},
    /*[21]*/     nodata, ampCmd {96},
    /*[22]*/     nodata, waitCmd {40},
    /*[23]*/     nodata, ampCmd {64},
    /*[24]*/     nodata, waitCmd {40},
    /*[25]*/     nodata, ampCmd {32},
    /*[26]*/     nodata, waitCmd {40},
    /*[27]*/     nodata, ampCmd {0},
},
{ /*array DataTables: 0 elements*/
}
};

```

The Format 2 Sound Resource

The `SndPlay` function can also play format 2 'snd' resources, which are designed for use only with sampled sounds. The `SndPlay` function supports this format by automatically opening a sound channel and using the `bufferCmd` command to send the data contained in the resource to the channel.

Sound Manager

Figure 2-4 illustrates the fields of a format 2 'snd' resource. The reference count field is for your application's use and is not used by the Sound Manager. The number of sound commands field and the sound command fields are the same as described in a format 1 resource. The last field of this resource contains the sampled sound. The first command should be either a `soundCmd` command or `bufferCmd` command with the data offset bit set in the command to specify the location of this sampled sound header.

Listing 2-41 shows a resource specification that illustrates the structure of a format 2 'snd' resource.

Listing 2-41 A format 2 'snd' resource

```
data 'snd' (9003, "Pig Squeal", purgeable) {
    /*the sound resource header*/
    "$0002"          /*format type*/
    "$0000"          /*reference count for application's use*/
    /*the sound command*/
    "$0001"          /*number of sound commands that follow (1)*/
    "$8051"          /*command 1--bufferCmd*/
    "$0000"          /*param1 = 0*/
    "$0000000E"      /*param2 = offset to sound header (14 bytes)*/
    /*the sampled sound header*/
    "$00000000"      /*pointer to data (it follows immediately)*/
    "$00000BB8"      /*number of bytes in sample (3000 bytes)*/
    "$56EE8BA3"      /*sampling rate of this sound (22 kHz)*/
    "$000007D0"      /*starting of the sample's loop point*/
    "$00000898"      /*ending of the sample's loop point*/
    "$00"            /*standard sample encoding*/
    "$3C"            /*baseFrequency at which sample was taken*/
    "$80 80 81 82 84 87 93 84" /*the sampled-sound data*/
    "$6F 68 6D 65 72 7B 82 88"
    "$91 8E 8D 8F 86 7E 7C 79"
    "$6F 6D 71 70 70 79 7F 81"
    "$89 8F 8D 8B" /*rest of data omitted in this example*/
};
```

Note

Remember that format 2 'snd' resources are obsolete. You should create only format 1 'snd' resources. ♦

Sound Files

This section describes in detail the structure of AIFF and AIFF-C files. Both of these types of sound files are collections of **chunks** that define characteristics of the sampled sound or other relevant data about the sound.

Sound Manager

Note

Most applications only need to read AIFF and AIFF-C files or to record sampled-sound data directly to them. You can both play and record AIFF and AIFF-C files without knowing the details of the AIFF and AIFF-C file formats, as explained in the chapter “Introduction to Sound on the Macintosh” in this book. Thus, the information in this section is for advanced programmers only. ♦

Currently, the AIFF and AIFF-C specifications include the following chunk types.

Chunk type	Description
Form Chunk	Contains information about the format of an AIFF or AIFF-C file and contains all the other chunks of such a file.
Format Version Chunk	Contains an indication of the version of the AIFF-C specification according to which this file is structured (AIFF-C only).
Common Chunk	Contains information about the sampled sound such as the sampling rate and sample size.
Sound Data Chunk	Contains the sample frames that comprise the sampled sound.
Marker Chunk	Contains markers that point to positions in the sound data.
Comments Chunk	Contains comments about markers in the file.
Sound Accelerator Chunk	Contains information intended to allow applications to accelerate the decompression of compressed audio data.
Instrument Chunk	Defines basic parameters that an instrument (such as a sampling keyboard) can use to play back the sound data.
MIDI Data Chunk	Contains MIDI data.
Audio Recording Chunk	Contains information pertaining to audio recording devices.
Application Specific Chunk	Contains application-specific information.
Name Chunk	Contains the name of the sampled sound.
Author Chunk	Contains one or more names of the authors (or creators) of the sampled sound.
Copyright Chunk	Contains a copyright notice for the sampled sound.
Annotation Chunk	Contains a comment.


The following sections document the four principal kinds of chunks that can occur in AIFF and AIFF-C files.

Chunk Organization and Data Types

An AIFF or AIFF-C file contains several different types of chunks. For example, there is a Common Chunk that specifies important parameters of the sampled sound, such as its size and sample rate. There is also a Sound Data Chunk that contains the actual audio samples. A chunk consists of some header information followed by some data. The

header information consists of a chunk ID number and a number that indicates the size of the chunk data. In general, therefore, a chunk has the structure shown in Figure 2-6.

Figure 2-6 The general structure of a chunk



The header information of a chunk has this structure:

```
TYPE ChunkHeader =
RECORD
    ckID:    ID;           {chunk type ID}
    ckSize:  LongInt;     {number of bytes of data}
END;
```

The `ckID` field specifies the chunk type. An ID is a 32-bit concatenation of any four printable ASCII characters in the range ' ' (space character, ASCII value \$20) through '~' (ASCII value \$7E). Spaces cannot precede printing characters, but trailing spaces are allowed. Control characters are not allowed. You can specify values for the four types of chunks described later by using these constants:

```
CONST
    FormID           = 'FORM';   {ID for Form Chunk}
    FormatVersionID  = 'FVER';   {ID for Format Version Chunk}
    CommonID         = 'COMM';   {ID for Common Chunk}
    SoundDataID     = 'SSND';   {ID for Sound Data Chunk}
```

The `ckSize` field specifies the size of the data portion of a chunk and does not include the length of the chunk header information.

The Form Chunk

The chunks that define the characteristics of a sampled sound and that contain the actual sound data are grouped together into a container chunk, known as the Form Chunk. The Form Chunk defines the type and size of the file and holds all remaining chunks in the file. The chunk ID for this container chunk is 'FORM'.

Sound Manager

A chunk of type 'FORM' has this structure:

```
TYPE ContainerChunk =
RECORD
    ckID:      ID;          {'FORM'}
    ckSize:    LongInt;     {number of bytes of data}
    formType:  ID;          {type of file}
END;
```

For a Form Chunk, the `ckSize` field contains the size of the data portion of this chunk. Note that the data portion of a Form Chunk is divided into two parts, `formType` and the rest of the chunks of the file, which follow the `formType` field. These chunks are called *local chunks* because their chunk IDs are local to the Form Chunk.

The local chunks can occur in any order in a sound file. As a result, your application should be designed to get a local chunk, identify it, and then process it without making any assumptions about what kind of chunk it is based on its order in the Form Chunk.

The `formType` field of the Form Chunk specifies the format of the file. For AIFF files, `formType` is 'AIFF'. For AIFF-C files, `formType` is 'AIFC'. Note that this type might not be the same as the operating-system type with which the File Manager identifies the file. In particular, a file of operating-system type 'AIFC' might be formatted as an AIFF file.

The Format Version Chunk

One difference between the AIFF and AIFF-C file formats is that files of type AIFF-C contain a Format Version Chunk and files of type AIFF do not. The Format Version Chunk contains a `timestamp` field that indicates when the format version of this AIFF-C file was defined. This in turn indicates what format rules this file conforms to and allows you to ensure that your application can handle a particular AIFF-C file. Every AIFF-C file must contain one and only one Format Version Chunk.

In AIFF-C files, a Format Version Chunk has this structure:

```
TYPE FormatVersionChunk =
RECORD
    ckID:      ID;          {'FVER'}
    ckSize:    LongInt;     {4}
    timestamp: LongInt;     {date of format version}
END;
```

Note

In AIFF files, there is no Format Version Chunk. ♦

The `timestamp` field indicates when the format version for this kind of file was created. The value indicates the number of seconds since January 1, 1904, following the normal time conventions used by the Macintosh Operating System. (See the chapter on date and

Sound Manager

time utilities in *Inside Macintosh: Operating System Utilities* for several routines that allow you to manipulate time stamps.)

You should not confuse the format version time stamp with the creation date of the file. The format version time stamp indicates the time of creation of the version of the format according to which this file is structured. Because Apple defines the formats of AIFF-C files, only Apple can change this value. The current version is defined by a constant:

```
CONST
    AIFCVersion1    = $A2805140;    {May 23, 1990, 2:40 p.m.}
```

The Common Chunk

Every AIFF and AIFF-C file must contain a Common Chunk that defines some fundamental characteristics of the sampled sound contained in the file. Note that the format of the Common Chunk is different for AIFF and AIFF-C files. As a result, you need to determine the type of file format (by inspecting the `formType` field of the Form Chunk) before reading the Common Chunk.

For AIFF files, the Common Chunk has this structure:

```
TYPE CommonChunk =
RECORD
    ckID:           ID;           {'COMM'}
    ckSize:         LongInt;      {size of chunk data}
    numChannels:    Integer;      {number of channels}
    numSampleFrames: LongInt;     {number of sample frames}
    sampleSize:     Integer;      {number of bits per sample}
    sampleRate:     Extended;     {number of frames per second}
END;
```

For AIFF-C files, the Common Chunk has this structure:

```
TYPE ExtCommonChunk =
RECORD
    ckID:           ID;           {'COMM'}
    ckSize:         LongInt;      {size of chunk data}
    numChannels:    Integer;      {number of channels}
    numSampleFrames: LongInt;     {number of sample frames}
    sampleSize:     Integer;      {number of bits per sample}
    sampleRate:     Extended;     {number of frames per second}
    compressionType: ID;          {compression type ID}
    compressionName: PACKED ARRAY[0..0] OF Byte;
                                     {compression type name}
END;
```

The fields that exist in both types of Common Chunk have the following meanings:

Sound Manager

The `numChannels` field of both types of Common Chunk indicate the number of audio channels contained in the sampled sound. A value of 1 indicates monophonic sound, a value of 2 indicates stereo sound, a value of 4 indicates four-channel sound, and so forth. Any number of audio channels may be specified. The actual sound data is stored elsewhere, in the Sound Data Chunk.

The `numSampleFrames` field indicates the number of sample frames in the Sound Data Chunk. Note that this field contains the number of sample frames, not the number of bytes of data and not the number of sample points. For noncompressed sound data, the total number of sample points in the file is `numChannels * numSampleFrames`. (For more information on sample points, see “Sampled-Sound Data” on page 2-9.)

The `sampleSize` field indicates the number of bits in each sample point of noncompressed sound. Although the field can contain any integer from 1 to 32, the Sound Manager currently supports only 8- and 16-bit sound. For compressed sound data, this field indicates the number of bits per sample in the original sound data, before compression.

The `sampleRate` field contains the sample rate at which the sound is to be played back, in sample frames per second. For a list of common sample rates, see Table 2-1 on page 2-16.

An AIFF-C Common Chunk includes two fields that describe the type of compression (if any) used on the audio data. The `compressionType` field contains the type of the compression algorithm, if any, used on the sound data. Here are the currently available compression types and their associated compression names:

```
CONST
    {compression types}
    NoneType           = 'NONE';
    ACE2Type           = 'ACE2';
    ACE8Type           = 'ACE8';
    MACE3Type          = 'MAC3';
    MACE6Type          = 'MAC6';
```

You can define your own compression types, but you should register them with Apple.

Finally, the `compressionName` field contains a human-readable name for the compression algorithm ID specified in the `compressionType` field. Compression names for Apple-supplied codecs are defined by constants:

```
CONST
    {compression names}
    NoneName           = 'not compressed';
    ACE2to1Name        = 'ACE 2-to-1';
    ACE8to3Name        = 'ACE 8-to-3';
    MACE3to1Name       = 'MACE 3-to-1';
    MACE6to1Name       = 'MACE 6-to-1';
```

This string is useful when putting up alert boxes (perhaps because a necessary decompression routine is missing). Pad the end of this array with a byte having the value 0 if the length of this array is not an even number (but do not include the pad byte in the count).

The Sound Data Chunk

The Sound Data Chunk contains the actual sample frames that make up the sampled sound. The Sound Data Chunk has this structure:

```

TYPE SoundDataChunk =
RECORD
    ckID:      ID;      {'SSND'}
    ckSize:    LongInt; {size of chunk data}
    offset:    LongInt; {offset to sound data}
    blockSize: LongInt; {size of alignment blocks}
END;
```

The `offset` field indicates an offset (in bytes) to the beginning of the first sample frame in the chunk data. Most applications do not need to use the `offset` field and should set it to 0.

The `blockSize` field contains the size (in bytes) of the blocks to which the sound data is aligned. This field is used in conjunction with the `offset` field for aligning sound data to blocks. As with the `offset` field, most applications do not need to use the `blockSize` field and should set it to 0.

The sampled-sound data follows the `blockSize` field. For information on the format of sampled-sound data, see “Sampled-Sound Data” on page 2-9.


Note

The Sound Data Chunk is required unless the `numSampleFrames` field in the Common Chunk is 0. A maximum of one Sound Data Chunk can appear in an AIFF or AIFF-C file. ♦

Format of Entire Sound Files

Figure 2-7 illustrates an AIFF-C file that contains approximately 4.476 seconds of 8-bit monophonic sound data sampled at 22 kHz. The sound data is not compressed. Note that the number of sample frames in this example is odd, forcing a pad byte to be inserted after the sound data. This pad byte is not reflected in the `ckSize` field of the Sound Data Chunk, which means that special processing is required to correctly determine the actual chunk size.

On a Macintosh computer, the Form Chunk (and hence all the other chunks in an AIFF or AIFF-C file) is stored in the data fork of the file. The file type of an AIFF format file is 'AIFF', and the file type of an AIFF-C format file is 'AIFC'. Macintosh applications should not store any information in the resource fork of an AIFF or AIFF-C file because that information might not be preserved by other applications that edit sound files.

Figure 2-7 A sample AIFF-C file

Every Form Chunk must contain a Common Chunk, and every AIFF-C file must contain a Format Version Chunk. In addition, if the sampled sound has a length greater than 0, there must be a Sound Data Chunk in the Form Chunk. All other chunk types are optional. Your application should be able to read all the required chunks if it uses AIFF or AIFF-C files, but it can choose to ignore any of the optional chunks.

When reading AIFF or AIFF-C files, you should keep the following points in mind:

- Remember that the local chunks in an AIFF or AIFF-C file can occur in any order. An application that reads these types of files should be designed to get a chunk, identify it, and then process it without making any assumptions about what kind of chunk it is based on its order.
- If your application allows modification of a chunk, then it must also update other chunks that might be based on the modified chunk. However, if there are chunks in the file that your application does not recognize, you must discard those unrecognized chunks. Of course, if your application is simply copying the AIFF or AIFF-C file without any modification, you should copy the unrecognized chunks, too.

- You can get the clearest indication of the number of sample frames contained in an AIFF or AIFF-C file from the `numSampleFrames` parameter in the Common Chunk, not from the `ckSize` parameter in the Sound Data Chunk. The `ckSize` parameter is padded to include the fields that follow it, but it does not include the byte with a value of 0 at the end if the total number of sound data bytes is odd.
- Remember that each chunk must contain an even number of bytes. Chunks whose total contents would yield an odd number of bytes must have a pad byte with a value of 0 added at the end of the chunk. This pad byte is not included in the `ckSize` field.
- Remember that the `ckSize` field of any chunk does not include the first 8 bytes of the chunk (which specify the chunk type).

Sound Manager Reference

This section describes the constants, data structures, and routines provided by the Sound Manager. It also describes the format of data stored in sound resources and files that the Sound Manager can play.

The section “Constants” describes the constants defined by the Sound Manager that you can use to specify channel initialization parameters and sound commands. It also lists the sound attributes selector for the `Gestalt` function and the returned bit numbers. See the section “Summary of the Sound Manager” on page 2-157 for a list of all the constants defined by the Sound Manager.

The section “Data Structures” beginning on page 2-99 describes the Pascal data structures for all of the Sound Manager records that applications can use, including sound commands, sound channels, and sound headers.

The section “Sound Manager Routines” beginning on page 2-119 describes the routines that allow you to play sounds, manage sound channels, and obtain sound-related information. That section also includes information on routines that give you low-level control over sound output.

The section “Application-Defined Routines” beginning on page 2-151 describes callback procedures and completion routines that your application might need to define.

The section “Resources” beginning on page 2-154 describes the organization of format 1 and format 2 ‘snd’ resources.

Constants

This section describes the constants that you can use to specify channel initialization parameters, sound commands, and chunk IDs. It also lists the `Gestalt` function sound attributes selector and the returned bit numbers. All other constants defined by the Sound Manager are described at the appropriate location in this chapter. (For example, the constants that you can use to specify sound data types are described in connection with the `SndNewChannel` function beginning on page 2-127.)

Gestalt Selector and Response Bits

You can pass the `gestaltSoundAttr` selector to the `Gestalt` function to determine information about the sound capabilities of a Macintosh computer.

CONST

```
gestaltSoundAttr          = 'snd ';    {sound attributes selector}
```

The `Gestalt` function returns information by setting or clearing bits in the `response` parameter. The bits currently used are defined by constants. Note that most of these bits provide information about the built-in hardware only.

IMPORTANT

Bits 7 through 12 are not defined for versions of the Sound Manager prior to version 3.0. ▲

CONST

```
gestaltStereoCapability   = 0;        {built-in hw can play stereo sounds}
gestaltStereoMixing       = 1;        {built-in hw mixes stereo to mono}
gestaltSoundIOMgrPresent  = 3;        {sound input routines available}
gestaltBuiltInSoundInput  = 4;        {built-in input hw available}
gestaltHasSoundInputDevice = 5;       {sound input device available}
gestaltPlayAndRecord      = 6;        {built-in hw can play while recording}
gestalt16BitSoundIO       = 7;        {built-in hw can handle 16-bit data}
gestaltStereoInput        = 8;        {built-in hw can record stereo sounds}
gestaltLineLevelInput     = 9;        {built-in input hw needs line level}
gestaltSndPlayDoubleBuffer = 10;     {play from disk routines available}
gestaltMultiChannels      = 11;       {multiple channels of sound supported}
gestalt16BitAudioSupport  = 12;       {16-bit audio data supported}
```

Constant descriptions

`gestaltStereoCapability`

Set if the built-in sound hardware is able to produce stereo sounds.

`gestaltStereoMixing`

Set if the built-in sound hardware mixes both left and right channels of stereo sound into a single audio signal for the internal speaker.

`gestaltSoundIOMgrPresent`

Set if the Sound Input Manager is available.

`gestaltBuiltInSoundInput`

Set if a built-in sound input device is available.

`gestaltHasSoundInputDevice`

Set if a sound input device is available. This device can be either built-in or external.

`gestaltPlayAndRecord`

Set if the built-in sound hardware is able to play and record sounds simultaneously. If this bit is clear, the built-in sound hardware can either play or record, but not do both at once. This bit is valid only if

Sound Manager

the `gestaltBuiltInSoundInput` bit is set, and it applies only to any built-in sound input and output hardware.

`gestalt16BitSoundIO`

Set if the built-in sound hardware is able to play and record 16-bit samples. This indicates that built-in hardware necessary to handle 16-bit data is available.

`gestaltStereoInput`

Set if the built-in sound hardware can record stereo sounds.

`gestaltLineLevelInput`

Set if the built-in sound input port requires line level input.

`gestaltSndPlayDoubleBuffer`

Set if the Sound Manager supports the play-from-disk routines.

`gestaltMultiChannels`

Set if the Sound Manager supports multiple channels of sound.

`gestalt16BitAudioSupport`

Set if the Sound Manager can handle 16-bit audio data. This indicates that software necessary to handle 16-bit data is available.

Note

For complete information about the `Gestalt` function, see the chapter “Gestalt Manager” in *Inside Macintosh: Operating System Utilities*. ♦

Channel Initialization Parameters

You can use the following constants to specify initialization parameters for a sound channel. You need to specify initialization parameters when you call `SndNewChannel`.

CONST

```

initChanLeft      = $0002;    {left stereo channel}
initChanRight     = $0003;    {right stereo channel}
waveInitChannel0  = $0004;    {wave-table channel 0}
waveInitChannel1  = $0005;    {wave-table channel 1}
waveInitChannel2  = $0006;    {wave-table channel 2}
waveInitChannel3  = $0007;    {wave-table channel 3}
initMono          = $0080;    {monophonic channel}
initStereo        = $00C0;    {stereo channel}
initMACE3         = $0300;    {3:1 compression}
initMACE6         = $0400;    {6:1 compression}
initNoInterp      = $0004;    {no linear interpolation}
initNoDrop        = $0008;    {no drop-sample conversion}

```

Constant descriptions

`initChanLeft` Play sounds through the left channel of the Macintosh audio jack.
`initChanRight` Play sounds through the right channel of the Macintosh audio jack.

Sound Manager

<code>waveInitChannel0</code>	Play sounds through the first wave-table channel.
<code>waveInitChannel1</code>	Play sounds through the second wave-table channel.
<code>waveInitChannel2</code>	Play sounds through the third wave-table channel.
<code>waveInitChannel3</code>	Play sounds through the fourth wave-table channel.
<code>initMono</code>	Play the same sound through both channels of the Macintosh audio jack and the internal speaker. This is the default channel mode.
<code>initStereo</code>	Play stereo sounds through both channels of the Macintosh audio jack and the internal speaker. Note that some machines cannot play stereo sounds.
<code>initMACE3</code>	Assume that the sounds to be played through the channel are MACE 3:1 compressed. The <code>SndNewChannel</code> function uses this information to help determine whether it can allocate a new sound channel. A noncompressed sound plays normally, even through a channel that has been initialized for MACE.
<code>initMACE6</code>	Assume that the sounds to be played through the channel are MACE 6:1 compressed. The <code>SndNewChannel</code> function uses this information to help determine whether it can allocate a new sound channel. A noncompressed sound plays normally, even through a channel that has been initialized for MACE.
<code>initNoInterp</code>	Do not use linear interpolation to smooth a sound played back at a different sample rate from the sound's recorded sample rate. Using the <code>initNoInterp</code> initialization parameter decreases the CPU load for this channel. Sounds most affected by the absence of linear interpolation are sinusoidal sounds. Sounds least affected are noisy sound effects like explosions and screams.
<code>initNoDrop</code>	Do not use drop-sample conversion to fake sample rate conversion. Using the <code>initNoDrop</code> initialization parameter increases the CPU load for the channel but results in a smoother sound.

The Sound Manager also recognizes the following masks, which you can use to select various channel attributes:

CONST		
<code>initPanMask</code>	= \$0003;	{mask for right/left pan values}
<code>initSRateMask</code>	= \$0030;	{mask for sample rate values}
<code>initStereoMask</code>	= \$00C0;	{mask for mono/stereo values}
<code>initCompMask</code>	= \$FF00;	{mask for compression IDs}

Sound Command Numbers

You can perform many sound-related operations by sending sound commands to a sound channel. For example, to change the volume of a sound that is currently playing, you can send the `ampCmd` sound command to the channel using the `SndDoImmediate`

routine. Similarly, to change the volume of all sounds subsequently to be played in a sound channel, you can send the `volumeCmd` sound command to that channel using the `SndDoCommand` routine.

The `cmd` field of the `SndCommand` data structure (described on page 2-99) specifies the sound command you want to execute. The `param1` and `param2` fields of that structure contain any additional information that might be needed to complete the command. One or both of these parameter fields might be ignored by a particular sound command. In some cases, the Sound Manager returns information to your application in one of the parameter fields.

IMPORTANT

In general, you'll use either `SndDoCommand` or `SndDoImmediate` to send sound commands to a sound channel. With several commands, however, you must use the `SndControl` function to issue the sound command. In Sound Manager version 3.0 and later, however, you virtually never need to use `SndControl` because the commands that require it are either no longer supported (for example, `availableCmd`, `totalLoadCmd`, and `loadCmd`) or are obsolete (for example, `versionCmd`). The sound commands specific to the `SndControl` function are documented here for completeness only. ▲

The sound commands available to your application are defined by constants.

CONST

```

nullCmd           = 0;           {do nothing}
quietCmd          = 3;           {stop a sound that is playing}
flushCmd          = 4;           {flush a sound channel}
reInitCmd         = 5;           {reinitialize a sound channel}
waitCmd           = 10;          {suspend processing in a channel}
pauseCmd          = 11;          {pause processing in a channel}
resumeCmd         = 12;          {resume processing in a channel}
callbackCmd       = 13;          {execute a callback procedure}
syncCmd           = 14;          {synchronize channels}
availableCmd      = 24;          {see if initialization options are }
                                { supported}
versionCmd        = 25;          {determine version}
totalLoadCmd      = 26;          {report total CPU load}
loadCmd           = 27;          {report CPU load for a new channel}
freqDurationCmd  = 40;          {play a note for a duration}
restCmd           = 41;          {rest a channel for a duration}
freqCmd           = 42;          {change the pitch of a sound}
ampCmd            = 43;          {change the amplitude of a sound}
timbreCmd         = 44;          {change the timbre of a sound}
getAmpCmd         = 45;          {get the amplitude of a sound}
volumeCmd         = 46;          {set volume}
getVolumeCmd     = 47;          {get volume}

```

Sound Manager

```

waveTableCmd      = 60;      {install a wave table as a voice}
soundCmd          = 80;      {install a sampled sound as a voice}
bufferCmd         = 81;      {play a sampled sound}
rateCmd           = 82;      {set the pitch of a sampled sound}
getRateCmd        = 85;      {get the pitch of a sampled sound}

```

Constant descriptions

nullCmd **Do nothing.**
param1: 0 (ignored on input and output)
param2: 0 (ignored on input and output)

quietCmd **Stop the sound that is currently playing. You should send quietCmd by using SndDoImmediate.**
param1: 0 (ignored on input and output)
param2: 0 (ignored on input and output)

flushCmd **Remove all commands currently queued in the specified sound channel. A flushCmd command does not affect any sound that is currently in progress. You should send flushCmd by using SndDoImmediate.**
param1: 0 (ignored on input and output)
param2: 0 (ignored on input and output)

reInitCmd **Reset the initialization parameters specified in param2 for the specified channel.**
param1: 0 (ignored on input and output)
param2: initialization parameters

waitCmd **Suspend further command processing in a channel until the specified duration has elapsed. To achieve sounds longer than 32,767 half-milliseconds, Pascal programmers can pass a negative number in param1, in which case the sound plays for 32,767 half-milliseconds plus the absolute value of param1.**
param1: duration in half-milliseconds (0 to 65,565)
param2: 0 (ignored on input and output)

pauseCmd **Pause any further command processing in a channel until resumeCmd is received.**
param1: 0 (ignored on input and output)
param2: 0 (ignored on input and output)

resumeCmd **Resume command processing in a channel that was previously paused by pauseCmd.**
param1: 0 (ignored on input and output)
param2: 0 (ignored on input and output)

callBackCmd **Execute the callback procedure specified as a parameter to the SndNewChannel function. Both param1 and param2 are application-specific; you can use these two parameters to send data to your callback routine.**
param1: application-defined
param2: application-defined

syncCmd **Synchronize multiple channels of sound. A syncCmd command is held in the specified channel, suspending all further command**

Sound Manager

	processing. The <code>param2</code> parameter contains an identifier that is arbitrary. Each time the Sound Manager receives <code>syncCmd</code> , it decrements the <code>count</code> parameter for each channel having that identifier. When the count for a specific channel reaches 0, command processing in that channel resumes. <code>param1: count</code> <code>param2: identifier</code>
<code>availableCmd</code>	Return 1 in <code>param1</code> if the Sound Manager supports the initialization options specified in <code>param2</code> and 0 otherwise. However, the Sound Manager might support certain initialization parameters in general but not on a specific machine. You should send <code>availableCmd</code> using the <code>SndControl</code> function. <code>param1: 0 on input; result of command on output</code> <code>param2: initialization parameters</code>
<code>versionCmd</code>	Previously, this command determined which version of a sound data format is available. The result is returned in <code>param2</code> . The high word of the result indicates the major revision number, and the low word indicates the minor revision number. For example, version 2.0 of a data format would be returned as \$00020000. However, this command is obsolete, and your application should not rely on it. You send <code>versionCmd</code> by using the <code>SndControl</code> function. <code>param1: 0 (ignored on input and output)</code> <code>param2: 0 on input; version on output</code>
<code>totalLoadCmd</code>	Previously, this command determined the total CPU load factor for all existing sound activity and for a new sound channel having the initialization parameters specified in <code>param2</code> . However, this command is obsolete, and your application should not rely on it. You send <code>totalLoadCmd</code> by using the <code>SndControl</code> function. <code>param1: 0 on input, load factor on output</code> <code>param2: initialization parameters</code>
<code>loadCmd</code>	Previously, this command determined the CPU load factor that would be incurred by a new channel of sound having the initialization parameters specified in <code>param2</code> . The load factor returned in <code>param1</code> is the percentage of CPU processing power that the specified sound channel would require. However, this command is obsolete, and your application should not rely on it. You send <code>loadCmd</code> by using the <code>SndControl</code> function. <code>param1: 0 on input, load factor on output</code> <code>param2: initialization parameters</code>
<code>freqDurationCmd</code>	Play the note specified in <code>param2</code> for the duration specified in <code>param1</code> . To achieve sounds longer than 32,767 half-milliseconds, Pascal programmers can pass a negative number in <code>param1</code> , in which case the sound plays for 32,767 half-milliseconds plus the absolute value of <code>param1</code> . The <code>param2</code> parameter must contain a value in the range 0 to 127. If you want the note to stop playing after the duration specified in <code>param1</code> , you must send <code>quietCmd</code> after <code>freqDurationCmd</code> .

Sound Manager

	<p>param1: duration in half-milliseconds (0 to 65,565)</p> <p>param2: desired frequency</p>
restCmd	<p>Rest a channel for a specified duration. The duration is specified in half-milliseconds in param1. To achieve sounds longer than 32,767 half-milliseconds, Pascal programmers can pass a negative number in param1, in which case the sound plays for 32,767 half-milliseconds plus the absolute value of param1.</p> <p>param1: duration in half-milliseconds (0 to 65,565)</p> <p>param2: 0 (ignored on input and output)</p>
freqCmd	<p>Change the frequency (or pitch) of a sound. If no sound is currently playing, then freqCmd causes the Sound Manager to begin playing indefinitely at the frequency specified in param2. If, however, no instrument is installed in the channel and you attempt to play either wave-table or sampled-sound data, no sound is produced. The param2 parameter must contain a value in the range 0 to 127. The freqCmd command is identical to the freqDurationCmd command, except that no duration is specified to a freqCmd command.</p> <p>param1: 0 (ignored on input and output)</p> <p>param2: desired frequency</p>
ampCmd	<p>Change the amplitude (or loudness) of a sound. If no sound is currently playing, then ampCmd sets the amplitude of the next sound to be played. You specify the amplitude in param1; the amplitude should be an integer in the range 0 to 255.</p> <p>param1: desired amplitude</p> <p>param2: 0 (ignored on input and output)</p>
timbreCmd	<p>Change the timbre (or tone) of a sound currently being defined using square-wave data. A timbre value of 0 produces a clear tone; a timbre value of 254 produces a buzzing tone. You can use timbreCmd only for sounds defined using square-wave data.</p> <p>param1: desired timbre (0 to 254)</p> <p>param2: 0 (ignored on input and output)</p>
getAmpCmd	<p>Determine the current amplitude (or loudness) of a sound. The amplitude is returned in an integer variable whose address you pass in param2 and is in the range 0 to 255.</p> <p>param1: 0 (ignored on input and output)</p> <p>param2: pointer to amplitude variable</p>
volumeCmd	<p>Set the right and left volumes of the specified sound channel to the volumes specified in the high and low words of param2. The value \$0100 represents full volume, and \$0080 represents half volume. You can specify values larger than \$0100 to overdrive the volume. For example, setting param2 to \$02000200 sets the volume on both left and right speakers to twice full volume. Note, however, that volumeCmd is available only in Sound Manager versions 3.0 and later.</p> <p>param1: 0 (ignored on input and output)</p> <p>param2: high word is right volume, low word is left volume</p>
getVolumeCmd	<p>Get the current right and left volumes of the specified sound channel. The volumes are returned in the high and low words of the</p>

	<p>long integer pointed to by <code>param2</code>. The value \$0100 represents full volume, and \$0080 represents half volume. Note, however, that <code>getVolumeCmd</code> is available only in Sound Manager versions 3.0 and later.</p> <p><code>param1</code>: 0 (ignored on input and output)</p> <p><code>param2</code>: pointer to volume data</p>
<code>waveTableCmd</code>	<p>Install a wave table as a voice in the specified channel. The <code>param1</code> parameter specifies the length of the wave table, and the <code>param2</code> parameter is a pointer to the wave-table data itself. You can use <code>waveTableCmd</code> only for sounds defined using wave-table data.</p> <p><code>param1</code>: length of wave table</p> <p><code>param2</code>: pointer to wave-table data</p>
<code>soundCmd</code>	<p>Install a sampled sound as a voice in a channel. If the high bit of the command is set, <code>param2</code> is interpreted as an offset from the beginning of the 'snd' resource containing the command to the sound header. If the high bit is not set, <code>param2</code> is interpreted as a pointer to the sound header. You can use the <code>soundCmd</code> command only with noncompressed sampled-sound data. You can also use <code>soundCmd</code> to preconfigure a sound channel, so that you can later send sound commands to it at interrupt time.</p> <p><code>param1</code>: 0 (ignored on input and output)</p> <p><code>param2</code>: offset or pointer to sound header</p>
<code>bufferCmd</code>	<p>Play a buffer of sampled-sound data. If the high bit of the command is set, <code>param2</code> is interpreted as an offset from the beginning of the 'snd' resource containing the command to the sound header. If the high bit is not set, <code>param2</code> is interpreted as a pointer to the sound header. You can use <code>bufferCmd</code> only with sampled-sound data. Note that sending a <code>bufferCmd</code> resets the rate of the channel to 1.0.</p> <p><code>param1</code>: 0 (ignored on input and output)</p> <p><code>param2</code>: offset or pointer to sound header</p>
<code>rateCmd</code>	<p>Set the rate of a sampled sound that is currently playing, thus effectively altering its pitch and duration. Your application can set a rate of 0 to pause a sampled sound that is playing. The new rate is set to the value specified in <code>param2</code>, which is interpreted relative to 22 kHz. (For example, to set the rate to 44 kHz, pass \$00020000 in <code>param2</code>; see Listing 2-4 on page 2-26 for sample code that uses <code>rateCmd</code>.) You can use <code>rateCmd</code> only with sampled-sound data.</p> <p><code>param1</code>: 0 (ignored on input and output)</p> <p><code>param2</code>: desired rate of sound</p>
<code>getRateCmd</code>	<p>Determine the sample rate of the sampled sound currently playing. The current rate of the channel is returned in a <code>Fixed</code> variable whose address you pass in <code>param2</code> of the sound command. The values returned are always relative to the 22 kHz sampling rate, as with the <code>rateCmd</code> sound command. You can use <code>getRateCmd</code> only with sampled-sound data, and you should send it by using <code>SndDoImmediate</code>.</p> <p><code>param1</code>: 0 (ignored on input and output)</p> <p><code>param2</code>: pointer to rate variable</p>

Chunk IDs

You can use the following constants to specify a chunk ID, a 4-byte value that identifies the type of a chunk in an AIFF or AIFF-C file.

CONST

```
{IDs for AIFF and AIFF-C file chunks}
FormID                = 'FORM';    {ID for Form Chunk}
FormatVersionID      = 'FVER';    {ID for Format Version Chunk}
CommonID              = 'COMM';    {ID for Common Chunk}
SoundDataID          = 'SSND';    {ID for Sound Data Chunk}
MarkerID              = 'MARK';    {ID for Marker Chunk}
InstrumentID          = 'INST';    {ID for Instrument Chunk}
MIDIDataID           = 'MIDI';    {ID for MIDI Data Chunk}
AudioRecordingID      = 'AESD';    {ID for Recording Chunk}
  ApplicationSpecificID = 'APPL';  {ID for Application Chunk}
CommentID             = 'COMT';    {ID for Comment Chunk}
NameID                = 'NAME';    {ID for Name Chunk}
AuthorID              = 'AUTH';    {ID for Author Chunk}
CopyrightID           = '(c)';     {ID for Copyright Chunk}
AnnotationID          = 'ANNO';    {ID for Annotation Chunk}
```

Constant descriptions

FormID	The Form Chunk. A Form Chunk contains information about the format of the file, and contains all the other chunks of the file.
FormatVersionID	The Format Version Chunk. A Format Version Chunk contains an indication of the version of the AIFF-C specification according to which this file is structured (AIFF-C only).
CommonID	The Common Chunk. A Common Chunk contains information about the sampled sound, such as the sampling rate and sample size.
SoundDataID	The Sound Data Chunk. A Sound Data Chunk contains the sample frames that comprise the sampled sound.
MarkerID	The Marker Chunk. A Marker Chunk contains markers that point to positions in the sound data.
InstrumentID	The Instrument Chunk. An Instrument Chunk defines basic parameters that an instrument (such as a sampling keyboard) can use to play back the sound data.
MIDIDataID	The MIDI Data Chunk. A MIDI Chunk contains MIDI data.
AudioRecordingID	The Audio Recording Chunk. An Audio Recording Chunk contains information pertaining to audio recording devices.
ApplicationSpecificID	The Application Chunk. An Application Chunk contains application-specific information.

Sound Manager

<code>CommentID</code>	The Comment Chunk. A Comment Chunk contains a comment.
<code>NameID</code>	The Name Chunk. A Name Chunk contains the name of the sampled sound.
<code>AuthorID</code>	The Author Chunk. An Author Chunk contains one or more names of the authors (or creators) of the sampled sound.
<code>CopyrightID</code>	The Copyright Chunk. A Copyright Chunk contains a copyright notice for the sampled sound.
<code>AnnotationID</code>	The Annotation Chunk. An Annotation Chunk contains a comment.

Data Structures

This section describes the data structures that the Sound Manager defines. The Sound Manager uses many of these data structures (such as sound headers) to store information about sounds or sound channels. You should use these data structures only if you need to access this information or to customize sound play. The Sound Manager also defines several data structures that allow you to control sound output or to receive information about its status.

You use the sound command record to define a sound command that you send to the Sound Manager using either the `SndDoCommand` or `SndDoImmediate` functions.

If you want to play only a portion of a sound, you can use an audio selection record in conjunction with the `SndStartFilePlay` function.

You use the sound channel status record to obtain information from the Sound Manager about a specific sound channel, and you use the Sound Manager status record to obtain information about all sound channels.

The sound channel record stores information about a sound channel. Many of the fields of this record are for internal Sound Manager use only, but there are a few that you can access directly.

The sound header record stores information about sampled-sound data. You can use a sound header record to obtain information on a sound or to change a sound's loop points. The extended sound header record and the compressed sound header record add several fields to the sound header record that provide more information about a sound.

If your application uses the `SndPlayDoubleBuffer` function to customize the double buffering of sound data, you need to set up a sound double buffer header record, which must include pointers to two sound double buffer records.

Sound Command Records

A **sound command record** describes a sound command that you send to a sound channel using the `SndDoCommand` or `SndDoImmediate` function. The `SndCommand` data type defines a sound command record.

Sound Manager

```

TYPE SndCommand =
PACKED RECORD
    cmd:      Integer;      {command number}
    param1:   Integer;      {first parameter}
    param2:   LongInt;     {second parameter}
END;

```

Field descriptions

cmd The number of the sound command you wish to execute.

param1 The first parameter of the sound command.

param2 The second parameter of the sound command.

The meaning of the `param1` and `param2` fields depends on the particular sound command being issued. See “Sound Command Numbers” beginning on page 2-92 for a description of the sound commands your application can use.

Audio Selection Records

You can pass a pointer to an audio selection record to the `SndStartFilePlay` function to play only part of a sound in a file on disk. The `AudioSelection` data type defines an audio selection record.

```

TYPE AudioSelection =
PACKED RECORD
    unitType:  LongInt;     {type of time unit}
    selStart:  Fixed;       {starting point of selection}
    selEnd:    Fixed;       {ending point of selection}
END;

```

Field descriptions

unitType The type of unit of time used in the `selStart` and `selEnd` fields. You can set this to seconds by specifying the constant `unitTypeSeconds`.

selStart The starting point in seconds of the sound to play. If `selStart` is greater than `selEnd`, `SndStartFilePlay` returns an error.

selEnd The ending point in seconds of the sound to play.

Use a constant to specify the unit type.

```

CONST
    unitTypeSeconds      = $0000;    {seconds}
    unitTypeNoSelection  = $FFFF;    {no selection}

```

If the value in the `unitType` field is `unitTypeNoSelection`, then the values in the `selStart` and `selEnd` fields are ignored and the entire sound plays. Alternatively, if you wish to play an entire sound, you can pass `NIL` instead of a pointer to an audio selection record to the `SndStartFilePlay` function.

Sound Channel Status Records

To obtain information about a sound channel, you can pass a pointer to a **sound channel status record** to the `SndChannelStatus` function. The `SCStatus` data type defines a sound channel status record.

```

TYPE SCStatus =
RECORD
    scStartTime:      Fixed;      {starting time for play from disk}
    scEndTime:       Fixed;      {ending time for play from disk}
    scCurrentTime:   Fixed;      {current time for play from disk}
    scChannelBusy:   Boolean;     {TRUE if channel is processing cmds}
    scChannelDisposed: Boolean;   {reserved}
    scChannelPaused: Boolean;     {TRUE if channel is paused}
    scUnused:        Boolean;     {unused}
    scChannelAttributes: LongInt; {attributes of this channel}
    scCPULoad:       LongInt;     {CPU load for this channel}
END;

```

Field descriptions

<code>scStartTime</code>	If the Sound Manager is playing from disk through the specified sound channel, then <code>scStartTime</code> is the starting time in seconds from the beginning of the sound for the play from disk. Otherwise, <code>scStartTime</code> is 0.
<code>scEndTime</code>	If the Sound Manager is playing from disk through the specified sound channel, then <code>scEndTime</code> is the ending time in seconds from the beginning of the sound for the play from disk. Otherwise, <code>scEndTime</code> is 0.
<code>scCurrentTime</code>	If the Sound Manager is playing from disk through the specified sound channel, then <code>scCurrentTime</code> is the current time in seconds from the beginning of the disk play. Otherwise, <code>scCurrentTime</code> is 0. The Sound Manager updates the value of this field only periodically, and you should not rely on the accuracy of its value.
<code>scChannelBusy</code>	If the specified channel is currently processing sound commands, then <code>scChannelBusy</code> is TRUE; otherwise, <code>scChannelBusy</code> is FALSE.
<code>scChannelDisposed</code>	Reserved for use by Apple Computer, Inc.
<code>scChannelPaused</code>	If the Sound Manager is playing from disk through the specified sound channel and the play from disk is paused, then <code>scChannelPaused</code> is TRUE; otherwise, <code>scChannelPaused</code> is FALSE. This field is also TRUE if the channel was paused with the <code>pauseCmd</code> sound command.
<code>scUnused</code>	Reserved for use by Apple Computer, Inc.

Sound Manager

`scChannelAttributes`

The current attributes of the specified channel. These attributes are in the channel initialization parameters format. The value returned in this field is always identical to the value passed in the `init` parameter to `SndNewChannel`.

`scCPULoad`

The CPU load for the specified channel. You should not rely on the value in this field.

You can mask out certain values in the `scChannelAttributes` field to determine how a channel has been initialized.

CONST

```

initPanMask      = $0003;    {mask for right/left pan values}
initSRateMask    = $0030;    {mask for sample rate values}
initStereoMask   = $00C0;    {mask for mono/stereo values}
initCompMask     = $FF00;    {mask for compression IDs}

```

Sound Manager Status Records

You can use the `SndManagerStatus` function to get a **Sound Manager status record**, which gives information on the current CPU loading caused by all open channels of sound. The `SMStatus` data type defines a Sound Manager status record.

```
TYPE SMStatus =
```

```
PACKED RECORD
```

```

smMaxCPULoad:    Integer;    {maximum load on all channels}
smNumChannels:   Integer;    {number of allocated channels}
smCurCPULoad:   Integer;    {current load on all channels}

```

```
END;
```

Field descriptions

`smMaxCPULoad` The maximum CPU load that the Sound Manager will not exceed when allocating channels. The `smMaxCPULoad` field is set to a default value of 100 when the system starts up.

`smNumChannels` The number of sound channels that are currently allocated by all applications. This does not mean that the channels allocated are being used, only that they have been allocated and that CPU loading is being reserved for these channels.

`smCurCPULoad` The CPU load that is being taken up by currently allocated channels.

IMPORTANT

Although you can use the information contained in the Sound Manager status record to determine how many channels are allocated, you should not rely on the information in the `smMaxCPULoad` or `smCurCPULoad` field. To determine whether the Sound Manager can create a new channel, simply call the `SndNewChannel` function, which returns an appropriate result code if it is unable to allocate a new channel. ▲

Sound Channel Records

The Sound Manager maintains a sound channel record to store information about each sound channel that you allocate directly by calling the `SndNewChannel` function or indirectly by passing a `NIL` channel to a high-level Sound Manager routine like the `SndPlay` function. The `SndChannel` data type defines a sound channel record.

```

TYPE SndChannel =
PACKED RECORD
    nextChan:      SndChannelPtr; {pointer to next channel}
    firstMod:      Ptr;           {used internally}
    callBack:      ProcPtr;       {pointer to callback procedure}
    userInfo:      LongInt;       {free for application's use}
    wait:          LongInt;       {used internally}
    cmdInProgress: SndCommand;    {used internally}
    flags:         Integer;       {used internally}
    qLength:       Integer;       {used internally}
    qHead:         Integer;       {used internally}
    qTail:         Integer;       {used internally}
    queue:         ARRAY[0..stdQLength-1] OF SndCommand;
END;
```

Field descriptions

<code>nextChan</code>	A pointer to the next sound channel in a single queue of channels that the Sound Manager maintains for all applications.
<code>firstMod</code>	Used internally.
<code>callBack</code>	A pointer to the callback procedure associated with the sound channel. See page 2-152 for information on this callback procedure.
<code>userInfo</code>	A value that your application can use to store information.
<code>wait</code>	Used internally.
<code>cmdInProgress</code>	Used internally.
<code>flags</code>	Used internally.
<code>qLength</code>	Used internally.
<code>qHead</code>	Used internally.
<code>qTail</code>	Used internally.
<code>queue</code>	The sound commands pending for the sound channel.

The only field of the sound channel record that you are likely to need to access directly is the `userInfo` field. This field is useful if you need to pass a value to a Sound Manager callback procedure or completion routine. For example, you might pass the value stored in the `A5` register so that your callback procedure can access your application's global variables. Or, you might store a handle to sound data here so that a routine that disposes of an allocated channel can also release the sound data that the channel played.

In rarer instances, you might need to access the `callBack` field of the sound channel record directly. Ordinarily, you set this field by specifying a callback procedure when

Sound Manager

you call the `SndNewChannel` function. However, you can change the callback procedure associated with a channel by changing this field directly. The Sound Manager will then execute the procedure you specify in this field whenever the channel processes a `callbackCmd` command.

▲ **WARNING**

You should not attempt to manipulate all open sound channels by using the `nextChan` field to walk the sound channel queue. The queue might contain channels opened by other applications. If you need to perform some operation on all sound channels that your application has allocated, you should maintain your own data structure that keeps track of your application's channels. ▲

Sound Header Records

Sound resources often contain sampled-sound data as well as sound commands. The sound data is contained in the last field of the sound header. You can access a sound header record to find information about sampled-sound data. The standard sound header is used only for simple monophonic sounds. The `SoundHeader` data type defines a sampled sound header record.

```
TYPE SoundHeader =
PACKED RECORD
    samplePtr:    Ptr;           {if NIL, samples in sampleArea}
    length:      LongInt;       {number of samples in array}
    sampleRate:  Fixed;         {sample rate}
    loopStart:   LongInt;       {loop point beginning}
    loopEnd:     LongInt;       {loop point ending}
    encode:      Byte;          {sample's encoding option}
    baseFrequency: Byte;        {base frequency of sample}
    sampleArea:  PACKED ARRAY[0..0] OF Byte;
END;
```

Field descriptions

<code>samplePtr</code>	A pointer to the sampled-sound data. If the sampled sound is located in memory immediately after the <code>baseFrequency</code> field, then this field should be set to <code>NIL</code> . Otherwise, this field is a pointer to the memory location of the sampled-sound data. (This might be useful if you want to change some fields of a sound header but do not want to modify a handle to a sound resource directly.)
<code>length</code>	The number of bytes of sound data.
<code>sampleRate</code>	The rate at which the sample was originally recorded. The Sound Manager can play sounds sampled at any rate up to 64 kHz. The values corresponding to the three most common sample rates (11 kHz, 22 kHz, and 44 kHz) are defined by constants:

Sound Manager

CONST

```

rate44khz = $AC440000; {44100.00000 Fixed}
rate22khz = $56EE8BA3; {22254.54545 Fixed}
rate11khz = $2B7745D1; {11127.27273 Fixed}

```

Note that the sample rate is declared as a `Fixed` data type, but the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768.

<code>loopStart</code>	The starting point of the portion of the sampled sound header that is to be used by the Sound Manager when determining the duration of <code>freqDurationCmd</code> . These loop points specify the byte numbers in the sampled data to be used as the beginning and end points to cycle through when playing the sound. The loop starting and ending points are 0-based.
<code>loopEnd</code>	The end point of the portion of the sampled sound header that is to be used by the Sound Manager when determining the duration of <code>freqDurationCmd</code> . If no looping is desired, set both <code>loopStart</code> and <code>loopEnd</code> to 0.
<code>encode</code>	The method of encoding used to generate the sampled-sound data. The current encoding option values are

CONST

```

stdSH = $00; {standard sound header}
extSH = $FF; {extended sound header}
cmpSH = $FE; {compressed sound header}

```

For a standard sound header, you should specify the constant `stdSH`. Encode option values in the ranges 0 through 63 and 128 to 255 are reserved for use by Apple. You are free to use numbers in the range 64 through 127 for your own encode options.

<code>baseFrequency</code>	The pitch at which the original sample was taken. This value must be in the range 1 through 127. Table 2-2 on page 2-43 lists the possible <code>baseFrequency</code> values. The <code>baseFrequency</code> value allows the Sound Manager to calculate the proper playback rate of the sample when an application uses the <code>freqDurationCmd</code> command. Applications should not alter the <code>baseFrequency</code> field of a sampled sound; to play the sample at different pitches, use <code>freqDurationCmd</code> or <code>freqCmd</code> .
<code>sampleArea</code>	If the value of <code>samplePtr</code> is <code>NIL</code> , this field is an array of bytes, each of which contains a value similar to the values in a wave-table description. These values are interpreted as offset values, where <code>\$80</code> represents an amplitude of 0. The value <code>\$00</code> is the most negative amplitude, and <code>\$FF</code> is the largest positive amplitude. The samples are numbered 1 through the value in the <code>length</code> parameter.

If you need to create a sound header for sampled-sound data that your application has recorded, then you should use the `SetupSndHeader` function, described in the chapter “Sound Input Manager” in this book.

Extended Sound Header Records

For sampled-sound data that is more complex than a standard sound header can describe, the Sound Manager uses an extended sound header record. Sound data described by such a header can be monophonic or stereo, but it cannot be compressed.

Most of the fields of the extended sound header correspond to fields of the sampled sound header. However, the extended sound header allows the encoding of stereo sound. The `numChannels` field contains the number of channels of sound recorded, and the `numFrames` field contains the number of frames of sound recorded in each channel. For more information on the format of sampled sound frames, see “Sound Files” on page 2-81.

Note

The word “channel” can be confusing in this context, because a sound resource containing polyphonic sound (that is, multichannel sound) can be played on a single Sound Manager sound channel. **Channel** is a general term for the portion of sound data that can be described by a single sound wave. Monophonic sound is composed of a single channel. **Stereo sound** (also called **polyphonic sound**) is composed of several channels of sound played simultaneously. “Sound channel” is a term specific to the Sound Manager. ♦

```

TYPE ExtSoundHeader =
PACKED RECORD
    samplePtr:      Ptr;           {if NIL, samples in sampleArea}
    numChannels:    LongInt;       {number of channels in sample}
    sampleRate:     Fixed;         {rate of original sample}
    loopStart:      LongInt;       {loop point beginning}
    loopEnd:        LongInt;       {loop point ending}
    encode:         Byte;         {sample's encoding option}
    baseFrequency: Byte;         {base freq. of original sample}
    numFrames:      LongInt;       {total number of frames}
    AIFFSampleRate: Extended80;   {rate of original sample}
    markerChunk:    Ptr;         {reserved}
    instrumentChunks: Ptr;       {pointer to instrument info}
    AESRecording:    Ptr;         {pointer to audio info}
    sampleSize:     Integer;       {number of bits per sample}
    futureUse1:     Integer;       {reserved}
    futureUse2:     LongInt;       {reserved}
    futureUse3:     LongInt;       {reserved}
    futureUse4:     LongInt;       {reserved}
    sampleArea:     PACKED ARRAY[0..0] OF Byte;
END;
```

Sound Manager

Field descriptions

<code>samplePtr</code>	A pointer to the sampled-sound data. If the sampled sound is located in memory immediately after the <code>futureUse4</code> field, then this field should be set to <code>NIL</code> . Otherwise, this field is a pointer to the memory location of the sampled-sound data.
<code>numChannels</code>	The number of channels in the sampled-sound data.
<code>sampleRate</code>	The rate at which the sample was originally recorded. The approximate sample rates are shown in Table 2-1 on page 2-16. Note that the sample rate is declared as a <code>Fixed</code> data type, but the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768.
<code>loopStart</code>	The starting point of the portion of the extended sampled sound header that is to be used by the Sound Manager when determining the duration of <code>freqDurationCmd</code> . These loop points specify the byte numbers in the sampled data to be used as the beginning and end points to cycle through when playing the sound. The loop starting and ending points are 0-based.
<code>loopEnd</code>	The end point of the portion of the extended sampled sound header that is to be used by the Sound Manager when determining the duration of <code>freqDurationCmd</code> .
<code>encode</code>	The method of encoding used to generate the sampled-sound data. For an extended sound header, you should specify the constant <code>extSH</code> . Encode option values in the ranges 0 through 63 and 128 to 255 are reserved for use by Apple. You are free to use numbers in the range 64 through 127 for your own encode options.
<code>baseFrequency</code>	The pitch at which the original sample was taken. This value must be in the range 1 through 127. Table 2-2 on page 2-43 lists the possible <code>baseFrequency</code> values. The <code>baseFrequency</code> value allows the Sound Manager to calculate the proper playback rate of the sample when an application uses the <code>freqDurationCmd</code> command. Applications should not alter the <code>baseFrequency</code> field of a sampled sound; to play the sample at different pitches, use <code>freqDurationCmd</code> or <code>freqCmd</code> .
<code>numFrames</code>	The number of frames in the sampled-sound data. Each frame contains <code>numChannels</code> bytes for 8-bit sound data.
<code>AIFFSampleRate</code>	The sample rate at which the frames were sampled before compression, as expressed in the 80-bit extended data type representation.
<code>markerChunk</code>	Synchronization information. The <code>markerChunk</code> field is not presently used and should be set to <code>NIL</code> .
<code>instrumentChunks</code>	Instrument information.
<code>AESRecording</code>	Information related to audio recording devices.
<code>sampleSize</code>	The number of bits in each sample frame.
<code>futureUse1</code>	Reserved.
<code>futureUse2</code>	Reserved.
<code>futureUse3</code>	Reserved.

Sound Manager

futureUse4	The four futureUse fields are reserved for use by Apple. To maintain compatibility with future releases of system software, you should always set these fields to 0.
sampleArea	An array of interleaved sample points, each of which contains a value similar to the values in a wave-table description. For 8-bit sampled-sound data, these values are interpreted as offset values, where \$80 represents an amplitude of 0. The value \$00 is the largest negative amplitude, and \$FF is the largest positive amplitude.

To compute the total number of bytes of a sample, multiply the values in the numChannels, numFrames, and sampleSize fields and divide by the number of bytes per sample (typically 8 or 16).

Note

Although extended sound headers (and compressed sound headers, described next) support the storage of 16-bit sound, only versions 3.0 and later of the Sound Manager can play 16-bit sounds. If your application uses 16-bit sound, you must convert it to 8-bit sound before earlier versions of the Sound Manager can play it. ♦

Compressed Sound Header Records

To describe compressed sampled-sound data, the Sound Manager uses a compressed sound header record. Compressed sound headers include all of the essential fields of extended sound headers in addition to several fields that pertain to compression. The CmpSoundHeader data type defines the compressed sound header record.

```

TYPE CmpSoundHeader =
PACKED RECORD
    samplePtr:      Ptr;           {if NIL, samples in sampleArea}
    numChannels:   LongInt;        {number of channels in sample}
    sampleRate:    Fixed;          {rate of original sample}
    loopStart:     LongInt;        {loop point beginning}
    loopEnd:       LongInt;        {loop point ending}
    encode:        Byte;           {sample's encoding option}
    baseFrequency: Byte;           {base freq. of original sample}
    numFrames:     LongInt;        {length of sample in frames}
    AIFFSampleRate: Extended80;   {rate of original sample}
    markerChunk:   Ptr;           {reserved}
    format:        OSType;         {data format type}
    futureUse2:    LongInt;        {reserved}
    stateVars:     StateBlockPtr;  {pointer to StateBlock}
    leftOverSamples: LeftOverBlockPtr;
                                {pointer to LeftOverBlock}
    compressionID: Integer;        {ID of compression algorithm}
    packetSize:    Integer;        {number of bits per packet}
    snthID:        Integer;        {unused}

```


Sound Manager

```

sampleSize:      Integer;          {bits in each sample point}
sampleArea:      PACKED ARRAY[0..0] OF Byte;
END;

```

Field descriptions

<code>samplePtr</code>	The location of the compressed sound frames. If <code>samplePtr</code> is <code>NIL</code> , then the frames are located in the <code>sampleArea</code> field of the compressed sound header. Otherwise, <code>samplePtr</code> points to a buffer that contains the frames.
<code>numChannels</code>	The number of channels in the sample.
<code>sampleRate</code>	The sample rate at which the frames were sampled before compression. The approximate sample rates are shown in Table 2-1 on page 2-16. Note that the sample rate is declared as a <code>Fixed</code> data type, but the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768.
<code>loopStart</code>	The beginning of the loop points of the sound before compression. The loop starting and ending points are 0-based.
<code>loopEnd</code>	The end of the loop points of the sound before compression.
<code>encode</code>	The method of encoding (if any) used to generate the sampled-sound data. For a compressed sound header, you should specify the constant <code>cmpSH</code> . Encode option values in the ranges 0 through 63 and 128 to 255 are reserved for use by Apple. You are free to use numbers in the range 64 through 127 for your own encode options.
<code>baseFrequency</code>	The pitch of the original sampled sound. It is not used by <code>bufferCmd</code> . If you wish to make use of <code>baseFrequency</code> with a compressed sound, you must first expand it and then play it with <code>soundCmd</code> and <code>freqDurationCmd</code> .
<code>numFrames</code>	The number of frames contained in the compressed sound header. When you store multiple channels of noncompressed sound, store them as interleaved sample frames (as in AIFF). When you store multiple channels of compressed sounds, store them as interleaved packet frames.
<code>AIFFSampleRate</code>	The sample rate at which the frames were sampled before compression, as expressed in the 80-bit extended data type representation.
<code>markerChunk</code>	Synchronization information. The <code>markerChunk</code> field is not presently used and should be set to <code>NIL</code> .
<code>format</code>	The data format type. This field contains a value of type <code>OSType</code> that defines the compression algorithm, if any, used to generate the audio data. For example, for data generated using MACE 3:1 compression, this field should contain the value <code>'MAC3'</code> . See page 2-86 for a list of the format types defined by Apple. This field is used only if the <code>compressionID</code> field contains the value <code>fixedCompression</code> .

Sound Manager

`futureUse2` This field is reserved for use by Apple. To maintain compatibility with future releases of system software, you should always set this field to 0.

`stateVars` A pointer to a state block. This field is used to store the state variables for a given algorithm across consecutive calls. See “State Blocks” on page 2-119 for a description of the state block.

`leftOverSamples` A pointer to a leftover block. You can use this block to store samples that will be truncated across algorithm invocations. See “Leftover Blocks” on page 2-119 for a description of the leftover block.

`compressionID` The compression algorithm used on the samples in the compressed sound header. You can use a constant to define the compression algorithm.

CONST

```

variableCompression      = -2; {variable-ratio compr.}
fixedCompression        = -1; {fixed-ratio compr.}
notCompressed           = 0;  {noncompressed samples}
threeToOne              = 3;  {3:1 compressed samples}
sixToOne                = 4;  {6:1 compressed samples}

```

The constant `fixedCompression` is available only with Sound Manager versions 3.0 and later. If the `compressionID` field contains the value `fixedCompression`, the Sound Manager reads the `format` field to determine the compression algorithm used to generate the compressed data. Otherwise, the Sound Manager reads the `compressionID` field. Apple reserves the right to use compression IDs in the range 0 through 511. Currently the constant `variableCompression` is not used by the Sound Manager.

`packetSize` The size, in bits, of the smallest element that a given expansion algorithm can work with. You can use a constant to define the packet size.

CONST

```

sixToOnePacketSize      = 8;  {size for 6:1}
threeToOnePacketSize    = 16; {size for 3:1}

```

Beginning with Sound Manager version 3.0, you can specify the value 0 in this field to instruct the Sound Manager to determine the packet size itself.

`snthID` This field is unused. You should set it to 0.

`sampleSize` The size of the sample before it was compressed. The samples passed in the compressed sound header should always be byte-aligned, and any padding done to achieve byte alignment should be done from the left with zeros.

Sound Manager

`sampleArea` The sample frames, but only when the `samplePtr` field is `NIL`. Otherwise, the sample frames are in the location indicated by `samplePtr`.

Sound Double Buffer Header Records

You must fill in a **sound double buffer header record** and two sound double buffer records if you wish to manage your own double buffers. The `SndDoubleBufferHeader` data type defines a sound double buffer header.

```

TYPE SndDoubleBufferHeader =
PACKED RECORD
    dbhNumChannels:      Integer;           {number of sound channels}
    dbhSampleSize:      Integer;           {sample size, if noncompressed}
    dbhCompressionID:  Integer;           {ID of compression algorithm}
    dbhPacketSize:     Integer;           {number of bits per packet}
    dbhSampleRate:     Fixed;             {sample rate}
    dbhBufferPtr:      ARRAY[0..1] OF SndDoubleBufferPtr;
                                     {pointers to SndDoubleBuffer}
    dbhDoubleBack:     ProcPtr;           {pointer to doubleback procedure}
END;
```

Sound Manager versions 3.0 and later support custom compression and decompression algorithms by defining the revised sound double buffer header record, of type `SndDoubleBufferHeader2`. It's identical to the `SndDoubleBufferHeader` data type except that it contains the `dbhFormat` field at the end.

```

TYPE SndDoubleBufferHeader2 =
PACKED RECORD
    dbhNumChannels:      Integer;           {number of sound channels}
    dbhSampleSize:      Integer;           {sample size, if noncompressed}
    dbhCompressionID:  Integer;           {ID of compression algorithm}
    dbhPacketSize:     Integer;           {number of bits per packet}
    dbhSampleRate:     Fixed;             {sample rate}
    dbhBufferPtr:      ARRAY[0..1] OF SndDoubleBufferPtr;
                                     {pointers to SndDoubleBuffer}
    dbhDoubleBack:     ProcPtr;           {pointer to doubleback procedure}
    dbhFormat:         OSType;           {signature of codec}
END;
```

Field descriptions

`dbhNumChannels`

The number of channels for the sound (1 for monophonic sound, 2 for stereo).

`dbhSampleSize`

The sample size for the sound if the sound is not compressed. If the sound is compressed, `dbhSampleSize` should be set to 0. Samples

Sound Manager

that are 1–8 bits have a `dbhSampleSize` value of 8; samples that are 9–16 bits have a `dbhSampleSize` value of 16. Currently, only 8-bit samples are supported. For further information on sample sizes, refer to the AIFF specification.

<code>dbhCompressionID</code>	The compression identification number of the compression algorithm, if the sound is compressed. If the sound is not compressed, <code>dbhCompressionID</code> should be set to 0.
<code>dbhPacketSize</code>	The packet size in bits for the compression algorithm specified by <code>dbhCompressionID</code> , if the sound is compressed.
<code>dbhSampleRate</code>	The sample rate for the sound. Note that the sample rate is declared as a <code>Fixed</code> data type, but the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768.
<code>dbhBufferPtr</code>	An array of two pointers, each of which should point to a valid <code>SndDoubleBuffer</code> record.
<code>dbhDoubleBack</code>	A pointer to the application-defined routine that is called when the double buffers are switched and the exhausted buffer needs to be refilled.
<code>dbhFormat</code>	The data format type. This field contains a value of type <code>OSType</code> that defines the compression algorithm, if any, to be used to decompress the audio data. For example, for data generated using MACE 3:1 compression, this field should contain the value <code>'MAC3'</code> . See page 2-86 for a list of the format types defined by Apple. This field is used only if the <code>dbhCompressionID</code> field contains the value <code>fixedCompression</code> .

The `dbhBufferPtr` array contains pointers to two sound double buffer records, whose format is defined below. These are the two buffers between which the Sound Manager switches until all the sound data has been sent into the sound channel. When you make the call to `SndPlayDoubleBuffer`, the two buffers should both already contain a nonzero number of frames of data.

Sound Double Buffer Records

You must fill in a **sound double buffer header record** if you wish to manage your own double buffers. The `dbhBufferPtr` field of the sound double buffer header record references two sound double buffer records, which you must also fill out. The `SndDoubleBufferHeader` data type defines a sound double buffer header.

```

TYPE SndDoubleBuffer =
PACKED RECORD
    dbNumFrames:    LongInt;           {number of frames in buffer}
    dbFlags:        LongInt;           {buffer status flags}
    dbUserInfo:     ARRAY[0..1] OF LongInt; {for application's use}
    dbSoundData:    PACKED ARRAY[0..0] OF Byte; {array of data}
END;
```

Sound Manager

Field descriptions

<code>dbNumFrames</code>	The number of frames in the <code>dbSoundData</code> array.
<code>dbFlags</code>	Buffer status flags.
<code>dbUserInfo</code>	Two long words into which you can place information that you need to access in your doubleback procedure.
<code>dbSoundData</code>	A variable-length array. You write samples into this array, and the Sound Manager reads samples out of this array.

The buffer status flags field for each of the two buffers can contain either of these values that your doubleback procedure must set when appropriate:

```
CONST
    dbBufferReady      = $00000001;
    dbLastBuffer       = $00000004;
```

All other bits in the `dbFlags` field are reserved by Apple; your application should not modify them.

Chunk Headers

Every chunk in an AIFF or AIFF-C file contains a **chunk header** that defines characteristics of the chunk. The `ChunkHeader` data type defines a chunk header.

```
TYPE ChunkHeader =
RECORD
    ckID:      ID;           {chunk type ID}
    ckSize:   LongInt;      {number of bytes of data}
END;
```

Field descriptions

<code>ckID</code>	The ID of the chunk. An ID is a 32-bit concatenation of any four printable ASCII characters in the range ' ' (space character, ASCII value \$20) through '~' (ASCII value \$7E). Spaces cannot precede printing characters, but trailing spaces are allowed. Control characters are not allowed. See “Chunk IDs” on page 2-98 for a list of the currently recognized chunk IDs.
<code>ckSize</code>	The size of the chunk in bytes, not including the <code>ckID</code> and <code>ckSize</code> fields.

Form Chunks

All sound files begin with a Form Chunk. This chunk defines the type and size of the file and can be thought of as enclosing the remaining chunks in the sound file. The `ContainerChunk` data type defines a Form Chunk.

Sound Manager

```

TYPE ContainerChunk =
RECORD
    ckID:      ID;          {'FORM'}
    ckSize:    LongInt;     {number of bytes of data}
    formType:  ID;          {type of file}
END;

```

Field descriptions

ckID The ID of this chunk. For a Form Chunk, this ID is 'FORM'.

ckSize The size of the data portion of this chunk. Note that the data portion of a Form Chunk is divided into two parts, `formType` and the remaining chunks of the sound file.

formType The type of audio file. For AIFF files, `formType` is 'AIFF'. For AIFF-C files, `formType` is 'AIFC'.

The size of an entire sound file is `ckSize+8`, because the `ckSize` field incorporates the size of all chunks of the sound file, except the sizes of the `ckID` and `ckSize` fields of the Form Chunk itself.

Format Version Chunks

AIFF-C files each contain exactly one Format Version Chunk, but files of type AIFF do not contain any. You can examine the Format Version Chunk to ensure that your application can process an AIFF-C file. The `FormatVersionChunk` data type defines a Format Version Chunk.

```

TYPE FormatVersionChunk =
RECORD
    ckID:      ID;          {'FVER'}
    ckSize:    LongInt;     {4}
    timestamp: LongInt;     {date of format version}
END;

```

Field descriptions

ckID The ID of this chunk. For a Format Version Chunk, this ID is 'FVER'.

ckSize The size of the data portion of this chunk. This value is always 4 in a Format Version Chunk because the `timestamp` field is 4 bytes long (the 8 bytes used by the `ckID` and `ckSize` fields are not included).

timestamp An indication of when the format version for this kind of file was created. The value indicates the number of seconds between midnight, January 1, 1904, and the time at which the AIFF-C file format was created.

Common Chunks

Every AIFF and AIFF-C file contains a Common Chunk that defines some fundamental characteristics of the sampled sound contained in the file. The format of the Common Chunk is different for AIFF and AIFF-C files. As a result, you need to determine the type of file format (by inspecting the `formType` field of the Form Chunk) before reading the Common Chunk.

For AIFF files, the `CommonChunk` data type defines a Common Chunk.

```

TYPE CommonChunk =
RECORD
    ckID:           ID;           {'COMM'}
    ckSize:         LongInt;      {size of chunk data}
    numChannels:    Integer;      {number of channels}
    numSampleFrames: LongInt;     {number of sample frames}
    sampleSize:     Integer;      {number of bits per sample}
    sampleRate:     Extended;     {number of frames per second}
END;
```

Field descriptions

<code>ckID</code>	The ID of this chunk. For a Common Chunk, this ID is 'COMM'.
<code>ckSize</code>	The size of the data portion of this chunk. In AIFF files, this field is always 18 because the 8 bytes used by the <code>ckID</code> and <code>ckSize</code> fields are not included.
<code>numChannels</code>	The number of audio channels contained in the sampled sound. A value of 1 indicates monophonic sound, a value of 2 indicates stereo sound, a value of 4 indicates four-channel sound, and so forth.
<code>numSampleFrames</code>	The number of sample frames in the Sound Data Chunk. Note that this field contains the number of sample frames, not the number of bytes of data and not the number of sample points. For noncompressed sound data, the total number of sample points in the file is <code>numChannels * numSampleFrames</code> .
<code>sampleSize</code>	The number of bits in each sample point of noncompressed sound data. The <code>sampleSize</code> field can contain any integer from 1 to 32. For compressed sound data, this field indicates the number of bits per sample in the original sound data, before compression.
<code>sampleRate</code>	The sample rate at which the sound is to be played back, in sample frames per second.

Extended Common Chunks

An AIFF-C file contains an extended Common Chunk that includes all of the fields of the Common Chunk, but adds two fields that describe the type of compression (if any) used on the audio data. The `ExtCommonChunk` data type defines an extended Common Chunk.

Sound Manager

```

TYPE ExtCommonChunk =
RECORD
    ckID:           ID;           {'COMM'}
    ckSize:         LongInt;      {size of chunk data}
    numChannels:    Integer;      {number of channels}
    numSampleFrames: LongInt;     {number of sample frames}
    sampleSize:     Integer;      {number of bits per sample}
    sampleRate:     Extended;     {number of frames per second}
    compressionType: ID;         {compression type ID}
    compressionName: PACKED ARRAY[0..0] OF Byte;
                                     {compression type name}
END;

```

Field descriptions

ckID The ID of this chunk. For an extended Common Chunk, this ID is 'COMM'.

ckSize The size of the data portion of this chunk. For an extended Common Chunk, this size is 22 plus the number of bytes in the `compressionName` string.

numChannels The number of audio channels contained in the sampled sound. A value of 1 indicates monophonic sound, a value of 2 indicates stereo sound, a value of 4 indicates four-channel sound, and so forth.

numSampleFrames The number of sample frames in the Sound Data Chunk. Note that this field contains the number of sample frames, not the number of bytes of data and not the number of sample points. For noncompressed sound data, the total number of sample points in the file is `numChannels * numSampleFrames`.

sampleSize The number of bits in each sample point of noncompressed sound data. The `sampleSize` field can contain any integer from 1 to 32. For compressed sound data, this field indicates the number of bits per sample in the original sound data, before compression.

sampleRate The sample rate at which the sound is to be played back, in sample frames per second.

compressionType The ID of the compression algorithm, if any, used on the sound data. Compression algorithms supplied by Apple have the following types:

```

CONST
    NoneType           = 'NONE';
    ACE2Type           = 'ACE2';
    ACE8Type           = 'ACE8';
    MACE3Type          = 'MAC3';
    MACE6Type          = 'MAC6';

```


You can define your own compression types, but you should register them with Apple.

compressionName

A human-readable name for the compression algorithm ID specified in the `compressionType` field. If the number of bytes in this field is odd, then it is padded with the digit 0. Compression algorithms supplied by Apple have the following names:

```
CONST
    NoneName           = 'not compressed';
    ACE2to1Name        = 'ACE 2-to-1';
    ACE8to3Name        = 'ACE 8-to-3';
    MACE3to1Name       = 'MACE 3-to-1';
    MACE6to1Name       = 'MACE 6-to-1';
```

You can define your own compression types, but you should register them with Apple.

Sound Data Chunks

AIFF and AIFF-C files generally contain a Sound Data Chunk that contains the actual sampled-sound data. The `SoundDataChunk` data type defines a Sound Data Chunk.

```
TYPE SoundDataChunk =
RECORD
    ckID:      ID;          {'SSND'}
    ckSize:    LongInt;     {size of chunk data}
    offset:    LongInt;     {offset to sound data}
    blockSize: LongInt;     {size of alignment blocks}
END;
```

Field descriptions

<code>ckID</code>	The ID of this chunk. For a Sound Data Chunk, this ID is 'SSND'.
<code>ckSize</code>	The size of the data portion of this chunk. This size does not include the 8 bytes occupied by the values in the <code>ckID</code> and the <code>ckSize</code> fields.
<code>offset</code>	An offset (in bytes) to the beginning of the first sample frame in the chunk data. Most applications do not need to use the <code>offset</code> field and should set it to 0.
<code>blockSize</code>	The size (in bytes) of the blocks to which the sound data is aligned. This field is used in conjunction with the <code>offset</code> field for aligning sound data to blocks. As with the <code>offset</code> field, most applications do not need to use the <code>blockSize</code> field and should set it to 0.

The sampled-sound data follows the `blockSize` field. If the data following the `blockSize` field contains an odd number of bytes, a pad byte with a value of 0 is added at the end to preserve an even length for this chunk. If there is a pad byte, it is not

Sound Manager

included in the `ckSize` field. For information on the format of the sampled-sound data, see “Sound Files” on page 2-81.

Version Records

The functions `SndSoundManagerVersion` and `MACEVersion` return version information using a **version record**. The `NumVersion` data type defines a version record.

```

TYPE NumVersion =
PACKED RECORD
CASE INTEGER OF
  0:
    (majorRev:      SignedByte;    {major revision level in BCD}
     minorAndBugRev: SignedByte;    {minor revision level}
     stage:         SignedByte;    {development stage}
     nonRelRev:     SignedByte);    {nonreleased revision level}
  1:
    (version:       LongInt);       {all 4 fields together}
END;
```

IMPORTANT

A version record has the same structure as the first four fields of a version resource (a resource of type 'vers'). See the chapter “Finder Interface” in *Inside Macintosh: Macintosh Toolbox Essentials* for complete information about version resources. ▲

Field descriptions

`majorRev` The major revision level. This field is a signed byte in binary-coded decimal format.

`minorAndBugRev` The minor revision level. This field is a signed byte in binary-coded decimal format.

`stage` The development stage. You should use the following constants to specify a development stage:

```

CONST
    developStage      = $20;    {prealpha release}
    alphaStage        = $40;    {alpha release}
    betaStage         = $60;    {beta release}
    finalStage        = $80;    {final release}
```

`nonRelRev` The revision level of a prereleased version.

`version` A long integer that contains all four version fields.

Leftover Blocks

The `leftOverSamples` field of a compressed sound header contains a pointer to a leftover block, defined by the `LeftOverBlock` data type.

```
TYPE LeftOverBlock =
RECORD
    count:          LongInt;
    sampleArea:     PACKED ARRAY[0..leftOverBlockSize - 1] OF Byte;
END;
```

Field descriptions

<code>count</code>	The number of bytes in the <code>sampleArea</code> field.
<code>sampleArea</code>	An array of bytes. This field contains samples that are truncated across invocations of the compression algorithm. The size of this field is defined by a constant.

```
CONST
    leftOverBlockSize      = 32;
```

State Blocks

The `stateVars` field of a compressed sound header contains a pointer to a state block, defined by the `StateBlock` data type.

```
TYPE StateBlock =
RECORD
    stateVar:        ARRAY[0..stateBlockSize - 1] OF Integer;
END;
```

Field descriptions

<code>stateVar</code>	An array of integers. This field contains state variables that need to be preserved across invocations of the compression algorithm. The size of this field is defined by a constant.
-----------------------	---

```
CONST
    stateBlockSize        = 64;
```

Sound Manager Routines

This section describes the routines provided by the Sound Manager. You can use these routines to

- play sound resources
- play sounds stored in files directly from disk
- allocate and release sound channels

Sound Manager

- send commands to a sound channel
- obtain information about the Sound Manager, a sound channel, all sound channels, or the system alert sound's status
- compress and expand audio data
- manage the reading and writing of double sound buffers

The section “Application-Defined Routines” on page 2-151 describes routines that your application might need to define, including callback procedures, completion routines, and doubleback procedures.

Assembly-Language Note

Most Sound Manager routines are accessed through the `_SoundDispatch` selector. However, the `SndAddModifier`, `SndControl`, `SndDisposeChannel`, `SndDoCommand`, `SndDoImmediate`, `SndNewChannel`, and `SndPlay` functions and the `SysBeep` procedure are accessed through their own trap macros. See “Summary of the Sound Manager,” which begins on page 2-157, for a list of trap selector numbers. ♦

Playing Sound Resources

You can use the `SysBeep` procedure to play the system alert sound. Alert sounds are stored in the System file as format 1 'snd' resources. You can use the `SndPlay` function to play the sounds that are stored in any 'snd' resource, either format 1 or format 2.

The `SysBeep` and `SndPlay` routines are the highest-level sound routines that the Sound Manager provides. Depending on the needs of your application, you might be able to accomplish all desired sound-related activity simply by using `SysBeep` to produce the system alert sound or by using `SndPlay` to play other sounds that are stored as 'snd' resources.

SysBeep

You can use the `SysBeep` procedure to play the system alert sound.

```
PROCEDURE SysBeep (duration: Integer);
```

duration The duration (in ticks) of the resulting sound. This parameter is ignored except on a Macintosh Plus, Macintosh SE, or Macintosh Classic when the system alert sound is the Simple Beep. The recommended duration is 30 ticks, which equals one-half second.

DESCRIPTION

The `SysBeep` procedure causes the Sound Manager to play the system alert sound at its current volume. If necessary, the Sound Manager loads into memory the sound resource containing the system alert sound and links it to a sound channel. The user selects a system alert sound in the Alert Sounds subpanel of the Sound control panel.

The volume of the sound produced depends on the current setting of the system alert sound volume, which the user can adjust in the Alert Sounds subpanel of the Sound control panel. The system alert sound volume can also be read and set by calling the `GetSysBeepVolume` and `SetSysBeepVolume` routines. If the volume is set to 0 (silent) and the system alert sound is enabled, calling `SysBeep` causes the menu bar to blink once.

SPECIAL CONSIDERATIONS

Because the `SysBeep` procedure moves memory, you should not call it at interrupt time.

SEE ALSO

For information on enabling and disabling the system alert sound, see the description of `SndGetSysBeepState` and `SndSetSysBeepState` on page 2-137. For information on reading or adjusting the system alert sound volume, see “Controlling Volume Levels” beginning on page 2-139.

SndPlay

You can use the `SndPlay` function to play a sound resource that your application has loaded into memory.

```
FUNCTION SndPlay (chan: SndChannelPtr; sndHdl: Handle;
                 async: Boolean): OSErr;
```

<code>chan</code>	A pointer to a valid sound channel. You can pass <code>NIL</code> instead of a pointer to a sound channel if you want the Sound Manager to internally allocate a sound channel in your application’s heap zone.
<code>sndHdl</code>	A handle to the sound resource to play.
<code>async</code>	A Boolean value that indicates whether the sound should be played asynchronously (<code>TRUE</code>) or synchronously (<code>FALSE</code>). This parameter is ignored (and the sound plays synchronously) if <code>NIL</code> is passed in the first parameter.

Sound Manager

DESCRIPTION

The `SndPlay` function attempts to play the sound located at `sndHdl`, which is expected to have the structure of a format 1 or format 2 'snd' resource. If the resource has not yet been loaded, the `SndPlay` function fails and returns the `resProblem` result code.

All commands and data contained in the sound handle are then sent to the channel. Note that you can pass `SndPlay` a handle to some data created by calling the Sound Input Manager's `SndRecord` function as well as a handle to an actual 'snd' resource that you have loaded into memory.

▲ WARNING

In some versions of system software prior to system software version 7.0, the `SndPlay` function will not work properly with sound resources that specify the sound data type twice. This might happen if a resource specifies that a sound consists of sampled-sound data and an application does the same when creating a sound channel. For more information on this problem, see “Allocating Sound Channels” on page 2-20. ▲

The `chan` parameter is a pointer to a sound channel. If `chan` is not `NIL`, it is used as a valid channel. If `chan` is `NIL`, an internally allocated sound channel is used. If you do supply a sound channel pointer in the `chan` parameter, you can play the sound asynchronously. When a sound is played asynchronously, a callback procedure can be called when a `callbackCmd` command is processed by the channel. (This procedure is the callback procedure supplied to `SndNewChannel`.) See “Playing Sounds Asynchronously” on page 2-46 for more information on playing sounds asynchronously. The handle you pass in the `sndHdl` parameter must be locked for as long as the sound is playing asynchronously.

If a format 1 'snd' resource does not specify which type of sound data is to be played, `SndPlay` defaults to square-wave data. `SndPlay` also supports format 2 'snd' resources using sampled-sound data and a `bufferCmd` command. Note that to use `SndPlay` and sampled-sound data with a format 1 'snd' resource, the resource must include a `bufferCmd` command.

SPECIAL CONSIDERATIONS

Because the `SndPlay` function moves memory, you should not call it at interrupt time.

RESULT CODES

<code>noErr</code>	0	No error
<code>notEnoughHardwareErr</code>	-201	Insufficient hardware available
<code>resProblem</code>	-204	Problem loading the resource
<code>badChannel</code>	-205	Channel is corrupt or unusable
<code>badFormat</code>	-206	Resource is corrupt or unusable

SEE ALSO

For an example of how to play a sound resource using the `SndPlay` function, see the chapter “Introduction to Sound on the Macintosh” in this book.

For information on playing a sound resource without using the `SndPlay` function, see “Playing Sounds Using Low-Level Routines” on page 2-61.

Playing From Disk

Use the `SndStartFilePlay`, `SndPauseFilePlay`, and `SndStopFilePlay` functions to manage a continuous play from disk.

SndStartFilePlay

You can call the `SndStartFilePlay` function to initiate a play from disk.

```
FUNCTION SndStartFilePlay (chan: SndChannelPtr; fRefNum: Integer;
                           resNum: Integer; bufferSize: LongInt;
                           theBuffer: Ptr;
                           theSelection: AudioSelectionPtr;
                           theCompletion: ProcPtr;
                           async: Boolean): OSErr;
```

<code>chan</code>	A pointer to a valid sound channel. You can pass <code>NIL</code> instead of a pointer to a sound channel if you want the Sound Manager to internally allocate a sound channel in your application’s heap zone.
<code>fRefNum</code>	The file reference number of the AIFF or AIFF-C file to play. To play a sound resource rather than a sound file, this field should be 0.
<code>resNum</code>	The resource ID number of a sound resource to play. To play a sound file rather than a sound resource, this field should be 0.
<code>bufferSize</code>	The number of bytes of memory that the Sound Manager is to use for input buffering while reading in sound data. For <code>SndStartFilePlay</code> to execute successfully on the slowest Macintosh computers, use a buffer of at least 20,480 bytes. You can pass the value 0 to instruct the Sound Manager to allocate a buffer of the default size.
<code>theBuffer</code>	A pointer to a buffer that the Sound Manager should use for input buffering while reading in sound data. If this parameter is <code>NIL</code> , the Sound Manager allocates two buffers, each half the size of the value specified in the <code>bufferSize</code> parameter. If this parameter is not <code>NIL</code> , the buffer should be a nonrelocatable block of size <code>bufferSize</code> .
<code>theSelection</code>	A pointer to an audio selection record that specifies which portion of a sound should be played. You can pass <code>NIL</code> to specify that the Sound Manager should play the entire sound.

Sound Manager

`theCompletion`

A pointer to a completion routine that the Sound Manager calls when the sound is finished playing. You can pass `NIL` to specify that the Sound Manager should not execute a completion routine. This field is useful only for asynchronous play.

`async`

A Boolean value that indicates whether the sound should be played asynchronously (`TRUE`) or synchronously (`FALSE`). You can play sound asynchronously only if you allocate your own sound channel (using `SndNewChannel`). If you pass `NIL` in the `chan` parameter and `TRUE` for this parameter, the `SndStartFilePlay` function returns the `badChannel` result code.

DESCRIPTION

The `SndStartFilePlay` function begins a continuous play from disk on a sound channel. The `chan` parameter is a pointer to the sound channel. If `chan` is not `NIL`, it is used as a valid channel. If `chan` is `NIL`, an internally allocated sound channel is used for play from disk. This internally allocated sound channel is not passed back to you. Because `SndPauseFilePlay` and `SndStopFilePlay` require a sound-channel pointer, you must allocate your own channel if you wish to use those routines.

The sounds you wish to play can be stored either in a file or in an 'snd' resource. If you are playing a file, then `fRefNum` should be the file reference number of the file to be played and the parameter `resNum` should be set to 0. If you are playing an 'snd' resource, then `fRefNum` should be set to 0 and `resNum` should be the resource ID number (not the file reference number) of the resource to play.

▲ **WARNING**

The `SndStartFilePlay` function might not play 'snd' resources from disk correctly. In particular, the function will not execute correctly if any resource in the resource file containing the 'snd' resource you wish to play has been changed through a call to the `WriteResource` procedure and you have not updated the resource file using the `UpdateResFile` procedure. To avoid this and other problems, you should use the `SndStartFilePlay` function to play only sound files. ▲

SPECIAL CONSIDERATIONS

Because the `SndStartFilePlay` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndStartFilePlay` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0D000008</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>notEnoughHardwareErr</code>	-201	Insufficient hardware available
<code>queueFull</code>	-203	No room in the queue
<code>badChannel</code>	-205	Channel is corrupt or unusable
<code>badFormat</code>	-206	Resource is corrupt or unusable
<code>notEnoughBufferSpace</code>	-207	Insufficient memory available
<code>badFileFormat</code>	-208	File is corrupt or unusable, or not AIFF or AIFF-C
<code>channelBusy</code>	-209	Channel is busy
<code>buffersTooSmall</code>	-210	Buffer is too small
<code>siInvalidCompression</code>	-223	Invalid compression type

SEE ALSO

For an example of how to play a sound file, see the chapter “Introduction to Sound on the Macintosh” in this book.

For information on the format of a completion routine, see “Completion Routines” on page 2-151.

SndPauseFilePlay

You can use the `SndPauseFilePlay` function to toggle the state of a play from disk in progress, just as you might use the pause button on an audiocassette tape player to temporarily pause and then resume play.

```
FUNCTION SndPauseFilePlay (chan: SndChannelPtr): OSErr;
```

`chan` A pointer to a valid sound channel currently processing a play from disk initiated by a call to the `SndStartFilePlay` function.

DESCRIPTION

The `SndPauseFilePlay` function suspends the play from disk on the channel specified by the `chan` parameter if that play from disk is not already paused; the function resumes play if the play from disk is already paused.

The `SndPauseFilePlay` function is used in conjunction with `SndStopFilePlay` to control play from disk on a sound channel. Note that this call can be made only if your application has already called `SndStartFilePlay` with a valid sound channel. You cannot use this function with a synchronous call to `SndStartFilePlay` because, in that case, program control does not return to the caller until after the sound has completely finished playing.

If the channel specified by the `chan` parameter is not being used for play from disk, then `SndPauseFilePlay` returns the result code `channelNotBusy`. If the channel is busy

Sound Manager

and paused, then play from disk is resumed. If the channel is busy and the channel is not paused, then play from disk is suspended.

SPECIAL CONSIDERATIONS

You can call the `SndPauseFilePlay` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndPauseFilePlay` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$02040008</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>queueFull</code>	-203	No room in the queue
<code>badChannel</code>	-205	Channel is corrupt or unusable
<code>channelNotBusy</code>	-211	Channel not currently used

SndStopFilePlay

You can use `SndStopFilePlay` to stop an asynchronous play from disk.

```
FUNCTION SndStopFilePlay (chan: SndChannelPtr;
                          quietNow: Boolean): OSErr;
```

<code>chan</code>	A pointer to a valid sound channel currently processing a play from disk initiated by a call to the <code>SndStartFilePlay</code> function.
<code>quietNow</code>	A Boolean value that indicates whether the play from disk should be stopped immediately (<code>TRUE</code>) or when it completes execution (<code>FALSE</code>).

DESCRIPTION

The `SndStopFilePlay` function either can stop an asynchronous play from disk immediately or can take control of the CPU until a play from disk finishes. The `SndStopFilePlay` function does not return until all asynchronous file I/O calls have completed and any internally allocated memory has been released. If `async` is `FALSE`, then `SndStopFilePlay` lets the sound complete normally and returns only after the sound has completed, all asynchronous file I/O calls have completed, and any internal allocated memory has been released.

For example, you might use the function to stop the playing of a sound file if the user selects an option that turns off sound output while the file is already playing. In that case, you would pass `TRUE` to `quietNow`. Alternatively, you might have started a sound

playing asynchronously so that you could perform other tasks while the sound plays. But you might then finish those other tasks and want to convert the play from disk into a synchronous play. By passing `FALSE` to `quietNow`, you effectively achieve that.

SPECIAL CONSIDERATIONS

Because the `SndStopFilePlay` function might move memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndStopFilePlay` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$03080008</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>badChannel</code>	-205	Channel is corrupt or unusable

Allocating and Releasing Sound Channels

If you use a high-level Sound Manager routine to play sounds, you might be able to let the Sound Manager internally allocate a sound channel. However, to use low-level sound commands or to take full advantage of the Sound Manager's high-level routines, you must allocate your own sound channels. The `SndNewChannel` function allows your application to allocate a new sound channel, and the `SndDisposeChannel` function allows your application to dispose of it.

SndNewChannel

You can use the `SndNewChannel` function to allocate a new sound channel.

```
FUNCTION SndNewChannel (VAR chan: SndChannelPtr; synth: Integer;
    init: LongInt; userRoutine: ProcPtr):
    OSErr;
```

<code>chan</code>	A pointer to a sound channel record. You can pass a pointer whose value is <code>NIL</code> to force the Sound Manager to allocate the sound channel record internally.
<code>synth</code>	The sound data type you intend to play on this channel. If you do not want to specify a specific data type, pass 0 in this parameter. You might do this if you plan to use the channel to play a single sound resource that itself specifies the sound's data type.

Sound Manager

`init` The desired initialization parameters for the channel. If you cannot determine what types of sounds you will be playing on the channel, pass 0 in this parameter. Only sounds defined by wave-table data and sampled-sound data currently use the `init` options. You can use the `Gestalt` function to determine if a sound feature (such as stereo output) is supported by a particular computer.

`userRoutine` A pointer to a callback procedure that the Sound Manager executes whenever it receives a `callBackCmd` command. If you pass `NIL` as the `userRoutine` parameter, then any `callBackCmd` commands sent to this channel are ignored.

DESCRIPTION

The `SndNewChannel` function internally allocates memory to store a queue of sound commands. If you pass a pointer to `NIL` as the `chan` parameter, the function also allocates a sound channel record in your application's heap and returns a pointer to that record. If you do not pass a pointer to `NIL` as the `chan` parameter, then that parameter must contain a pointer to a sound channel record.

If you pass a pointer to `NIL` as the `chan` parameter, then the amount of memory the `SndNewChannel` function allocates to store the sound commands is enough to store 128 sound commands. However, if you pass a pointer to the sound channel record rather than a pointer to `NIL`, the amount of memory allocated is determined by the `qLength` field of the sound channel record. Thus, if you wish to control the size of the sound queue, you must allocate your own sound channel record. Regardless of whether you allocate your own sound channel record, the Sound Manager allocates memory for the sound command queue internally.

The `synth` parameter specifies the sound data type you intend to play on this channel. You can use these constants to specify the data type:

```
CONST
    squareWaveSynth      = 1;          {square-wave data}
    waveTableSynth       = 3;          {wave-table data}
    sampledSynth         = 5;          {sampled-sound data}
```

In Sound Manager versions earlier than version 3.0, only one data type can be produced at any one time. As a result, `SndNewChannel` may fail if you attempt to open a channel specifying a data type other than the one currently being played.

To specify a sound output device other than the current sound output device, pass the value `kUseOptionalOutputDevice` in the `synth` parameter and the signature of the desired sound output device component in the `init` parameter.

```
CONST
    kUseOptionalOutputDevice = -1;
```

The ability to redirect output away from the current sound output device is intended for use by specialized applications that need to use a specific sound output device. In

general, your application should always send sound to the current sound output device selected by the user.

SPECIAL CONSIDERATIONS

Because the `SndNewChannel` function allocates memory, you should not call it at interrupt time.

RESULT CODES

<code>noErr</code>	0	No error
<code>resProblem</code>	-204	Problem loading the resource
<code>badChannel</code>	-205	Channel is corrupt or unusable

SEE ALSO

For an example of a routine that uses the `SndNewChannel` function, see Listing 2-1 on page 2-20.

For information on the format of a callback procedure, see “Callback Procedures” on page 2-152.

SndDisposeChannel

If you allocate a sound channel by calling the `SndNewChannel` function, you must release the memory it occupies by calling the `SndDisposeChannel` function.

```
FUNCTION SndDisposeChannel (chan: SndChannelPtr;
                           quietNow: Boolean): OSErr;
```

<code>chan</code>	A pointer to a valid sound channel record.
<code>quietNow</code>	A Boolean value that indicates whether the channel should be disposed immediately (<code>TRUE</code>) or after sound stops playing (<code>FALSE</code>).

DESCRIPTION

The `SndDisposeChannel` function disposes of the queue of sound commands associated with the sound channel specified in the `chan` parameter. If your application created its own sound channel record in memory or installed a sound as a voice in a channel, the Sound Manager does not dispose of that memory. The Sound Manager also does not release memory associated with a sound resource that you have played on a channel. You might use the `userInfo` field of the sound channel record to store the address of a sound handle you wish to release before disposing of the sound channel itself.

Sound Manager

The `SndDisposeChannel` function can dispose of a channel immediately or wait until the queued commands are processed. If `quietNow` is set to `TRUE`, a `flushCmd` command and then a `quietCmd` command are sent to the channel bypassing the command queue. This removes all commands, stops any sound in progress, and closes the channel. If `quietNow` is set to `FALSE`, then the Sound Manager issues a `quietCmd` command only; it does not bypass the command queue, and it waits until the `quietCmd` command is processed before disposing of the channel.

SPECIAL CONSIDERATIONS

Because the `SndDisposeChannel` function might dispose of memory, you should not call it at interrupt time.

RESULT CODES

<code>noErr</code>	0	No error
<code>badChannel</code>	-205	Channel is corrupt or unusable

Sending Commands to a Sound Channel

Once a sound channel is opened, you can send commands to that channel by issuing requests with the `SndDoCommand` and `SndDoImmediate` functions.

The section “Sound Command Numbers” beginning on page 2-92 lists the sound commands that you can send using `SndDoCommand`, `SndDoImmediate`, or (in several cases) `SndControl`.

SndDoCommand

You can queue a command in a sound channel by calling the `SndDoCommand` function.

```
FUNCTION SndDoCommand (chan: SndChannelPtr; cmd: SndCommand;
                      noWait: Boolean): OSErr;
```

<code>chan</code>	A pointer to a valid sound channel.
<code>cmd</code>	A sound command to be sent to the channel specified in the <code>chan</code> parameter.
<code>noWait</code>	A flag indicating whether the Sound Manager should wait for a free space in a full queue (<code>FALSE</code>) or whether it should return immediately with a <code>queueFull</code> result code if the queue is full (<code>TRUE</code>).

DESCRIPTION

The `SndDoCommand` function sends the sound command specified in the `cmd` parameter to the end of the command queue of the channel specified in the `chan` parameter.

Sound Manager

The `noWait` parameter has meaning only if a sound channel's queue of sound commands is full. If the `noWait` parameter is set to `FALSE` and the queue is full, the Sound Manager waits until there is space to add the command, thus preventing your application from doing other processing. If `noWait` is set to `TRUE` and the queue is full, the Sound Manager does not send the command and returns the `queueFull` result code.

SPECIAL CONSIDERATIONS

Whether `SndDoCommand` moves memory depends on the particular sound command you're sending it. Most of the available sound commands do not cause `SndDoCommand` to move memory and can therefore be issued at interrupt time. Moreover, you can sometimes safely send commands at interrupt time that would otherwise cause memory to move if you've previously issued the `soundCmd` sound command to preconfigure the channel at noninterrupt time.

RESULT CODES

<code>noErr</code>	0	No error
<code>queueFull</code>	-203	No room in the queue
<code>badChannel</code>	-205	Channel is corrupt or unusable

SEE ALSO

For an example of a routine that uses the `SndDoCommand` function, see Listing 2-15 on page 2-42.

SndDoImmediate

You can use the `SndDoImmediate` function to place a sound command in front of a sound channel's command queue.

```
FUNCTION SndDoImmediate (chan: SndChannelPtr; cmd: SndCommand):
    OSErr;
```

<code>chan</code>	A pointer to a sound channel.
<code>cmd</code>	A sound command to be sent to the channel specified in the <code>chan</code> parameter.

DESCRIPTION

The `SndDoImmediate` function operates much like `SndDoCommand`, except that it bypasses the existing command queue of the sound channel and sends the specified command directly to the Sound Manager for immediate processing. This routine also overrides any `waitCmd`, `pauseCmd`, or `syncCmd` commands that might have already been processed. However, other commands already received by the Sound Manager will

Sound Manager

not be interrupted by the `SndDoImmediate` function (although a `quietCmd` command sent via `SndDoImmediate` will quiet a sound already playing).

SPECIAL CONSIDERATIONS

Whether `SndDoImmediate` moves memory depends on the particular sound command you're sending it. Most of the available sound commands do not cause `SndDoImmediate` to move memory and can therefore be issued at interrupt time. Moreover, you can sometimes safely send commands at interrupt time that would otherwise cause memory to move if you've previously issued the `soundCmd` sound command to preconfigure the channel at noninterrupt time.

RESULT CODES

<code>noErr</code>	0	No error
<code>badChannel</code>	-205	Channel is corrupt or unusable

SEE ALSO

For an example of a routine that uses the `SndDoImmediate` function, see Listing 2-4 on page 2-26.

Obtaining Information

To obtain information about whether a computer supports certain sound features, you should use the `Gestalt` function, documented in *Inside Macintosh: Operating System Utilities*. Sometimes, however, you might need information the `Gestalt` function is not able to provide. The Sound Manager provides a number of routines that you can use to obtain additional sound-related information.

You can obtain the version numbers of the Sound Manager and the MACE tools by calling the `SndSoundManagerVersion` and `MACEVersion` functions, respectively. You can obtain information about a sound channel and about all sound channels by calling the `SndControl`, `SndChannelStatus`, and `SndManagerStatus` functions, respectively.

The Sound Manager includes two routines—`SndGetSysBeepState` and `SndSetSysBeepState`—that allow you to determine and alter the status of the system alert sound.

To play a sound resource using low-level Sound Manager routines, you need the address of the sound header stored in the sound resource. Sound Manager versions 3.0 and later provide the `GetSoundHeaderOffset` function that you can use to obtain that information.

SndSoundManagerVersion

You can use `SndSoundManagerVersion` to determine the version of the Sound Manager tools available on a computer.

```
FUNCTION SndSoundManagerVersion: NumVersion;
```

DESCRIPTION

The `SndSoundManagerVersion` function returns a version number that contains the same information as in the first 4 bytes of a 'vers' resource. You might use the `SndSoundManagerVersion` function to determine if a computer has the enhanced Sound Manager, which is necessary for multichannel sound and for continuous plays from disk.

SPECIAL CONSIDERATIONS

You can call the `SndSoundManagerVersion` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndSoundManagerVersion` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$000C0008</code>

SEE ALSO

For information on how to use the `SndSoundManagerVersion` function to determine whether the enhanced Sound Manager is available, see “Obtaining Version Information” on page 2-34.

MACEVersion

You can use `MACEVersion` to determine the version of the MACE tools available on a machine.

```
FUNCTION MACEVersion: NumVersion;
```

DESCRIPTION

The `MACEVersion` function returns a version number that contains the same information as in the first 4 bytes of a 'vers' resource.

SPECIAL CONSIDERATIONS

You can call the `MACEVersion` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `MACEVersion` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00000010</code>

SndControl

You can obtain information about a sound data type by using the `SndControl` function. In Sound Manager version 3.0 and later, however, you virtually never need to call `SndControl`. The capabilities that `SndControl` provides are either provided by the `Gestalt` function or are no longer supported. The `SndControl` function is documented here for completeness only.

```
FUNCTION SndControl (id: Integer; VAR cmd: SndCommand): OSErr;
```

`id` The sound data type you want to get information about.
`cmd` A sound command.

DESCRIPTION

The `SndControl` function sends a control command directly to the Sound Manager to get information about a specific data type. The available data types are specified by constants:

```
CONST
    squareWaveSynth    = 1;    {square-wave data}
    waveTableSynth     = 3;    {wave-table data}
    sampledSynth       = 5;    {sampled-sound data}
```

You can call `SndControl` even if no channel has been created for the type of data you want to get information about. `SndControl` can be used with the `availableCmd` or `versionCmd` sound commands to request information. The requested information is returned in the sound command record specified by the `cmd` parameter.

IMPORTANT

The `SndControl` function can indicate only whether a particular data format supports some feature (for example, stereo output), not whether the available sound hardware also supports that feature. In general, you should use the `Gestalt` function to determine whether the sound features you need are available in the current operating environment. ▲

Sound Manager

In Sound Manager version 2.0, you can also use the `totalLoadCmd` and `loadCmd` commands to get information about the amount of CPU time consumed by sound-related processing. However, these commands are not very accurate and are not supported by version 3.0 and later.

SPECIAL CONSIDERATIONS

You should not call the `SndControl` function at interrupt time.

RESULT CODES

`noErr` 0 No error

SEE ALSO

See the list of sound commands in “Sound Command Numbers” beginning on page 2-92 for a complete description of the sound commands supported by `SndControl`.

SndChannelStatus

You can use the `SndChannelStatus` function to determine the status of a sound channel.

```
FUNCTION SndChannelStatus (chan: SndChannelPtr;
                           theLength: Integer;
                           theStatus: SCStatusPtr): OSErr;
```

`chan` A pointer to a valid sound channel.

`theLength` The size in bytes of the sound channel status record. You should set this field to `SizeOf(SCStatus)`.

`theStatus` A pointer to a sound channel status record.

DESCRIPTION

If the `SndChannelStatus` function executes successfully, the fields of the record specified by `theStatus` accurately describe the sound channel specified by `chan`.

SPECIAL CONSIDERATIONS

You can call the `SndChannelStatus` function at interrupt time.

Sound Manager

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndChannelStatus` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00100008</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>paramErr</code>	-50	A parameter is incorrect
<code>badChannel</code>	-205	Channel is corrupt or unusable

SEE ALSO

For information on the structure of a sound channel status record, see “Sound Channel Status Records” on page 2-101.

SndManagerStatus

You can use the `SndManagerStatus` function to determine information about all sound channels currently allocated.

```
FUNCTION SndManagerStatus (theLength: Integer;
                          theStatus: SMStatusPtr): OSErr;
```

`theLength` The size in bytes of the Sound Manager status record. You should set this field to `SizeOf(SMStatus)`.

`theStatus` A pointer to a Sound Manager status record.

DESCRIPTION

The `SndManagerStatus` function determines information about all currently allocated sound channels. If the `SndManagerStatus` function executes successfully, the fields of the record specified by `theStatus` accurately describe the current status of the Sound Manager.

SPECIAL CONSIDERATIONS

You can call the `SndManagerStatus` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndManagerStatus` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00140008</code>

RESULT CODES

noErr 0 No error

SndGetSysBeepState

You can use the `SndGetSysBeepState` procedure to determine if the system alert sound is enabled.

```
PROCEDURE SndGetSysBeepState (VAR sysBeepState: Integer);
```

```
sysBeepState
```

On exit, the state of the system alert sound.

DESCRIPTION

The `SndGetSysBeepState` procedure returns one of two states in the `sysBeepState` parameter, either the `sysBeepDisable` or the `sysBeepEnable` constant.

```
CONST
```

```
sysBeepDisable     = $0000;     {system alert sound disabled}
sysBeepEnable     = $0001;     {system alert sound enabled}
```

SPECIAL CONSIDERATIONS

You can call the `SndGetSysBeepState` procedure at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndGetSysBeepState` procedure are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00180008</code>

SndSetSysBeepState

You can use the `SndSetSysBeepState` function to set the state of the system alert sound.

```
FUNCTION SndSetSysBeepState (sysBeepState: Integer): OSErr;
```

```
sysBeepState
```

The desired state of the system alert sound.

Sound Manager

DESCRIPTION

You can use the `SndSetSysBeepState` function to temporarily disable the system alert sound while you play a sound and then enable the alert sound when you are done. The `sysBeepState` parameter should be set to either `sysBeepDisable` or `sysBeepEnable`.

If your application disables the system alert sound, be sure to enable it when your application gets a suspend event.

SPECIAL CONSIDERATIONS

You can call the `SndSetSysBeepState` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndSetSysBeepState` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$001C0008</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>paramErr</code>	-50	A parameter is incorrect

GetSoundHeaderOffset

You can use the `GetSoundHeaderOffset` function to get the offset from the beginning of a sound resource to the embedded sound header.

```
FUNCTION GetSoundHeaderOffset (sndHdl: Handle;
                               VAR offset: LongInt): OSErr;
```

<code>sndHdl</code>	A handle to a sound resource.
<code>offset</code>	On exit, the offset from the beginning of the sound resource specified by the <code>sndHdl</code> parameter to the beginning of the sound header within that sound resource.

DESCRIPTION

The `GetSoundHeaderOffset` function returns, in the `offset` parameter, the number of bytes from the beginning of the sound resource specified by the `sndHdl` parameter to the sound header that is contained within that resource. You might need this information if you want to use the address of that sound header in a sound command (such as the `soundCmd` or `bufferCmd` sound command).

The handle passed to `GetSoundHeaderOffset` does not have to be locked.

SPECIAL CONSIDERATIONS

The `GetSoundHeaderOffset` function is available only in version 3.0 and later of the Sound Manager. See “Obtaining a Pointer to a Sound Header” beginning on page 2-57 for a function you can call in earlier versions of the Sound Manager to obtain the same information.

You can call the `GetSoundHeaderOffset` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetSoundHeaderOffset` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$04040024</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>badFormat</code>	-206	Resource is corrupt or unusable

SEE ALSO

See Listing 2-27 on page 2-57 for an example of calling `GetSoundHeaderOffset`.

Controlling Volume Levels

You can use the `GetSysBeepVolume` and `SetSysBeepVolume` functions to get and set the volume level of the system alert sound. You can use `GetDefaultOutputVolume` and `SetDefaultOutputVolume` to get and set the default output volume for a particular output device.

IMPORTANT

These four functions are available only in Sound Manager version 3.0 and later. ▲

With all of these functions, you specify a volume with a 16-bit value, where 0 represents no volume (that is, silence) and 256 (hexadecimal `$0100`) represents full volume. The right and left volumes of a stereo sound are encoded as the high word and the low word, respectively, of a 32-bit value. Moreover, it's possible to overdrive a particular volume level if you need to amplify a low signal. For example, the long word `$02000200` specifies a volume level of twice full volume on both the left and right channels of a stereo sound.

In addition to the four functions described in this section, Sound Manager version 3.0 introduces two new sound commands, `getVolumeCmd` and `volumeCmd`, that you can use to get and set the volume of a particular sound channel. See page 2-96 for details on these two sound commands; see “Managing Sound Volumes” beginning on page 2-31 for a code listing that uses the `volumeCmd` command.

GetSysBeepVolume

You can use the `GetSysBeepVolume` function to determine the current volume of the system alert sound.

```
FUNCTION GetSysBeepVolume (VAR level: LongInt): OSErr;
```

`level` On exit, the current volume level of the system alert sound.

DESCRIPTION

The `GetSysBeepVolume` function returns, in the `level` parameter, the current volume level of the system alert sound. The values returned in the high and low words of the `level` parameter range from 0 (silence) to \$0100 (full volume).

SPECIAL CONSIDERATIONS

The `GetSysBeepVolume` function is available only in versions 3.0 and later of the Sound Manager. You can call this function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetSysBeepVolume` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$02240024</code>

RESULT CODES

<code>noErr</code>	0	No error
--------------------	---	----------

SetSysBeepVolume

You can use the `SetSysBeepVolume` function to set the current volume of the system alert sound.

```
FUNCTION SetSysBeepVolume (level: LongInt): OSErr;
```

`level` The desired volume level of the system alert sound.

DESCRIPTION

The `SetSysBeepVolume` function sets the current volume level of the system alert sound. The values you can specify in the high and low words of the `level` parameter

range from 0 (silence) to \$0100 (full volume). Any calls to the `SysBeep` procedure use the volume set by the most recent call to `SetSysBeepVolume`.

SPECIAL CONSIDERATIONS

The `SetSysBeepVolume` function is available only in versions 3.0 and later of the Sound Manager. You can call this function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SetSysBeepVolume` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$02280024</code>

RESULT CODES

<code>noErr</code>	0	No error
--------------------	---	----------

GetDefaultOutputVolume

You can use the `GetDefaultOutputVolume` function to determine the default volume of a sound output device.

```
FUNCTION GetDefaultOutputVolume (VAR level: LongInt): OSErr;
```

`level` On exit, the default volume level of a sound output device.

DESCRIPTION

The `GetDefaultOutputVolume` function returns, in the `level` parameter, the default volume of a sound output device. The values returned in the high and low words of the `level` parameter range from 0 (silence) to \$0100 (full volume).

SPECIAL CONSIDERATIONS

The `GetDefaultOutputVolume` function is available only in versions 3.0 and later of the Sound Manager. You can call this function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetDefaultOutputVolume` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$022C0024</code>

Sound Manager

RESULT CODES

noErr	0	No error
-------	---	----------

SetDefaultOutputVolume

You can use the `SetDefaultOutputVolume` function to set the default volume of a sound output device.

```
FUNCTION SetDefaultOutputVolume (level: LongInt): OSErr;
```

`level` The desired default volume level of a sound output device.

DESCRIPTION

The `SetDefaultOutputVolume` function sets the default volume of a sound output device. The values you can specify in the high and low words of the `level` parameter range from 0 (silence) to \$0100 (full volume).

SPECIAL CONSIDERATIONS

The `SetDefaultOutputVolume` function is available only in versions 3.0 and later of the Sound Manager. You can call this function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SetDefaultOutputVolume` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$02300024</code>

RESULT CODES

noErr	0	No error
-------	---	----------

Compressing and Expanding Audio Data

You can use the procedures `Comp3to1` and `Comp6to1` to compress sound data. You can use the procedures `Exp1to3` and `Exp1to6` to expand compressed audio data.

Comp3to1

You can use the `Comp3to1` procedure to compress sound data at a ratio of 3:1.

```
PROCEDURE Comp3to1 (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
                   inState: Ptr; outState: Ptr;
                   numChannels: LongInt; whichChannel: LongInt);
```

<code>inBuffer</code>	A pointer to a buffer of samples to be compressed.
<code>outBuffer</code>	A pointer to a buffer where the samples are to be written.
<code>cnt</code>	The number of samples to compress.
<code>inState</code>	A pointer to a 128-byte buffer from which the input state of the algorithm is read, or <code>NIL</code> . To initialize the algorithm, this buffer should be filled with zeros.
<code>outState</code>	A pointer to a 128-byte buffer to which the output state of the algorithm is written, or <code>NIL</code> . This buffer might be the same as that specified by the <code>inState</code> parameter.
<code>numChannels</code>	The number of channels in the buffer pointed to by the <code>inBuffer</code> parameter.
<code>whichChannel</code>	The channel to compress, when <code>numChannels</code> is greater than 1. This parameter must be in the range of 1 to <code>numChannels</code> .

DESCRIPTION

The `Comp3to1` procedure compresses `cnt` samples of sound stored in the buffer specified by `inBuffer` and places the result in the buffer specified by `outBuffer`, which must be at least `cnt/3` bytes in size. The original samples can be monophonic or include multiple channels of sound, but they must be in 8-bit offset binary format. Also, if `numChannels` is greater than 1, then the noncompressed sound must be stored in interleaved format on a sample basis.

If you compress polyphonic sound, you retain only one channel of sound, which you specify in the `whichChannel` parameter. Thus, if you use the `Comp3to1` procedure to compress three-channel sound, you will have effectively compressed the sound to one-ninth its original size in bytes. To retain multiple channels of sound after compression, you must call the `Comp3to1` procedure for each channel to be compressed and then interleave the compressed sound data on a packet basis.

The `Comp3to1` procedure compresses every 48 bytes of sound data to exactly 16 bytes of compressed sound data and compresses remaining bytes to no more than one-third the original size.

You can use the `inState` and `outState` parameters to allow the MACE compression routines to preserve information about algorithms across calls. Alternatively, you may pass `NIL` state buffers and let the Sound Manager allocate the buffers internally.

SPECIAL CONSIDERATIONS

Because the `Comp3to1` procedure might allocate and dispose of memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `Comp3to1` procedure are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00040010</code>

Comp6to1

You can use the `Comp6to1` procedure to compress sound data at a ratio of 6:1.

```
PROCEDURE Comp6to1 (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
                   inState: Ptr; outState: Ptr;
                   numChannels: LongInt; whichChannel: LongInt);
```

<code>inBuffer</code>	A pointer to a buffer of samples to be compressed.
<code>outBuffer</code>	A pointer to a buffer where the samples are to be written.
<code>cnt</code>	The number of samples to compress.
<code>inState</code>	A pointer to a 128-byte buffer from which the input state of the algorithm is read, or <code>NIL</code> . To initialize the algorithm, this buffer should be filled with zeros.
<code>outState</code>	A pointer to a 128-byte buffer to which the output state of the algorithm is written, or <code>NIL</code> . This buffer might be the same as that specified by the <code>inState</code> parameter.
<code>numChannels</code>	The number of channels in the buffer pointed to by the <code>inBuffer</code> parameter.
<code>whichChannel</code>	The channel to compress, when <code>numChannels</code> is greater than 1. This parameter must be in the range of 1 to <code>numChannels</code> .

DESCRIPTION

The `Comp6to1` procedure compresses `cnt` samples of sound stored in the buffer specified by `inBuffer` and places the result in the buffer specified by `outBuffer`, which must be at least `cnt/6` bytes in size. The `Comp6to1` procedure works much like the `Comp3to1` procedure, but compresses every 48 bytes of sound data to exactly 8 bytes of compressed sound data and compresses remaining bytes to no more than one-sixth the original size.

SPECIAL CONSIDERATIONS

Because the `Comp6to1` procedure might allocate and dispose of memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `Comp6to1` procedure are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$000C0010</code>

Exp1to3

You can use the `Exp1to3` procedure to expand a buffer of sound samples you previously have compressed with the `Comp3to1` procedure.

```
PROCEDURE Exp1to3 (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
                  inState: Ptr; outState: Ptr;
                  numChannels: LongInt; whichChannel: LongInt);
```

`inBuffer` A pointer to a buffer of packets to be expanded.

`outBuffer` A pointer to a buffer where the expanded samples will be written.

`cnt` The number of packets to expand.

`inState` A pointer to a 128-byte buffer from which the input state of the algorithm is read, or `NIL`. To initialize the algorithm, this buffer should be filled with zeros.

`outState` A pointer to a 128-byte buffer to which the output state of the algorithm is written, or `NIL`. This buffer might be the same as that specified by the `inState` parameter.

`numChannels` The number of channels in the buffer pointed to by the `inBuffer` parameter.

`whichChannel` The channel to expand, when `numChannels` is greater than 1. This parameter must be in the range of 1 to `numChannels`.

DESCRIPTION

The `Exp1to3` procedure expands `cnt` packets of sound stored in the buffer specified by `inBuffer` and places the result in the buffer specified by `outBuffer`, whose size must be at least `cnt` packets * 2 bytes per packet * 3, or `cnt` * 6 bytes. If `numChannels` is greater than 1, then the compressed sound must be stored in interleaved format on a packet basis.

Sound Manager

If you expand compressed sound data that includes multiple sound channels, you retain only one channel of sound, which you specify in the `whichChannel` parameter. Thus, if you use the `Exp1to3` procedure to expand three-channel sound, the output buffer will be the same size as the input buffer since only one channel is retained. To retain multiple channels of sound after expansion, you must call the `Exp1to3` procedure for each channel to be expanded and then interleave the expanded sound data on a sample basis.

The `Exp1to3` procedure expands every packet of sampled-sound data to exactly 6 bytes.

You can use the `inState` and `outState` parameters to allow the MACE compression routines to preserve information about algorithms across calls. Alternatively, you may pass `NIL` state buffers and let the Sound Manager allocate the buffers internally.

SPECIAL CONSIDERATIONS

Because the `Exp1to3` procedure might allocate memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `Exp1to3` procedure are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00080010</code>

Exp1to6

You can use the `Exp1to6` procedure to expand a buffer of sound samples you previously have compressed with the `Comp6to1` procedure.

```
PROCEDURE Exp1to6 (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
                  inState: Ptr; outState: Ptr;
                  numChannels: LongInt; whichChannel: LongInt);
```

<code>inBuffer</code>	A pointer to a buffer of packets to be expanded.
<code>outBuffer</code>	A pointer to a buffer where the expanded samples will be written.
<code>cnt</code>	The number of packets to expand.
<code>inState</code>	A pointer to a 128-byte buffer from which the input state of the algorithm is read, or <code>NIL</code> . To initialize the algorithm, this buffer should be filled with zeros.
<code>outState</code>	A pointer to a 128-byte buffer to which the output state of the algorithm is written, or <code>NIL</code> . This buffer might be the same as that specified by the <code>inState</code> parameter.
<code>numChannels</code>	The number of channels in the buffer pointed to by the <code>inBuffer</code> parameter.

Sound Manager

`whichChannel`

The channel to expand, when `numChannels` is greater than 1. This parameter must be in the range of 1 to `numChannels`.

DESCRIPTION

The `Exp1to6` procedure expands `cnt` packets of sound stored in the buffer specified by `inBuffer` and places the result in the buffer specified by `outBuffer`, whose size must be at least `cnt` packets * 1 byte per packet * 6, or `cnt` * 6 bytes. If `numChannels` is greater than 1, then the compressed sound must be stored in interleaved format on a packet basis. The `Exp1to6` procedure works just like the `Exp1to3` procedure, but expands 1-byte packets rather than 2-byte packets.

SPECIAL CONSIDERATIONS

Because the `Exp1to6` procedure might allocate memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `Exp1to6` procedure are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00100010</code>

Managing Double Buffers

If you wish to customize the double buffering algorithm that the Sound Manager uses to manage a play from disk, you can use the `SndPlayDoubleBuffer` function. The Sound Manager's high-level play-from-disk routines make extensive use of this function.

SndPlayDoubleBuffer

The `SndPlayDoubleBuffer` function is a low-level routine that gives you maximum efficiency and control over double buffering while still maintaining compatibility with the Sound Manager.

```
FUNCTION SndPlayDoubleBuffer (chan: SndChannelPtr;
                             theParams: SndDoubleBufferHeaderPtr): OSErr;
```

`chan` A pointer to a valid sound channel.

`theParams` A pointer to a sound double buffer header record.

Sound Manager

DESCRIPTION

The `SndPlayDoubleBuffer` function launches a low-level sound play using the information in the double buffer header record specified by `theParams`. After your application calls this function, the Sound Manager repeatedly calls the `doubleback` procedure you specify in the double buffer header record. The `doubleback` procedure then manages the filling of buffers of sound data from disk whenever one of the two buffers specified in the double buffer header record becomes exhausted.

SPECIAL CONSIDERATIONS

Because the `SndPlayDoubleBuffer` function might move memory, you should not call it at interrupt time.

You can use the `SndPlayDoubleBuffer` function only on a Macintosh computer that supports the play-from-disk routines. For information on how to determine whether a computer supports these routines, see “Testing for Multichannel Sound and Play-From-Disk Capabilities” on page 2-35.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndPlayDoubleBuffer` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00200008</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>badChannel</code>	-205	Channel is corrupt or unusable

SEE ALSO

For information on the format of a `doubleback` procedure, see “Doubleback Procedures” on page 2-153.

Performing Unsigned Fixed-Point Arithmetic

This section describes the `UnsignedFixMulDiv` function provided by the Sound Manager that you can use to perform multiplication and division on unsigned fixed-point numbers.

UnsignedFixMulDiv

You can use the `UnsignedFixMulDiv` function to perform multiplications and divisions on unsigned fixed-point numbers. You'll typically use it to calculate sample rates.

```
FUNCTION UnsignedFixMulDiv (value: UnsignedFixed;
                           multiplier: UnsignedFixed;
                           divisor: UnsignedFixed):
                           UnsignedFixed;
```

`value` The value to be multiplied and divided.

`multiplier` The multiplier to be applied to the value in the `value` parameter.

`divisor` The divisor to be applied to the value in the `value` parameter.

DESCRIPTION

The `UnsignedFixMulDiv` function returns the fixed-point number that is the value of the `value` parameter, multiplied by the value in the `multiplier` parameter and divided by the value in the `divisor` parameter. Note that `UnsignedFixMulDiv` performs both operations before returning. If you want to perform only a multiplication or only a division, pass the value `$00010000` for whichever parameter you want to ignore. For example, to determine the sample rate that is twice that of the 22 kHz rate, you can use `UnsignedFixMulDiv` as follows:

```
myNewRate := UnsignedFixMulDiv(rate22kHz, $00020000, $00010000);
```

Similarly, to determine the sample rate that is half that of the 44 kHz rate, you can use `UnsignedFixMulDiv` as follows:

```
myNewRate := UnsignedFixMulDiv(rate44kHz, $00010000, $00020000);
```

SPECIAL CONSIDERATIONS

The `UnsignedFixMulDiv` function is available only in versions 3.0 and later of the Sound Manager.

Linking Modifiers to Sound Channels

Early versions of the Sound Manager allowed application developers to use modifiers to alter sound commands before being processed by the Sound Manager. The Sound Manager no longer supports this capability. `SndAddModifier` is documented here for completeness only.

SndAddModifier

The Sound Manager previously used the `SndAddModifier` function to link modifiers to sound channels.

```
FUNCTION SndAddModifier (chan: SndChannelPtr; modifier: ProcPtr;
                        id: Integer; init: LongInt): OSErr;
```

`chan` A pointer to a valid sound channel.

`modifier` A pointer to a modifier function to be added to the sound channel specified by `chan`. This field is obsolete.

`id` The resource ID of the modifier to be linked to the sound channel.

`init` The initialization parameters for the sound channel specified by `chan`.

DESCRIPTION

The `SndAddModifier` function installs a modifier into an open channel specified in the `chan` parameter. The `modifier` parameter should be `NIL`, and the `id` parameter is the resource ID of the modifier to be linked to the sound channel. `SndAddModifier` causes the Sound Manager to load the specified 'sntn' resource, lock it in memory, and link it to the channel specified.

IMPORTANT

The `SndAddModifier` function is for internal Sound Manager use only. You should not call it in your application. ▲

The only supported use of the `SndAddModifier` function is to change the data type associated with a sound channel. For example, you can pass the constant `sampledSynth` in the `id` parameter to reconfigure a sound channel for sampled-sound data. You should, however, set a sound channel's data type when you call `SndNewChannel`, not by calling `SndAddModifier`.

SPECIAL CONSIDERATIONS

You should not use the `SndAddModifier` function.

RESULT CODES

<code>noErr</code>	0	No error
<code>resProblem</code>	-204	Problem loading the resource
<code>badChannel</code>	-205	Channel is corrupt or unusable

SEE ALSO

To modify sampled-sound data immediately before the Sound Manager plays it, you can customize double buffering routines so that your application can modify sampled-sound

data when it fills a buffer of sound data for the Sound Manager to play. For more information, see “Using Double Buffers” on page 2-68.

To change the initialization options for a sound channel, you can use the `reInitCmd` command. For a description of that command, see “Sound Command Numbers” beginning on page 2-92.

Application-Defined Routines

The Sound Manager allows you to define a completion routine that execute when a play from disk finishes executing, a callback procedure that executes whenever your application issues the `callbackCmd` command, and a doubleback procedure that you must define if you wish to customize the double buffering of data during a play from disk.

Completion Routines

You can specify a completion routine as the seventh parameter to the `SndStartFilePlay` function. The completion routine executes when the sound file finishes playing (unless sound play was stopped by the `SndStopFilePlay` function).

MyCompletionRoutine

A Sound Manager completion routine has the following syntax:

```
PROCEDURE MyFilePlayCompletionRoutine (chan: SndChannelPtr);
```

`chan` A pointer to the sound channel on which a play from disk has completed.

DESCRIPTION

The Sound Manager executes your completion routine when a play from disk on the channel specified by the `chan` parameter finishes. You might use the completion routine to set a global flag that alerts the application that it must dispose of the sound channel.

SPECIAL CONSIDERATIONS

A completion routine is called at interrupt time. It must not make any calls to the Memory Manager, either directly or indirectly. If your completion routine needs to access your application’s global variables, you must ensure that register A5 contains your application’s A5. (You can use the `userInfo` field of the sound channel pointed to by the `chan` parameter to pass that value to your completion routine.)

ASSEMBLY-LANGUAGE INFORMATION

Because this routine is called at interrupt time, it must preserve all registers other than A0–A1 and D0–D2.

SEE ALSO

For information on how you can use completion routines to help manage an asynchronous play from disk, see “Managing an Asynchronous Play From Disk” on page 2-52.

Callback Procedures

You can specify a callback procedure as the fourth parameter to the `SndNewChannel` function. The callback procedure executes whenever the Sound Manager processes a `callBackCmd` command for the channel.

MyCallbackProcedure

A callback procedure has the following syntax:

```
PROCEDURE MyCallbackProcedure (theChan: SndChannelPtr;
                               theCmd: SndCommand);
```

`theChan` A pointer to the sound channel on which a `callBackCmd` command was issued.

`theCmd` The sound command record in which a `callBackCmd` command was issued.

DESCRIPTION

The Sound Manager executes the callback procedure associated with a sound channel whenever it processes a `callBackCmd` command for the channel. You can use a callback procedure to set a global flag that alerts the application that it must dispose of the sound channel. Or, you can use a callback procedure so that your application can synchronize a series of sound commands with other actions.

SPECIAL CONSIDERATIONS

A callback procedure is called at interrupt time. It must not make any calls to the Memory Manager, either directly or indirectly. If your callback procedure needs to access your application’s global variables, you must ensure that register A5 contains your application’s A5. (You can use the `userInfo` field of the sound channel pointed to by the `theChan` parameter or the `param2` field of the sound command specified in the `theCmd` parameter to pass that value to your callback procedure.)

ASSEMBLY-LANGUAGE INFORMATION

Because a callback procedure is called at interrupt time, it must preserve all registers other than A0–A1 and D0–D2.

SEE ALSO

For information on how you can use callback procedures when playing sound asynchronously, see “Using Callback Procedures” on page 2-47.

Doubleback Procedures

If you wish to customize the double buffering of sound during a play from disk, you must use the `SndPlayDoubleBuffer` function and define a doubleback procedure. Doubleback procedures also give you the power to modify sampled-sound data immediately before the Sound Manager plays it.

MyDoubleBackProc

A doubleback procedure has the following syntax:

```
PROCEDURE MyDoubleBackProc (chan: SndChannelPtr;
                             exhaustedBuffer: SndDoubleBufferPtr);
```

`chan` A pointer to a sound channel on which a play from disk is executing.

`exhaustedBuffer`
 A pointer to a sound double buffer record

DESCRIPTION

The Sound Manager calls the doubleback procedure associated with a play from disk whenever the Sound Manager has exhausted the buffer. As the doubleback procedure refills the buffer, the Sound Manager plays the other buffer. Your application might also call the doubleback procedure twice to fill both buffers before the initial call to `SndPlayDoubleBuffer` function.

When your doubleback procedure is called, it must

- fill the buffer specified in the `exhaustedBuffer` parameter with the next set of sound frames that the Sound Manager must play
- set the `dbNumFrames` field of the sound double buffer record to the number of frames in the buffer
- set the `dbBufferReady` bit of the `dbFlags` field of the sound double buffer record

If your doubleback procedure fills the buffer with the last frames of sound that need to be played, then your procedure should set the `dbLastBuffer` bit of the `dbFlags` field of the sound double buffer record.

Sound Manager

Your doubleback procedure might fill the buffer with data from any of several sources. For example, the doubleback procedure might compute the data, copy it from elsewhere in RAM, or read it from disk. A doubleback procedure can also read data from disk and then modify the data. This might be useful, for example, if you would like the Sound Manager to be able to play sampled-sound data stored in 16-bit binary offset format. Your doubleback procedure could translate the data to the 8-bit binary offset format that the Sound Manager can read before placing it in the buffer.

SPECIAL CONSIDERATIONS

A doubleback procedure is called at interrupt time. It must not make any calls to the Memory Manager, either directly or indirectly. If your callback procedure needs to access your application's global variables, you must ensure that register A5 contains your application's A5. (You can use one of the two long integers in the `dbUserInfo` field of the sound double buffer record specified by the `exhaustedBuffer` parameter to pass that value to your callback procedure.)

ASSEMBLY-LANGUAGE INFORMATION

Because a doubleback procedure is called at interrupt time, it must preserve all registers other than A0–A1 and D0–D2.

SEE ALSO

For an example of how you might use doubleback procedures, see “Using Double Buffers” on page 2-68.


Resources

This section describes the structure of format 1 and format 2 sound resources. For a more complete discussion of the structure of sound resources, see “Sound Resources” on page 2-74.

The Sound Resource

You can store sound commands and sound data as a resource with the resource type `'snd '`. Resource IDs from 0 to 8191 are reserved by Apple Computer, Inc. You may use all other resource IDs for your `'snd '` resources.

You can use the `GetResource` function to search all open resource files for the first `'snd '` resource type with the given ID. The `'snd '` resource type defines a sound resource. Figure 2-8 shows the structure of a sound resource.

Figure 2-8 The 'snd' resource type

Often, you can create a sound resource simply by using the `SndRecord` function, documented in the chapter “Introduction to Sound on the Macintosh” in this book. However, you can also define a sound resource manually. This is especially useful for sound resources that are simply series of sound commands and contain no sampled-sound data. Also, you might construct a sound resource that contains wave-table data manually. A sound resource contains the following elements:


- **Sound resource header.** The gives information about the format of a sound resource, as explained below.
- **Number of sound commands.** Following the sound resource header is a word indicating the number of sound commands contained in the resource.
- **Sound commands.** Each sound command is 8 bytes, which includes 2 bytes that identify the command, 2 bytes for the command's first parameter, and 4 bytes for the command's second parameter. When a sound command contained in an 'snd' resource has associated sound data, the high bit (defined by the `dataOffsetFlag` constant) should be set. This tells the Sound Manager that the value in the second parameter is an offset from the beginning of the resource and not a pointer to a memory location.
- **Sound data.** For a format 1 'snd' resource, this field might contain wave-table data or a sampled sound header that includes sampled-sound data. For a format 2 'snd' resource, this field should contain a sampled sound header that includes sampled-sound data.

The format of the sound resource header differs depending on whether the 'snd' resource is format 1 or format 2. Figure 2-9 illustrates the formats of the two types of

Sound Manager

sound resource header. Both sound headers begin with a format field, which defines the format of the sound resource as either \$0001 or \$0002.

Figure 2-9 The sound resource header



- **Format 1 sound resource header.** For format 1 'snd ' resources, the sound resource header includes a word that indicates the number of data types to be sent to the sound channel. Because a sound channel cannot play more than one type of sound data, you should typically specify either \$00 or \$01 in this field. If you specify \$01 or more, then the sound resource header contains both a word specifying the data type and a long word specifying the initialization options for each data type.
- **Format 2 sound resource header.** For format 2 'snd ' resources, the sound resource header next includes a single word that the Sound Manager ignores. This word is known as the reference count field. Your application can use this field as it pleases.

Summary of the Sound Manager

Pascal Summary

Constants

CONST

```

{Gestalt sound attributes selector and response bits}
gestaltSoundAttr          = 'snd '; {sound attributes selector}
gestaltStereoCapability   = 0;     {built-in hw can play stereo sounds}
gestaltStereoMixing       = 1;     {built-in hw mixes stereo to mono}
gestaltSoundIOMgrPresent  = 3;     {sound input routines available}
gestaltBuiltInSoundInput  = 4;     {built-in input hw available}
gestaltHasSoundInputDevice = 5;    {sound input device available}
gestaltPlayAndRecord      = 6;     {built-in hw can play while recording}
gestalt16BitSoundIO       = 7;     {built-in hw can handle 16-bit data}
gestaltStereoInput        = 8;     {built-in hw can record stereo sounds}
gestaltLineLevelInput     = 9;     {built-in input hw needs line level}
gestaltSndPlayDoubleBuffer = 10;   {play from disk routines available}
gestaltMultiChannels      = 11;    {multiple channels of sound supported}
gestalt16BitAudioSupport  = 12;    {16-bit audio data supported}

{channel initialization parameters}
initChanLeft              = $0002; {left stereo channel}
initChanRight             = $0003; {right stereo channel}
waveInitChannel0         = $0004; {wave-table channel 0}
waveInitChannel1         = $0005; {wave-table channel 1}
waveInitChannel2         = $0006; {wave-table channel 2}
waveInitChannel3         = $0007; {wave-table channel 3}
initMono                  = $0080; {monophonic channel}
initStereo                = $00C0; {stereo channel}
initMACE3                 = $0300; {3:1 compression}
initMACE6                 = $0400; {6:1 compression}
initNoInterp              = $0004; {no linear interpolation}
initNoDrop                = $0008; {no drop-sample conversion}

```

Sound Manager

```

{masks for channel attributes}
initPanMask          = $0003;    {mask for right/left pan values}
initSRateMask        = $0030;    {mask for sample rate values}
initStereoMask       = $00C0;    {mask for mono/stereo values}
initCompMask         = $FF00;    {mask for compression IDs}

{sound data types}
squareWaveSynth      = 1;        {square-wave data}
waveTableSynth       = 3;        {wave-table data}
sampledSynth         = 5;        {sampled-sound data}

{sound command numbers}
nullCmd              = 0;        {do nothing}
quietCmd             = 3;        {stop a sound that is playing}
flushCmd             = 4;        {flush a sound channel}
reInitCmd            = 5;        {reinitialize a sound channel}
waitCmd              = 10;       {suspend processing in a channel}
pauseCmd             = 11;       {pause processing in a channel}
resumeCmd            = 12;       {resume processing in a channel}
callBackCmd          = 13;       {execute a callback procedure}
syncCmd              = 14;       {synchronize channels}
availableCmd         = 24;       {see if initialization options }
                        { are supported}
versionCmd           = 25;       {determine version}
totalLoadCmd         = 26;       {report total CPU load}
loadCmd              = 27;       {report CPU load for a new channel}
freqDurationCmd      = 40;       {play a note for a duration}
restCmd              = 41;       {rest a channel for a duration}
freqCmd              = 42;       {change the pitch of a sound}
ampCmd               = 43;       {change the amplitude of a sound}
timbreCmd            = 44;       {change the timbre of a sound}
getAmpCmd            = 45;       {get the amplitude of a sound}
volumeCmd            = 46;       {set volume}
getVolumeCmd         = 47;       {get volume}
waveTableCmd         = 60;       {install a wave table as a voice}
soundCmd             = 80;       {install a sampled sound as a voice}
bufferCmd            = 81;       {play a sampled sound}
rateCmd              = 82;       {set the pitch of a sampled sound}
getRateCmd           = 85;       {get the pitch of a sampled sound}

{sampled sound header encoding options}
stdSH                = $00;      {standard sound header}
extSH                = $FF;      {extended sound header}
cmpSH                = $FE;      {compressed sound header}

```

Sound Manager

```

{size of data structures}
stdQLength          = 128;          {default size of standard sound }
                                   { channel}

{sound resource formats}
firstSoundFormat    = $0001;      {format 1 'snd ' resource}
secondSoundFormat   = $0002;      {format 2 'snd ' resource}

{sound command mask}
dataOffsetFlag      = $8000;      {sound command data offset bit}

{system beep states}
sysBeepDisable      = $0000;      {system alert sound disabled}
sysBeepEnable       = $0001;      {system alert sound enabled}

{values for the unitType field in AudioSelection}
unitTypeSeconds     = $0000;      {seconds}
unitTypeNoSelection = $FFFF;      {no selection}

{double buffer status flags}
dbBufferReady       = $00000001; {double buffer is filled}
dbLastBuffer        = $00000004; {last double buffer to play}

{values for the compressionID field of CmpSoundHeader}
variableCompression = -2;          {variable-ratio compression}
fixedCompression    = -1;          {fixed-ratio compression}
notCompressed       = 0;           {noncompressed samples}
threeToOne          = 3;           {3:1 compressed samples}
sixToOne            = 4;           {6:1 compressed samples}

{values for the packetSize field of CmpSoundHeader}
sixToOnePacketSize  = 8;           {packet size in bits for 6:1}
threeToOnePacketSize = 16;        {packet size in bits for 3:1}

{compression names and types}
NoneName            = 'not compressed';
ACE2to1Name         = 'ACE 2-to-1';
ACE8to3Name         = 'ACE 8-to-3';
MACE3to1Name        = 'MACE 3-to-1';
MACE6to1Name        = 'MACE 6-to-1';
NoneType            = 'NONE';
ACE2Type            = 'ACE2';
ACE8Type            = 'ACE8';
MACE3Type           = 'MAC3';
MACE6Type           = 'MAC6'

```

Sound Manager

{IDs for AIFF and AIFF-C files}

```
AIFFID          = 'AIFF';    {AIFF file}
AIFCID          = 'AIFC';    {AIFF-C file}
```

{IDs for AIFF and AIFF-C file chunks}

```
FormID          = 'FORM';    {ID for Form Chunk}
FormatVersionID = 'FVER';    {ID for Format Version Chunk}
CommonID        = 'COMM';    {ID for Common Chunk}
SoundDataID     = 'SSND';    {ID for Sound Data Chunk}
MarkerID        = 'MARK';    {ID for Marker Chunk}
InstrumentID     = 'INST';    {ID for Instrument Chunk}
MIDIDataID      = 'MIDI';    {ID for MIDI Data Chunk}
AudioRecordingID = 'AESD';    {ID for Recording Chunk}
ApplicationSpecificID = 'APPL'; {ID for Application Chunk}
CommentID       = 'COMT';    {ID for Comment Chunk}
NameID          = 'NAME';    {ID for Name Chunk}
AuthorID        = 'AUTH';    {ID for Author Chunk}
CopyrightID     = '(c) ';    {ID for Copyright Chunk}
AnnotationID    = 'ANNO';    {ID for Annotation Chunk}
```

{version of AIFC format specification}

```
AIFCVersion1    = $A2805140; {date of version creation}
```

{MIDI note value for middle C}

```
kMiddleC        = 60;
```

{ratio between frequencies of MIDI note values}

```
twelfthRootTwo = 1.05946309434;
```

{standard sampling rates}

```
rate44khz       = $AC440000;  {44100.00000 in fixed-point}
rate22khz       = $56EE8BA3;  {22254.54545 in fixed-point}
rate22050hz     = $56220000;  {22050.00000 in fixed-point}
rate11khz       = $2B7745D1;  {11127.27273 in fixed-point}
rate11025hz     = $2B110000;  {11025.00000 in fixed-point}
```

{constant for synth parameter of SndNewChannel}

```
kUseOptionalOutputDevice = -1;
```

{volumes}

```
kFullVolume     = $0100;
kNoVolume       = 0;
```

Sound Manager

```

{development stages}
developStage      = $20;           {prealpha release}
alphaStage        = $40;           {alpha release}
betaStage         = $60;           {beta release}
finalStage        = $80;           {final release}

{sizes of data buffers}
stateBlockSize    = 64;            {size of state block buffer}
leftOverBlockSize = 32;            {size of leftover block buffer}

```

Data Types
Unsigned Fixed-Point Numbers

```

TYPE
  UnsignedFixed = LongInt;           {unsigned fixed-point number}

```

Times

```

TYPE
  Time = LongInt;                   {in half-milliseconds}

```

Sound Command Record

```

SndCommand =
PACKED RECORD
  cmd:           Integer;           {command number}
  param1:        Integer;           {first parameter}
  param2:        LongInt;           {second parameter}
END;

```

Audio Selection Record

```

AudioSelection =
PACKED RECORD
  unitType:      LongInt;           {type of time unit}
  selStart:      Fixed;             {starting point of selection}
  selEnd:        Fixed;             {ending point of selection}
END;
AudioSelectionPtr = ^AudioSelection;

```

Sound Manager

Sound Channel Status Record

```

SCStatus =
RECORD
    scStartTime:      Fixed;      {starting time for play from disk}
    scEndTime:       Fixed;      {ending time for play from disk}
    scCurrentTime:   Fixed;      {current time for play from disk}
    scChannelBusy:   Boolean;     {TRUE if channel is processing cmds}
    scChannelDisposed: Boolean;   {reserved}
    scChannelPaused: Boolean;     {TRUE if play from disk is paused}
    scUnused:        Boolean;     {unused}
    scChannelAttributes: LongInt; {attributes of this channel}
    scCPULoad:       LongInt;     {CPU load for this channel}
END;
SCStatusPtr = ^SCStatus;

```

Sound Manager Status Record

```

SMStatus =
PACKED RECORD
    smMaxCPULoad:    Integer;     {maximum load on all channels}
    smNumChannels:   Integer;     {number of allocated channels}
    smCurCPULoad:    Integer;     {current load on all channels}
END;
SMStatusPtr = ^SMStatus;

```

Sound Channel Record

```

SndChannel =
PACKED RECORD
    nextChan:        SndChannelPtr; {pointer to next channel}
    firstMod:        Ptr;           {used internally}
    callBack:        ProcPtr;      {pointer to callback procedure}
    userInfo:        LongInt;      {free for application's use}
    wait:            LongInt;      {used internally}
    cmdInProgress:   SndCommand;   {used internally}
    flags:           Integer;      {used internally}
    qLength:         Integer;      {used internally}
    qHead:           Integer;      {used internally}
    qTail:           Integer;      {used internally}
    queue:           ARRAY[0..stdQLength-1] OF SndCommand;
END;
SndChannelPtr = ^SndChannel;

```

Sound Header Record

```

SoundHeader =
PACKED RECORD
    samplePtr:      Ptr;           {if NIL, samples in sampleArea}
    length:         LongInt;       {number of samples in array}
    sampleRate:     Fixed;         {sample rate}
    loopStart:      LongInt;       {loop point beginning}
    loopEnd:        LongInt;       {loop point ending}
    encode:         Byte;          {sample's encoding option}
    baseFrequency: Byte;           {base frequency of sample}
    sampleArea:     PACKED ARRAY[0..0] OF Byte;
END;
SoundHeaderPtr = ^SoundHeader;

```

Extended Sound Header Record

```

ExtSoundHeader =
PACKED RECORD
    samplePtr:      Ptr;           {if NIL, samples in sampleArea}
    numChannels:    LongInt;       {number of channels in sample}
    sampleRate:     Fixed;         {rate of original sample}
    loopStart:      LongInt;       {loop point beginning}
    loopEnd:        LongInt;       {loop point ending}
    encode:         Byte;          {sample's encoding option}
    baseFrequency: Byte;           {base frequency of sample}
    numFrames:      LongInt;       {total number of frames}
    AIFFSampleRate: Extended80;    {rate of original sample}
    markerChunk:    Ptr;           {reserved}
    instrumentChunks: Ptr;         {pointer to instrument info}
    AESRecording:   Ptr;           {pointer to audio info}
    sampleSize:     Integer;       {number of bits per sample}
    futureUse1:     Integer;       {reserved}
    futureUse2:     LongInt;       {reserved}
    futureUse3:     LongInt;       {reserved}
    futureUse4:     LongInt;       {reserved}
    sampleArea:     PACKED ARRAY[0..0] OF Byte;
END;
ExtSoundHeaderPtr = ^ExtSoundHeader;

```

Compressed Sound Header Record

```

CmpSoundHeader =
PACKED RECORD
    samplePtr:      Ptr;           {if NIL, samples in sampleArea}
    numChannels:    LongInt;       {number of channels in sample}
    sampleRate:     Fixed;         {rate of original sample}
    loopStart:      LongInt;       {loop point beginning}
    loopEnd:        LongInt;       {loop point ending}
    encode:         Byte;          {sample's encoding option}
    baseFrequency: Byte;          {base freq. of original sample}
    numFrames:      LongInt;       {length of sample in frames}
    AIFFSampleRate: Extended80;   {rate of original sample}
    markerChunk:    Ptr;           {reserved}
    format:         OSType;        {data format type}
    futureUse2:     LongInt;       {reserved}
    stateVars:      StateBlockPtr; {pointer to StateBlock}
    leftOverSamples: LeftOverBlockPtr;
                                {pointer to LeftOverBlock}
    compressionID: Integer;        {ID of compression algorithm}
    packetSize:     Integer;        {number of bits per packet}
    snthID:         Integer;        {unused}
    sampleSize:     Integer;        {bits in each sample point}
    sampleArea:     PACKED ARRAY[0..0] OF Byte;
END;
CmpSoundHeaderPtr = ^CmpSoundHeader;

```

Sound Double Buffer Header Record

```

SndDoubleBufferHeader =
PACKED RECORD
    dbhNumChannels: Integer;       {number of sound channels}
    dbhSampleSize:  Integer;       {sample size, if noncompressed}
    dbhCompressionID: Integer;     {ID of compression algorithm}
    dbhPacketSize:  Integer;       {number of bits per packet}
    dbhSampleRate:  Fixed;         {sample rate}
    dbhBufferPtr:   ARRAY[0..1] OF SndDoubleBufferPtr;
                                {pointers to SndDoubleBuffer}
    dbhDoubleBack:  ProcPtr;       {pointer to doubleback procedure}
END;
SndDoubleBufferHeaderPtr = ^SndDoubleBufferHeader;

```


Sound Manager

```

SndDoubleBufferHeader2 =
PACKED RECORD
    dbhNumChannels:   Integer;           {number of sound channels}
    dbhSampleSize:    Integer;           {sample size, if noncompressed}
    dbhCompressionID: Integer;           {ID of compression algorithm}
    dbhPacketSize:    Integer;           {number of bits per packet}
    dbhSampleRate:    Fixed;             {sample rate}
    dbhBufferPtr:     ARRAY[0..1] OF SndDoubleBufferPtr;
                                           {pointers to SndDoubleBuffer}
    dbhDoubleBack:    ProcPtr;           {pointer to doubleback procedure}
    dbhFormat:        OSType;            {signature of codec}
END;
SndDoubleBufferHeaderPtr2 = ^SndDoubleBufferHeader2;

```

Sound Double Buffer Record

```

SndDoubleBuffer =
PACKED RECORD
    dbNumFrames:      LongInt;           {number of frames in buffer}
    dbFlags:          LongInt;           {buffer status flags}
    dbUserInfo:       ARRAY[0..1] OF LongInt;
                                           {for application's use}
    dbSoundData:      PACKED ARRAY[0..0] OF Byte;
                                           {array of data}
END;
SndDoubleBufferPtr = ^SndDoubleBuffer;

```

Chunk Header

```

ID = LongInt;           {chunk ID type}

ChunkHeader =
RECORD
    ckID:              ID;              {chunk type ID}
    ckSize:            LongInt;         {number of bytes of data}
END;

```

Sound Manager

Form Chunk

```

ContainerChunk =
RECORD
    ckID:          ID;          {'FORM'}
    ckSize:        LongInt;     {number of bytes of data}
    formType:      ID;          {type of file}
END;

```

Format Version Chunk

```

FormatVersionChunk =
RECORD
    ckID:          ID;          {'FVER'}
    ckSize:        LongInt;     {4 bytes}
    timestamp:     LongInt;     {date of format version}
END;

```

Common Chunk

```

CommonChunk =
RECORD
    ckID:          ID;          {'COMM'}
    ckSize:        LongInt;     {18 bytes}
    numChannels:   Integer;     {number of channels}
    numSampleFrames: LongInt;   {number of sample frames}
    sampleSize:    Integer;     {number of bits per sample}
    sampleRate:    Extended;    {number of frames per second}
END;

```

Extended Common Chunk

```

ExtCommonChunk =
RECORD
    ckID:          ID;          {'COMM'}
    ckSize:        LongInt;     {22 bytes + compression name}
    numChannels:   Integer;     {number of channels}
    numSampleFrames: LongInt;   {number of sample frames}
    sampleSize:    Integer;     {number of bits per sample}
    sampleRate:    Extended;    {number of frames per second}
    compressionType: ID;        {compression type ID}
    compressionName: PACKED ARRAY[0..0] OF Byte;
                                                {compression type name}
END;

```

Sound Data Chunk

```

SoundDataChunk =
RECORD
  ckID:      ID;      {'SSND'}
  ckSize:    LongInt; {size of chunk data}
  offset:    LongInt; {offset to sound data}
  blockSize: LongInt; {size of alignment blocks}
END;

```

Version Record

```

NumVersion =
PACKED RECORD
CASE INTEGER OF
  0:
    (majorRev:      SignedByte;    {major revision level in BCD}
     minorAndBugRev: SignedByte;    {minor revision level}
     stage:          SignedByte;    {development stage}
     nonRelRev:      SignedByte);   {nonreleased revision level}
  1:
    (version:       LongInt);       {all 4 fields together}
END;

```

Leftover Block

```

LeftOverBlock =
RECORD
  count:      LongInt;
  sampleArea: PACKED ARRAY[0..leftOverBlockSize - 1] OF Byte;
END;
LeftOverBlockPtr = ^LeftOverBlock;

```

State Block

```

StateBlock =
RECORD
  stateVar:    ARRAY[0..stateBlockSize - 1] OF Integer;
END;
StateBlockPtr = ^StateBlock;

```

Sound Manager Routines

Playing Sound Resources

```
PROCEDURE SysBeep          (duration: Integer);
FUNCTION SndPlay           (chan: SndChannelPtr; sndHdl: Handle;
                           async: Boolean): OSErr;
```

Playing From Disk

```
FUNCTION SndStartFilePlay (chan: SndChannelPtr; fRefNum: Integer;
                           resNum: Integer; bufferSize: LongInt;
                           theBuffer: Ptr;
                           theSelection: AudioSelectionPtr;
                           theCompletion: ProcPtr; async: Boolean): OSErr;
FUNCTION SndPauseFilePlay (chan: SndChannelPtr): OSErr;
FUNCTION SndStopFilePlay  (chan: SndChannelPtr; quietNow: Boolean): OSErr;
```

Allocating and Releasing Sound Channels

```
FUNCTION SndNewChannel     (VAR chan: SndChannelPtr; synth: Integer;
                           init: LongInt; userRoutine: ProcPtr): OSErr;
FUNCTION SndDisposeChannel (chan: SndChannelPtr; quietNow: Boolean): OSErr;
```

Sending Commands to a Sound Channel

```
FUNCTION SndDoCommand     (chan: SndChannelPtr; cmd: SndCommand;
                           noWait: Boolean): OSErr;
FUNCTION SndDoImmediate   (chan: SndChannelPtr; cmd: SndCommand): OSErr;
```

Obtaining Information

```
FUNCTION SndSoundManagerVersion
                           : NumVersion;
FUNCTION MACEVersion       : NumVersion;
FUNCTION SndControl        (id: Integer; VAR cmd: SndCommand): OSErr;
FUNCTION SndChannelStatus  (chan: SndChannelPtr; theLength: Integer;
                           theStatus: SCStatusPtr): OSErr;
FUNCTION SndManagerStatus  (theLength: Integer; theStatus: SMStatusPtr):
                           OSErr;
PROCEDURE SndGetSysBeepState
                           (VAR sysBeepState: Integer);
FUNCTION SndSetSysBeepState
                           (sysBeepState: Integer): OSErr;
```

Sound Manager

```
FUNCTION GetSoundHeaderOffset
    (sndHdl: Handle; VAR offset: LongInt): OSErr;
```

Controlling Volume Levels

```
FUNCTION GetSysBeepVolume    (VAR level: LongInt): OSErr;
FUNCTION SetSysBeepVolume    (level: LongInt): OSErr;
FUNCTION GetDefaultOutputVolume
    (VAR level: LongInt): OSErr;
FUNCTION SetDefaultOutputVolume
    (level: LongInt): OSErr;
```

Compressing and Expanding Audio Data

```
PROCEDURE Comp3to1          (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
    inState: Ptr; outState: Ptr;
    numChannels: LongInt; whichChannel: LongInt);
PROCEDURE Comp6to1          (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
    inState: Ptr; outState: Ptr;
    numChannels: LongInt; whichChannel: LongInt);
PROCEDURE Explto3           (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
    inState: Ptr; outState: Ptr;
    numChannels: LongInt; whichChannel: LongInt);
PROCEDURE Explto6           (inBuffer: Ptr; outBuffer: Ptr; cnt: LongInt;
    inState: Ptr; outState: Ptr;
    numChannels: LongInt; whichChannel: LongInt);
```

Managing Double Buffers

```
FUNCTION SndPlayDoubleBuffer
    (chan: SndChannelPtr;
    theParams: SndDoubleBufferHeaderPtr): OSErr;
```

Performing Unsigned Fixed-Point Arithmetic

```
FUNCTION UnsignedFixMulDiv (value: UnsignedFixed;
    multiplier: UnsignedFixed;
    divisor: UnsignedFixed): UnsignedFixed;
```

Linking Modifiers to Sound Channels

```
FUNCTION SndAddModifier    (chan: SndChannelPtr; modifier: ProcPtr;
    id: Integer; init: LongInt): OSErr;
```

Application-Defined Routines

```
PROCEDURE MyFilePlayCompletionRoutine
    (chan: SndChannelPtr);

PROCEDURE MyCallback
    (chan: SndChannelPtr; cmd: SndCommand);

PROCEDURE MyDoubleBackProc
    (chan: SndChannelPtr;
     doubleBufferPtr: SndDoubleBufferPtr);
```

C Summary

Constants

```
/*Gestalt sound attributes selector and response bits*/
#define gestaltSoundAttr    'snd ' /*sound attributes selector*/

enum {
    gestaltStereoCapability    = 0, /*built-in hw can play stereo sounds*/
    gestaltStereoMixing        = 1, /*built-in hw mixes stereo to mono*/
    gestaltSoundIOMgrPresent   = 3, /*sound input routines available*/
    gestaltBuiltInSoundInput   = 4, /*built-in input hw available*/
    gestaltHasSoundInputDevice = 5, /*sound input device available*/
    gestaltPlayAndRecord       = 6, /*built-in hw can play while recording*/
    gestalt16BitSoundIO        = 7, /*built-in hw can handle 16-bit data*/
    gestaltStereoInput         = 8, /*built-in hw can record stereo sounds*/
    gestaltLineLevelInput      = 9, /*built-in input hw needs line level*/
    gestaltSndPlayDoubleBuffer = 10, /*play from disk routines available*/
    gestaltMultiChannels       = 11, /*multiple channels of sound supported*/
    gestalt16BitAudioSupport   = 12 /*16-bit audio data supported*/
};

/*channel initialization parameters*/
enum {
    initChanLeft                = 0x0002, /*left stereo channel*/
    initChanRight               = 0x0003, /*right stereo channel*/
    initMono                    = 0x0080, /*monophonic channel*/
    initStereo                  = 0x00C0, /*stereo channel*/
    initMACE3                   = 0x0300, /*3:1 compression*/
    initMACE6                   = 0x0400, /*6:1 compression*/
    initNoInterp                = 0x0004, /*no linear interpolation*/
    initNoDrop                  = 0x0008 /*no drop-sample conversion*/
};
```

Sound Manager

```

/*wave channel initialization parameters*/
enum {
    waveInitChannel0      = 0x04,      /*wave-table channel 0*/
    waveInitChannel1      = 0x05,      /*wave-table channel 1*/
    waveInitChannel2      = 0x06,      /*wave-table channel 2*/
    waveInitChannel3      = 0x07,      /*wave-table channel 3*/
    waveInitChannelMask   = 0x07      /*mask for wave-table parameters*/
};

/*masks for channel attributes*/
enum {
    initPanMask           = 0x0003,    /*mask for left/right pan values*/
    initSRateMask         = 0x0030,    /*mask for sample rate values*/
    initStereoMask        = 0x00C0,    /*mask for mono/stereo values*/
    initCompMask          = 0xFF00     /*mask for compression IDs*/
};

/*sound data types*/
enum {
    squareWaveSynth       = 1,         /*square-wave data*/
    waveTableSynth        = 3,         /*wave-table data*/
    sampledSynth          = 5         /*sampled-sound data*/
};

/*sound command numbers*/
enum {
    nullCmd               = 0,         /*do nothing*/
    quietCmd              = 3,         /*stop a sound that is playing*/
    flushCmd              = 4,         /*flush a sound channel*/
    reInitCmd             = 5,         /*reinitialize a sound channel*/
    waitCmd               = 10,        /*suspend processing in a channel*/
    pauseCmd              = 11,        /*pause processing in a channel*/
    resumeCmd             = 12,        /*resume processing in a channel*/
    callBackCmd           = 13,        /*execute a callback procedure*/
    syncCmd               = 14,        /*synchronize channels*/
    availableCmd          = 24,        /*see if initialization options */
                                   /* are supported*/
    versionCmd            = 25,        /*determine version*/
    totalLoadCmd          = 26,        /*report total CPU load*/
    loadCmd               = 27,        /*report CPU load for a new channel*/
    freqDurationCmd       = 40,        /*play a note for a duration*/
    restCmd               = 41,        /*rest a channel for a duration*/
    freqCmd               = 42,        /*change the pitch of a sound*/
    ampCmd                = 43,        /*change the amplitude of a sound*/
};

```

Sound Manager

```

    timbreCmd           = 44,          /*change the timbre of a sound*/
    getAmpCmd           = 45,          /*get the amplitude of a sound*/
    volumeCmd          = 46,          /*set volume*/
    getVolumeCmd        = 47,          /*get volume*/
    waveTableCmd        = 60,          /*install a wave table as a voice*/
    soundCmd            = 80,          /*install a sampled sound as a voice*/
    bufferCmd           = 81,          /*play a sampled sound*/
    rateCmd             = 82,          /*set the pitch of a sampled sound*/
    getRateCmd          = 85          /*get the pitch of a sampled sound*/
};

/*sampled sound header encoding options*/
enum {
    stdSH               = 0x00,       /*standard sound header*/
    extSH               = 0xFF,       /*extended sound header*/
    cmpSH               = 0xFE        /*compressed sound header*/
};

/*size of data structures*/
enum {
    stdQLength          = 128         /*default size of sound channel*/
};

/*sound resource formats*/
enum {
    firstSoundFormat    = 0x0001,    /*format 1 'snd ' resource*/
    secondSoundFormat   = 0x0002     /*format 2 'snd ' resource*/
};

/*sound command mask*/
enum {
    dataOffsetFlag      = 0x8000     /*sound command data offset bit*/
};

/*system beep states*/
enum {
    sysBeepDisable      = 0x0000,    /*system alert sound disabled*/
    sysBeepEnable       = 0x0001     /*system alert sound enabled*/
};

/*values for the unitType field in AudioSelection*/
enum {
    unitTypeSeconds     = 0x0000,    /*seconds*/
    unitTypeNoSelection = 0xFFFF     /*no selection*/
};

```


Sound Manager

```

/*double buffer status flags*/
enum {
    dbBufferReady          = 0x00000001, /*double buffer is filled*/
    dbLastBuffer          = 0x00000004 /*last double buffer to play*/
};

/*values for the compressionID field of CmpSoundHeader*/
enum {
    variableCompression    = -2,        /*variable-ratio compression*/
    fixedCompression       = -1,        /*fixed-ratio compression*/
    notCompressed          = 0,        /*noncompressed samples*/
    threeToOne             = 3,        /*3:1 compressed samples*/
    sixToOne               = 4,        /*6:1 compressed samples*/
};

/*values for the packetSize field of CmpSoundHeader*/
enum {
    sixToOnePacketSize    = 8,        /*packet size in bits for 6:1*/
    threeToOnePacketSize  = 16       /*packet size in bits for 3:1*/
};

/*compression names and types*/
#define NoneName          "\pnot compressed"
#define ACE2to1Name      "\pACE 2-to-1"
#define ACE8to3Name      "\pACE 8-to-3"
#define MACE3to1Name     "\pMACE 3-to-1"
#define MACE6to1Name     "\pMACE 6-to-1"
#define NoneType         'NONE'
#define ACE2Type         'ACE2'
#define ACE8Type         'ACE8'
#define MACE3Type        'MAC3'
#define MACE6Type        'MAC6'

/*IDs for AIFF and AIFF-C files*/
#define AIFFID           'AIFF' /*AIFF file*/
#define AIFCID           'AIFC' /*AIFF-C file*/

/*IDs for AIFF and AIFF-C file chunks*/
#define FORMID           'FORM' /*ID for Form Chunk*/
#define FormatVersionID  'FVER' /*ID for Format Version Chunk*/
#define CommonID         'COMM' /*ID for Common Chunk*/
#define SoundDataID     'SSND' /*ID for Sound Data Chunk*/
#define MarkerID         'MARK' /*ID for Marker Chunk*/
#define InstrumentID     'INST' /*ID for Instrument Chunk*/

```

Sound Manager

```

#define MIDIDataID          'MIDI'    /*ID for MIDI Data Chunk*/
#define AudioRecordingID    'AESD'    /*ID for Recording Chunk*/
#define ApplicationSpecificID 'APPL'  /*ID for Application Chunk*/
#define CommentID          'COMT'    /*ID for Comment Chunk*/
#define NameID             'NAME'    /*ID for Name Chunk*/
#define AuthorID           'AUTH'    /*ID for Author Chunk*/
#define CopyrightID        '(c) '    /*ID for Copyright Chunk*/
#define AnnotationID       'ANNO'    /*ID for Annotation Chunk*/

/*version of AIFC format specification*/
#define AIFCVersion1        0xA2805140
                                /*date of version creation*/

/*MIDI note value for middle C*/
enum {
    kMiddleC                = 60
};

/*ratio between frequencies of MIDI note values*/
#define twelfthRootTwo      1.05946309434

/*standard sampling rates*/
#define rate44khz           0xAC440000 /*44100.00000 in fixed-point*/
#define rate22khz           0x56EE8BA3 /*22254.54545 in fixed-point*/
#define rate22050hz         0x56220000 /*22050.00000 in fixed-point*/
#define rate11khz           0x2B7745D1 /*11127.27273 in fixed-point*/
#define rate11025hz         0x2B110000 /*11025.00000 in fixed-point*/

/*constant for synth parameter of SndNewChannel*/
enum {
    kUseOptionalOutputDevice = -1
};

/*volumes*/
enum {
    kFullVolume              = 0x0100,
    kNoVolume                 = 0
};

/*development stages*/
enum {
    developStage             = 0x20,    /*prealpha release*/
    alphaStage                = 0x40,    /*alpha release*/
};

```

Sound Manager

```

    betaStage          = 0x60,          /*beta release*/
    finalStage         = 0x80          /*final release*/
};

/*sizes of data buffers*/
enum {
    stateBlockSize     = 64,          /*size of state block buffer*/
    leftOverBlockSize  = 32          /*size of leftover block buffer*/
};

```

Data Types
Unsigned Fixed-Point Numbers

```
typedef unsigned long UnsignedFixed;    /*unsigned fixed-point number*/
```

Times

```
typedef long Time;                    /*in half-milliseconds*/
```

Sound Command Record

```

struct SndCommand {
    unsigned short    cmd;            /*command number*/
    short             param1;        /*first parameter*/
    long              param2;        /*second parameter*/
};
typedef struct SndCommand SndCommand;

```

Audio Selection Record

```

struct AudioSelection {
    long              unitType;      /*type of time unit*/
    Fixed             selStart;     /*starting point of selection*/
    Fixed             selEnd;       /*ending point of selection*/
};
typedef struct AudioSelection AudioSelection;
typedef AudioSelection *AudioSelectionPtr;

```

Sound Manager

Sound Channel Status Record

```

struct SCStatus {
    Fixed          scStartTime; /*starting time for play from disk*/
    Fixed          scEndTime;   /*ending time for play from disk*/
    Fixed          scCurrentTime; /*current time for play from disk*/
    Boolean        scChannelBusy; /*TRUE if channel is processing cmds*/
    Boolean        scChannelDisposed;
                                /*reserved*/
    Boolean        scChannelPaused;
                                /*TRUE if play from disk is paused*/
    Boolean        scUnused;    /*unused*/
    unsigned long  scChannelAttributes;
                                /*attributes of this channel*/
    long          scCPUload;    /*CPU load for this channel*/
};
typedef struct SCStatus SCStatus;
typedef SCStatus *SCStatusPtr;

```

Sound Manager Status Record

```

struct SMStatus {
    short          smMaxCPUload; /*maximum load on all channels*/
    short          smNumChannels; /*number of allocated channels*/
    short          smCurCPUload; /*current load on all channels*/
};
typedef struct SMStatus SMStatus;
typedef SMStatus *SMStatusPtr;

```

Sound Channel Record

```

struct SndChannel {
    struct SndChannel *nextChan; /*pointer to next channel*/
    Ptr              firstMod;   /*used internally*/
    SndCallbackProcPtr callBack; /*pointer to callback procedure*/
    long             userInfo;   /*free for application's use*/
    long             wait;       /*used internally*/
    SndCommand       cmdInProgress; /*used internally*/
    short            flags;      /*used internally*/
    short            qLength;    /*used internally*/
    short            qHead;     /*used internally*/
    short            qTail;     /*used internally*/
    SndCommand       queue[stdQLength];
};

```

Sound Manager

```
};
typedef struct SndChannel SndChannel;
typedef SndChannel *SndChannelPtr;
```

Sound Header Record

```
struct SoundHeader {
    Ptr          samplePtr;      /*if NIL, samples in sampleArea*/
    unsigned long length;       /*number of samples in array*/
    Fixed        sampleRate;    /*sample rate for this sound*/
    unsigned long loopStart;    /*loop point beginning*/
    unsigned long loopEnd;      /*loop point ending*/
    unsigned char encode;       /*sample's encoding option*/
    unsigned char baseFrequency; /*base frequency of sample*/
    unsigned char sampleArea[1];
};
typedef struct SoundHeader SoundHeader;
typedef SoundHeader *SoundHeaderPtr;
```

Extended Sound Header Record

```
struct ExtSoundHeader {
    Ptr          samplePtr;      /*if NIL, samples in sampleArea*/
    unsigned long numChannels;   /*number of channels in sample*/
    Fixed        sampleRate;    /*rate of original sample*/
    unsigned long loopStart;    /*loop point beginning*/
    unsigned long loopEnd;      /*loop point ending*/
    unsigned char encode;       /*sample's encoding option*/
    unsigned char baseFrequency; /*base frequency of sample*/
    unsigned long numFrames;    /*total number of frames*/
    extended80   AIFFSampleRate; /*rate of original sample*/
    Ptr          markerChunk;    /*reserved*/
    Ptr          instrumentChunks;
                                /*pointer to instrument info*/
    Ptr          AESRecording;    /*pointer to audio info*/
    unsigned short sampleSize;   /*number of bits per sample*/
    unsigned short futureUse1;   /*reserved*/
    unsigned long futureUse2;    /*reserved*/
    unsigned long futureUse3;    /*reserved*/
    unsigned long futureUse4;    /*reserved*/
    unsigned char sampleArea[1];
};
typedef struct ExtSoundHeader ExtSoundHeader;
typedef ExtSoundHeader *ExtSoundHeaderPtr;
```

Compressed Sound Header Record

```

struct CmpSoundHeader {
    Ptr          samplePtr;      /*if NIL, samples in sampleArea*/
    unsigned long numChannels;   /*number of channels in sample*/
    Fixed        sampleRate;    /*rate of original sample*/
    unsigned long loopStart;    /*loop point beginning*/
    unsigned long loopEnd;     /*loop point ending*/
    unsigned char encode;      /*sample's encoding option*/
    unsigned char baseFrequency; /*base frequency of original sample*/
    unsigned long numFrames;    /*length of sample in frames*/
    extended80   AIFFSampleRate; /*rate of original sample*/
    Ptr          markerChunk;   /*reserved*/
    OSType       format;        /*data format type*/
    unsigned long futureUse2;   /*reserved*/
    StateBlockPtr stateVars;    /*pointer to StateBlock*/
    LeftOverBlockPtr leftOverSamples;
                                /*pointer to LeftOverBlock*/
    unsigned short compressionID; /*ID of compression algorithm*/
    unsigned short packetSize;   /*number of bits per packet*/
    unsigned short snthID;       /*unused*/
    unsigned short sampleSize;   /*bits in each sample point*/
    unsigned char  sampleArea[1];
};
typedef struct CmpSoundHeader CmpSoundHeader;
typedef CmpSoundHeader *CmpSoundHeaderPtr;

```

Sound Double Buffer Header Record

```

struct SndDoubleBufferHeader {
    short        dbhNumChannels; /*number of sound channels*/
    short        dbhSampleSize; /*sample size, if noncompressed*/
    short        dbhCompressionID;
                                /*ID of compression algorithm*/
    short        dbhPacketSize; /*number of bits per packet*/
    Fixed        dbhSampleRate; /*sample rate*/
    SndDoubleBufferPtr dbhBufferPtr[2];
                                /*pointers to SndDoubleBuffer*/
    SndDoubleBackProcPtr dbhDoubleBack; /*pointer to doubleback procedure*/
};
typedef struct SndDoubleBufferHeader SndDoubleBufferHeader;
typedef SndDoubleBufferHeader *SndDoubleBufferHeaderPtr;

```

Sound Manager

```

struct SndDoubleBufferHeader2 {
    short          dbhNumChannels; /*number of sound channels*/
    short          dbhSampleSize; /*sample size, if noncompressed*/
    short          dbhCompressionID;
                                /*ID of compression algorithm*/
    short          dbhPacketSize; /*number of bits per packet*/
    Fixed          dbhSampleRate; /*sample rate*/
    SndDoubleBufferPtr dbhBufferPtr[2];
                                /*pointers to SndDoubleBuffer*/
    SndDoubleBackProcPtr dbhDoubleBack; /*pointer to doubleback procedure*/
    OSType         dbhFormat;        /*signature of codec*/
};
typedef struct SndDoubleBufferHeader2 SndDoubleBufferHeader2;
typedef SndDoubleBufferHeader2 *SndDoubleBufferHeaderPtr2;

```

Sound Double Buffer Record

```

struct SndDoubleBuffer {
    long          dbNumFrames; /*number of frames in buffer*/
    long          dbFlags;     /*buffer status flags*/
    long          dbUserInfo[2]; /*for application's use*/
    char          dbSoundData[1]; /*array of data*/
};
typedef struct SndDoubleBuffer SndDoubleBuffer;
typedef SndDoubleBuffer *SndDoubleBufferPtr;

```

Chunk Headers

```

typedef unsigned long ID; /*chunk ID type*/

struct ChunkHeader {
    ID          ckID; /*chunk type ID*/
    long        ckSize; /*number of bytes of data*/
};
typedef struct ChunkHeader ChunkHeader;

```

Form Chunk

```

struct ContainerChunk {
    ID          ckID; /*'FORM'*/
    long        ckSize; /*number of bytes of data*/
    ID          formType; /*type of file*/
};
typedef struct ContainerChunk ContainerChunk;

```

Sound Manager

Format Version Chunk

```

struct FormatVersionChunk {
    ID                ckID;           /*'FVER'*/
    long              ckSize;         /*4 bytes*/
    unsigned long     timestamp;      /*date of format version*/
};
typedef struct FormatVersionChunk FormatVersionChunk;

```

Common Chunk

```

struct CommonChunk {
    ID                ckID;           /*'COMM'*/
    long              ckSize;         /*18 bytes*/
    short             numChannels;     /*number of channels*/
    unsigned long     numSampleFrames;
                                   /*number of sample frames*/
    short             sampleSize;      /*number of bits per sample*/
    extended80        sampleRate;     /*number of frames per second*/
};
typedef struct CommonChunk CommonChunk;

```

Extended Common Chunk

```

struct ExtCommonChunk {
    ID                ckID;           /*'COMM'*/
    long              ckSize;         /*22 bytes + compression name*/
    short             numChannels;     /*number of channels*/
    unsigned long     numSampleFrames;
                                   /*number of sample frames*/
    short             sampleSize;      /*number of bits per sample*/
    extended80        sampleRate;     /*number of frames per second*/
    ID                compressionType;
                                   /*compression type ID*/
    char              compressionName[1];
                                   /*compression type name*/
};
typedef struct ExtCommonChunk ExtCommonChunk;

```


Sound Data Chunk

```

struct SoundDataChunk {
    ID                ckID;           /*'SSND'*/
    long              ckSize;         /*size of chunk data*/
    unsigned long     offset;         /*offset to sound data*/
    unsigned long     blockSize;      /*size of alignment blocks*/
};
typedef struct SoundDataChunk SoundDataChunk;

```

Version Record

```

struct NumVersion {
    unsigned char     majorRev;       /*major revision level in BCD*/
    unsigned char     minorAndBugRev; /*minor revision level*/
    unsigned char     stage;          /*development stage*/
    unsigned char     nonRelRev;      /*nonreleased version revision level*/
};
typedef struct NumVersion NumVersion;

```

Leftover Block

```

struct LeftOverBlock {
    unsigned long     count;
    char              sampleArea[leftOverBlockSize];
};
typedef struct LeftOverBlock LeftOverBlock;
typedef LeftOverBlock *LeftOverBlockPtr;

```

State Block

```

struct StateBlock {
    short             stateVar[stateBlockSize];
};
typedef struct StateBlock StateBlock;
typedef StateBlock *StateBlockPtr;

```

Procedure Types

```

typedef pascal void (*FilePlayCompletionProcPtr)
                    (SndChannelPtr chan);
typedef pascal void (*SndCallBackProcPtr)
                    (SndChannelPtr chan, SndCommand *cmd);

```

Sound Manager

```
typedef pascal void (*SndDoubleBackProcPtr)
                    (SndChannelPtr chan,
                     SndDoubleBufferPtr doubleBufferPtr);
```

Sound Manager Routines

Playing Sound Resources

```
pascal void SysBeep      (short duration);
pascal OSErr SndPlay    (SndChannelPtr chan, Handle sndHdl,
                        Boolean async);
```

Playing From Disk

```
pascal OSErr SndStartFilePlay
                    (SndChannelPtr chan, short fRefNum,
                     short resNum, long bufferSize, void *theBuffer,
                     AudioSelectionPtr theSelection,
                     FilePlayCompletionProcPtr theCompletion,
                     Boolean async);
pascal OSErr SndPauseFilePlay
                    (SndChannelPtr chan);
pascal OSErr SndStopFilePlay
                    (SndChannelPtr chan, Boolean quietNow);
```

Allocating and Releasing Sound Channels

```
pascal OSErr SndNewChannel (SndChannelPtr *chan, short synth, long init,
                           SndCallBackProcPtr userRoutine);
pascal OSErr SndDisposeChannel
                    (SndChannelPtr chan, Boolean quietNow);
```

Sending Commands to a Sound Channel

```
pascal OSErr SndDoCommand (SndChannelPtr chan, const SndCommand *cmd,
                           Boolean noWait);
pascal OSErr SndDoImmediate
                    (SndChannelPtr chan, const SndCommand *cmd);
```

Obtaining Information

```
pascal NumVersion SndSoundManagerVersion
                    (void);
pascal NumVersion MACEVersion
                    (void);
```

Sound Manager

```

pascal OSErr SndControl      (short id, SndCommand *cmd);
pascal OSErr SndChannelStatus
                            (SndChannelPtr chan, short theLength,
                             SCStatusPtr theStatus);
pascal OSErr SndManagerStatus
                            (short theLength, SMStatusPtr theStatus);
pascal void SndGetSysBeepState
                            (short *sysBeepState);
pascal OSErr SndSetSysBeepState
                            (short sysBeepState);
pascal OSErr GetSoundHeaderOffset
                            (Handle sndHandle, long *offset);

```

Controlling Volume Levels

```

pascal OSErr GetSysBeepVolume
                            (long *level);
pascal OSErr SetSysBeepVolume
                            (long level);
pascal OSErr GetDefaultOutputVolume
                            (long *level);
pascal OSErr SetDefaultOutputVolume
                            (long level);

```

Compressing and Expanding Audio Data

```

pascal void Comp3to1      (const void *inBuffer, void *outBuffer,
                           unsigned long cnt, const void *inState,
                           void *outState, unsigned long numChannels,
                           unsigned long whichChannel);
pascal void Comp6to1      (const void *inBuffer, void *outBuffer,
                           unsigned long cnt, const void *inState,
                           void *outState, unsigned long numChannels,
                           unsigned long whichChannel);
pascal void Explt3to3     (const void *inBuffer, void *outBuffer,
                           unsigned long cnt, const void *inState,
                           void *outState, unsigned long numChannels,
                           unsigned long whichChannel);
pascal void Explt6to6     (const void *inBuffer, void *outBuffer,
                           unsigned long cnt, const void *inState,
                           void *outState, unsigned long numChannels,
                           unsigned long whichChannel);

```

Managing Double Buffers

```
pascal OSErr SndPlayDoubleBuffer
                (SndChannelPtr chan,
                 SndDoubleBufferHeaderPtr theParams);
```

Performing Unsigned Fixed-Point Arithmetic

```
pascal UnsignedFixed UnsignedFixMulDiv
                (UnsignedFixed value, UnsignedFixed multiplier,
                 UnsignedFixed divisor);
```

Linking Modifiers to Sound Channels

```
pascal OSErr SndAddModifier
                (SndChannelPtr chan, Ptr modifier, short id,
                 long init);
```

Application-Defined Routines

```
pascal void MyFilePlayCompletionRoutine
                (SndChannelPtr chan);
pascal void MyCallback    (SndChannelPtr chan, SndCommand *cmd);
pascal void MyDoubleBackProc
                (SndChannelPtr chan,
                 SndDoubleBufferPtr doubleBufferPtr);
```

Assembly-Language Summary

Data Structures

SndCommand Data Structure

0	cmd	word	command number
2	param1	word	first parameter
4	param2	long	second parameter

AudioSelection Data Structure

0	unitType	long	type of time unit
4	selStart	4 bytes	starting point of selection (Fixed)
8	selEnd	4 bytes	ending point of selection (Fixed)

SCStatus Data Structure

0	scStartTime	4 bytes	starting time for play from disk (Fixed)
4	scEndTime	4 bytes	ending time for play from disk (Fixed)
8	scCurrentTime	4 bytes	current time for play from disk (Fixed)
12	scChannelBusy	byte	channel playing sampled sound flag
13	scChannelDisposed	byte	reserved
14	scChannelPaused	byte	play from disk is paused flag
15	scUnused	byte	unused
16	scChannelAttributes	long	attributes of channel
20	scCPUload	long	CPU load for channel

SMStatus Data Structure

0	smMaxCPUload	word	maximum load on all channels
2	smNumChannels	word	number of allocated channels
4	smCurCPUload	word	current load on all channels

SndChannel Data Structure

0	nextChan	long	pointer to next channel
4	firstMod	long	used internally
8	callBack	long	pointer to callback procedure
12	userInfo	long	free for application's use
16	wait	long	used internally
20	cmdInProgress	8 bytes	used internally
28	flags	word	used internally
30	qLength	word	used internally
32	qHead	word	used internally
34	qTail	word	used internally
36	queue	variable	queue of sound commands

SoundHeader Data Structure

0	samplePtr	long	pointer to samples (or NIL if samples follow data structure)
4	length	long	number of samples in array
8	sampleRate	4 bytes	sample rate (Fixed)
12	loopStart	long	loop point beginning
16	loopEnd	long	loop point ending
20	encode	byte	sample's encoding option
21	baseFrequency	byte	base frequency of sample
22	sampleArea	variable	sampled-sound data

ExtSoundHeader Data Structure

0	samplePtr	long	pointer to samples (or NIL if samples follow data structure)
4	numChannels	long	number of channels in sample
8	sampleRate	4 bytes	sample rate (Fixed)
12	loopStart	long	loop point beginning
16	loopEnd	long	loop point ending

Sound Manager

20	encode	byte	sample's encoding option
21	baseFrequency	byte	base frequency of sample
22	numFrames	long	total number of frames
26	AIFFSampleRate	10 bytes	rate of original sample (Extended80)
36	markerChunk	long	reserved
40	instrumentChunks	long	pointer to instrument info
44	AESRecording	long	pointer to audio info
48	sampleSize	word	number of bits per sample
50	futureUse1	word	reserved
52	futureUse2	long	reserved
56	futureUse3	long	reserved
60	futureUse4	long	reserved
64	sampleArea	variable	sampled-sound data

CmpSoundHeader Data Structure

0	samplePtr	long	pointer to samples (or NIL if samples follow data structure)
4	numChannels	long	number of channels in sample
8	sampleRate	4 bytes	sample rate (Fixed)
12	loopStart	long	loop point beginning
16	loopEnd	long	loop point ending
20	encode	byte	sample's encoding option
21	baseFrequency	byte	base frequency of original sample
22	numFrames	long	length of sample in frames
26	AIFFSampleRate	10 bytes	rate of original sample (Extended80)
36	markerChunk	long	reserved
40	format	OSType	data format type
44	futureUse2	long	reserved
48	stateVars	long	pointer to StateBlock
52	leftOverSamples	long	pointer to LeftOverBlock
56	compressionID	word	ID of compression algorithm
58	packetSize	word	number of bits per packet
60	snthID	word	unused
62	sampleSize	word	bits in each sample point
64	sampleArea	variable	compressed sound data

SndDoubleBufferHeader Data Structure

0	dbhNumChannels	word	number of sound channels
2	dbhSampleSize	word	sample size, if noncompressed
4	dbhCompressionID	word	ID of compression algorithm
6	dbhPacketSize	word	number of bits per packet
8	dbhSampleRate	4 bytes	sample rate (Fixed)
12	dbhBufferPtr	2 longs	pointers to SndDoubleBuffer data structures
20	dbhDoubleBack	long	pointer to doubleback procedure

SndDoubleBuffer Data Structure

0	dbNumFrames	long	number of frames in buffer
4	dbFlags	long	buffer status flags
8	dbUserInfo	2 longs	for application's use
16	dbSoundData	variable	array of data

ChunkHeader Data Structure

0	ckID	long	chunk type ID
4	ckSize	long	number of bytes of data

ContainerChunk Data Structure

0	ckID	long	chunk type ID ('FORM')
4	ckSize	long	number of bytes of data
8	formType	long	type of file

FormatVersionChunk Data Structure

0	ckID	long	chunk type ID ('FVER')
4	ckSize	long	number of bytes of data (4)
8	timestamp	long	date of format version

CommonChunk Data Structure

0	ckID	long	chunk type ID ('COMM')
4	ckSize	long	number of bytes of data (18)
8	numChannels	word	number of channels
10	numSampleFrames	long	number of sample frames
14	sampleSize	word	number of bits per sample
16	sampleRate	10 bytes	number of frames per second (Extended80)

ExtCommonChunk Data Structure

0	ckID	long	chunk type ID ('COMM')
4	ckSize	long	number of bytes of data (22 + length of compression name)
8	numChannels	word	number of channels
10	numSampleFrames	long	number of sample frames
14	sampleSize	word	number of bits per sample
16	sampleRate	10 bytes	number of frames per second (Extended80)
26	compressionType	long	compression type ID
30	compressionName	variable	compression type name

SoundDataChunk

0	ckID	long	chunk type ID ('SSND')
4	ckSize	long	number of bytes of data
8	offset	long	offset to sound data
12	blockSize	long	size of alignment blocks

Trap Macros

Trap Macro Requiring Routine Selectors`_SoundDispatch`

Selector	Routine
\$00000010	MACEVersion
\$00040010	Comp3to1
\$00080010	Exp1to3
\$000C0008	SndSoundManagerVersion
\$000C0010	Comp6to1
\$00100008	SndChannelStatus
\$00100010	Exp1to6
\$00140008	SndManagerStatus
\$00180008	SndGetSysBeepState
\$001C0008	SndSetSysBeepState
\$00200008	SndPlayDoubleBuffer
\$02040008	SndPauseFilePlay
\$02240024	GetSysBeepVolume
\$02280024	SetSysBeepVolume
\$022C0024	GetDefaultOutputVolume
\$02300024	SetDefaultOutputVolume
\$03080008	SndStopFilePlay
\$0D000008	SndStartFilePlay
\$04040024	GetSoundHeaderOffset

Result Codes

<code>noErr</code>	0	No error
<code>paramErr</code>	-50	A parameter is incorrect
<code>noHardwareErr</code>	-200	Required sound hardware not available
<code>notEnoughHardwareErr</code>	-201	Insufficient hardware available
<code>queueFull</code>	-203	No room in the queue
<code>resProblem</code>	-204	Problem loading the resource
<code>badChannel</code>	-205	Channel is corrupt or unusable
<code>badFormat</code>	-206	Resource is corrupt or unusable
<code>notEnoughBufferSpace</code>	-207	Insufficient memory available
<code>badFileFormat</code>	-208	File is corrupt or unusable, or not AIFF or AIFF-C
<code>channelBusy</code>	-209	Channel is busy
<code>buffersTooSmall</code>	-210	Buffer is too small

Sound Manager

channelNotBusy	-211	Channel not currently used
noMoreRealTime	-212	Not enough CPU time available
siInvalidCompression	-223	Invalid compression type

Sound Input Manager

Contents

About the Sound Input Manager	3-3
Sound Recording Without the Standard Interface	3-4
Interaction With Sound Input Devices	3-4
Sound Input Device Drivers	3-5
Using the Sound Input Manager	3-5
Recording Sounds Directly From a Device	3-6
Defining a Sound Input Completion Routine	3-9
Defining a Sound Input Interrupt Routine	3-10
Getting and Setting Sound Input Device Information	3-10
Writing a Sound Input Device Driver	3-13
Responding to Status and Control Requests	3-13
Responding to Read Requests	3-15
Supporting Stereo Recording	3-16
Supporting Continuous Recording	3-17
Sound Input Manager Reference	3-17
Constants	3-17
Gestalt Selector and Response Bits	3-17
Sound Input Device Information Selectors	3-18
Data Structures	3-26
Sound Input Parameter Blocks	3-26
Sound Input Manager Routines	3-27
Recording Sounds	3-28
Opening and Closing Sound Input Devices	3-31
Recording Sounds Directly From Sound Input Devices	3-33
Manipulating Device Settings	3-41
Constructing Sound Resource and File Headers	3-44
Registering Sound Input Devices	3-48
Converting Between Milliseconds and Bytes	3-51
Obtaining Information	3-53
Application-Defined Routines	3-53

Sound Input Completion Routines	3-54
Sound Input Interrupt Routines	3-55
Summary of the Sound Input Manager	3-57
Pascal Summary	3-57
Constants	3-57
Data Types	3-58
Sound Input Manager Routines	3-59
Application-Defined Routines	3-60
C Summary	3-61
Constants	3-61
Data Types	3-62
Sound Input Manager Routines	3-63
Application-Defined Routines	3-65
Assembly-Language Summary	3-65
Data Structures	3-65
Trap Macros	3-66
Result Codes	3-66

Sound Input Manager

This chapter describes the Sound Input Manager, the part of the Macintosh system software that controls the recording of sound through sound input devices. You can use the Sound Input Manager to display and manage the sound recording dialog box. This ensures that the user is presented with a consistent and standard user interface for sound recording. You can, however, also use Sound Input Manager routines to record sound without the sound recording dialog box or to interact directly with a sound input device driver.

To use this chapter, you should already be familiar with the information in the chapter “Introduction to Sound on the Macintosh” earlier in this book, and in particular with the portions of that chapter that concern sound recording. That chapter explains how your application can record either a sound resource or a sound file using the standard sound recording dialog box. You need to read this chapter only if you need to interact with the Sound Input Manager at a lower level than is allowed by the high-level functions `SndRecord` and `SndRecordToFile`. For example, you need to read this chapter to learn how to

- record sound without using the sound recording dialog box
- interact with a sound input device driver
- write a sound input device driver

To use this chapter, you should also be familiar with the chapter “Sound Manager” in this book, especially the portions of that chapter that describe

- the format of sampled-sound data
- the Macintosh Audio Compression and Expansion (MACE) routines
- the structure of sound resources and sound files
- the use of the `Gestalt` function to determine whether certain sound-related facilities are available.

If you are writing a sound input device driver, you should already be familiar with writing device drivers in general, as described in the book *Inside Macintosh: Devices*.

About the Sound Input Manager

The Sound Input Manager uses sound input device drivers to allow applications to access sound input hardware in a device-independent way. A **sound input device driver** is a standard Macintosh device driver used to interface to an audio digitizer or other recording hardware. If you use the Sound Input Manager’s high-level routines, the Sound Input Manager handles all communication with a sound input device driver for you. If, however, you need to use the Sound Input Manager’s low-level routines, you must open a sound input device driver yourself. You might also need to get information about certain attributes of a sound input device. Sound input device drivers allow your application to query a device about such attributes.

Sound Recording Without the Standard Interface

The Sound Input Manager provides your application with the ability to record and digitally store sounds in a device-independent manner even if your application does not use the standard sound recording interface. In cases where you need very fine control over the recording process, you can call various low-level sound input routines.

Your application can obtain control over sound recording in two different ways. First, if your application uses the sound recording dialog box, you can modify the dialog box's features by defining a custom filter procedure, as explained in detail in the chapter "Dialog Manager" in *Inside Macintosh: Macintosh Toolbox Essentials*. Second, if your application needs to fine tune the sound recording process itself (or if your application does not use the standard sound recording dialog box), then the application must use the Sound Input Manager's low-level routines.

In instances where you need to gain greater control over the recording process, you can use a set of routines that manipulate the incoming sound data by using sound parameter blocks. The parameter blocks contain information about the current recording device, the length recorded, a routine to call on completion of the recording, and so forth. You can call the `SPBRecord` function (or the `SPBRecordToFile` function) to begin a recording. Then you can use the functions `SPBPauseRecording`, `SPBResumeRecording`, and `SPBStopRecording` to control the recording. Note that you need to open a device (using the `SPBOpenDevice` function) before you can record from it. On completion of the recording, you should close the device (using the `SPBCloseDevice` function).

If you do record sounds using the Sound Input Manager's low-level routines, you also need to set up your own sound resource headers or sound files, because the Sound Input Manager's low-level routines return raw sampled-sound data to your application. The Sound Input Manager provides two functions, `SetupSndHeader` and `SetupAIFFHeader`, that allow you to set up your own sound resource headers or sound files.

Interaction With Sound Input Devices

The Sound Input Manager provides routines that allow your application to request information about a sound input device or to change a sound input device's settings. The types of information you can obtain about a sound input device include

- the name, icon, and icon mask of the device driver
- whether the device driver supports asynchronous recording
- the device's settings, such as the number of channels the device is to record, the compression type, the number of bytes per sample at the current compression setting, and the sample rate to be produced by the device
- the range of compression types, sample rates, and sample sizes that the device supports

You can also use the Sound Input Manager to change some of a sound input device's settings and to turn features on and off. For example, you can turn on and off automatic gain control on some device drivers. **Automatic gain control** moderates sound recording

to give a consistent signal level. Second, you can turn on and off the **playthrough feature**, which allows the user to hear through the Macintosh speaker the sound being recorded. Third, you can turn on and off **VOX recording**, or voice-activated recording, which allows your application to record only when the amplitude of sound input exceeds a certain level. You can use VOX recording either to prevent recording from starting until sound is at least a certain amplitude or to automatically stop recording when sound falls below a certain amplitude. This latter capability is called **VOX stopping**.

An important feature of sound input devices is **continuous recording**. All sound input devices that support asynchronous recording should support continuous recording as well. Continuous recording allows your application to make several consecutive calls to the `SPBRecord` function without losing data between calls. For example, you might need to record a lengthy sound to disk but not be able to fit the entire sound into RAM. Thus, it's important to be able to save a buffer of data to disk while the sound input device driver continues to collect recorded data. The Sound Input Manager's `SndRecordToFile` function relies on continuous recording.

To get information about a device or to turn features on and off, you can use the `SPBGetDeviceInfo` and `SPBSetDeviceInfo` functions. These functions allow you to use sound input device information selectors to specify what type of information you need to know about the device or what settings you wish to change.

Sound Input Device Drivers

The Sound Input Manager also provides several routines intended for use only by sound input device drivers. Sound input device drivers need to register themselves with the Sound Input Manager by calling the `SPBSignInDevice` function. This makes that device visible in the Sound In control panel for possible selection as the current input device. You can remove a device from that panel by calling the `SPBSignOutDevice` function.

For Macintosh computers with built-in sound recording hardware, the system software includes a sound input device driver. This driver automatically calls `SPBSignInDevice` when the computer starts up. If you are creating a sound input device driver for some other sound recording hardware, your device driver must register itself at startup time. Once your driver is registered, it must respond to Status, Control, and Read calls issued by the Sound Input Manager. The Sound Input Manager issues Status calls to get information about a device, Control calls to set device settings, and Read calls to initiate recording.

Using the Sound Input Manager

You can use the Sound Input Manager to record sounds with the sound recording dialog box, to record sounds directly from a device, to get and set information about a sound input device, and to register your sound input device driver so that it can respond to

Sound Input Manager

Read, Status, and Control calls. This section does not explain how to record sounds using the sound recording dialog box; for information on that, see the chapter “Introduction to Sound on the Macintosh” in this book.

Recording Sounds Directly From a Device

The Sound Input Manager provides a number of routines that you can use for low-level control over the recording process (such as the ability to intercept sound input data at interrupt time). You can open a sound input device and read data from it by calling these low-level Sound Input Manager routines. Several of those routines access information through a **sound input parameter block**, which is defined by the `SPB` data type:

```

TYPE SPB =
RECORD
    inRefNum:      LongInt;    {reference number of input device}
    count:         LongInt;    {number of bytes to record}
    milliseconds: LongInt;    {number of milliseconds to record}
    bufferLength:  LongInt;    {length of buffer to record into}
    bufferPtr:     Ptr;        {pointer to buffer to record into}
    completionRoutine: ProcPtr; {pointer to a completion routine}
    interruptRoutine: ProcPtr;  {pointer to an interrupt routine}
    userLong:      LongInt;    {for application's use}
    error:         OSErr;      {error returned after recording}
    unused1:       LongInt;    {reserved}
END;

```

The `inRefNum` field indicates the reference number of the sound input device from which the recording is to occur. You can obtain the reference number of the default sound input device by using the `SPBOpenDevice` function.

The `count`, `milliseconds`, and `bufferLength` fields jointly determine the length of recording. The `count` field indicates the number of bytes to record; the `milliseconds` field indicates the number of milliseconds to record; and the `bufferLength` field indicates the length in bytes of the buffer into which the recorded sound data is to be placed. If the `count` and `milliseconds` fields are not equivalent, then the field which specifies the longer recording time is used. If the buffer specified by the `bufferLength` field is shorter than this recording time, then the recording time is truncated so that the recorded data can fit into the buffer specified by the `bufferPtr` field. The Sound Input Manager provides two functions, `SPBMillisecondsToBytes` and `SPBBytesToMilliseconds`, that allow you to convert between byte and millisecond values.

After recording finishes, the `count` and `milliseconds` fields indicate the number of bytes and milliseconds actually recorded.

The `completionRoutine` and `interruptRoutine` fields allow your application to define a sound input completion routine and a sound input interrupt routine, respectively. More information on these routines is provided later in this section.

Sound Input Manager

The `userLong` field contains a long integer that is provided for your application's own use. You can use this field, for instance, to pass a handle to an application-defined structure to the sound input completion or interrupt routine. Or, you can use this field to store the value of your application's A5 register, so that your sound input completion or interrupt routine can access your application's global variables. For more information on preserving the value of the A5 register, see the discussion of the `SetA5` and `SetCurrentA5` functions in the chapter "Memory Management Utilities" in *Inside Macintosh: Memory*.

The `error` field describes any errors that occur during the recording. This field contains a value greater than 0 while recording unless an error occurs, in which case it contains a value less than 0 that indicates an operating system error. Your application can poll this field to check on the status of an asynchronous recording. If recording terminates without an error, this field contains 0.

Listing 3-1 shows how to set up a sound parameter block and record synchronously using the `SPBRecord` function. This procedure takes one parameter, a handle to a block of memory in which the recorded sound data is to be stored. It is assumed that the block of memory is large enough to hold the sound to be recorded.

Listing 3-1 Recording directly from a sound input device

```
PROCEDURE MyRecordSnd (mySndH: Handle);
CONST
    kAsync = TRUE;
    kMiddleC = 60;
VAR
    mySPB:           SPB;           {a sound input parameter block}
    myInRefNum:      LongInt;       {device reference number}
    myBuffSize:      LongInt;       {size of buffer to record into}
    myHdrLen:        Integer;       {length of sound header}
    myNumChans:      Integer;       {number of channels}
    mySampSize:      Integer;       {size of a sample}
    mySampRate:      Fixed;         {sample rate}
    myCompType:      OSType;        {compression type}
    myErr:           OSErr;
BEGIN
    {Open the default input device for reading and writing.}
    myErr := SPBOpenDevice('', siWritePermission, myInRefNum);

    IF myErr = noErr THEN
    BEGIN
        {Get current settings of sound input device.}
        MyGetDeviceSettings(myInRefNum, myNumChans, mySampRate,
            mySampSize, myCompType);
```

Sound Input Manager

```

{Set up handle to contain the 'snd ' resource header.}
myErr := SetupSndHeader(mySndH, myNumChans, mySampRate, mySampSize,
                        myCompType, kMiddleC, 0, myHeadrLen);

{Leave room in buffer for the sound resource header.}
myBuffSize := GetHandleSize(mySndH) - myHeadrLen;

{Lock down the sound handle until the recording is over.}
HLockHi(mySndH);

{Set up the sound input parameter block.}
WITH mySPB do
BEGIN
    inRefNum := myInRefNum;           {input device reference number}
    count := myBuffSize;             {number of bytes to record}
    milliseconds := 0;               {no milliseconds}
    bufferLength := myBuffSize;      {length of buffer}
    bufferPtr := Ptr(ORD4(mySndH^) + myHeadrLen);
                                     {put data after 'snd ' header}
    completionRoutine := NIL;        {no completion routine}
    interruptRoutine := NIL;         {no interrupt routine}
    userLong := 0;                   {no user data}
    error := noErr;                  {clear error field}
    unused1 := 0;                    {clear reserved field}
END;

{Record synchronously through the open sound input device.}
myErr := SPBRecord(@mySPB, NOT kAsync);

HUnlock(mySndH);                    {unlock the handle}

{Indicate the number of bytes actually recorded.}
myErr := SetupSndHeader(mySndH, myNumChans, mySampRate, mySampSize,
                        myCompType, kMiddleC, mySPB.count,
                        myHeadrLen);

{Close the input device.}
myErr := SPBCloseDevice(myInRefNum);
END;
END;

```

Sound Input Manager

The `MyRecordSnd` procedure defined in Listing 3-1 opens the default sound input device by using the `SPBOpenDevice` function. You can specify one of two values for the permission parameter of `SPBOpenDevice`:

```
CONST
    siReadPermission = 0; {open device for reading}
    siWritePermission = 1; {open device for reading/writing}
```

You must open a device for both reading and writing if you intend to use the `SPBSetDeviceInfo` function or the `SPBRecord` function. If `SPBOpenDevice` successfully opens the specified device for reading and writing, `MyRecordSnd` calls the `MyGetDeviceSettings` procedure (defined in Listing 3-3 on page 3-12). That procedure calls the Sound Input Manager function `SPBGetDeviceInfo` (explained in “Getting and Setting Sound Input Device Information” on page 3-10) to determine the current number of channels, sample rate, sample size, and compression type in use by the device.

This information is then passed to the `SetupSndHeader` function, which sets up the handle `mySndH` with a sound header describing the current device settings. After doing this, `MyRecordSnd` sets up a sound input parameter block and calls the `SPBRecord` function to record a sound. Note that the handle must be locked during the recording because the parameter block contains a pointer to the input buffer. After the recording is done, `MyRecordSnd` once again calls the `SetupSndHeader` function to fill in the actual number of bytes recorded.

If the `MyRecordSnd` procedure defined in Listing 3-1 executes successfully, the handle `mySndH` points to a resource of type `'snd'`. Your application can then synchronously play the recorded sound, for example, by executing the following line of code:

```
myErr := SndPlay(NIL, mySndH, FALSE);
```

For more information on playing sounds your application has recorded, see the chapter “Sound Manager” in this book.

Defining a Sound Input Completion Routine

The `completionRoutine` field of the sound parameter block record contains the address of a completion routine that is executed when the recording terminates normally, either by reaching its prescribed time or size limits or by the application calling the `SPBStopRecording` function. A completion routine should have the following format:

```
PROCEDURE MySICompletionRoutine (inParamPtr: SPBPtr);
```

The completion routine is passed the address of the sound input parameter block that was passed to the `SPBRecord` function. You can gain access to other data structures in your application by passing an address in the `userLong` field of the parameter block. After the completion routine executes, your application should check the `error` field of the sound input parameter block to see if an error code was returned.

Sound Input Manager

Your sound input interrupt routine is always called at interrupt time, so it should not call routines that might allocate or move memory or assume that A5 is set up. For more information on sound input interrupt routines, see “Sound Input Interrupt Routines” beginning on page 3-55.

Defining a Sound Input Interrupt Routine

The `interruptRoutine` field of the sound input parameter block contains the address of a routine that executes when the internal buffers of an asynchronous recording device are filled. The internal buffers contain raw sound samples taken directly from the input device. The interrupt routine can modify the samples in the buffer in any way it requires. The processed samples are then written to the application buffer. If compression is enabled, the modified data is compressed after your interrupt routine operates on the samples and before the samples are written to the application buffer.

Your sound input interrupt routine is always called at interrupt time, so it should not call routines that might allocate or move memory or assume that A5 is set up. For more information on sound input interrupt routines, see “Sound Input Interrupt Routines” beginning on page 3-55.

Getting and Setting Sound Input Device Information

You can get information about a specific sound input device and alter a sound input device’s settings by calling the functions `SPBGetDeviceInfo` and `SPBSetDeviceInfo`. These functions accept **sound input device information selectors** that determine which information you need or want to change. The selectors currently available are defined by constants of type `OSType`.

Here is a list of the selectors that all sound input device drivers must support. For complete details on all the selectors described in this section, see “Sound Input Device Information Selectors” beginning on page 3-18.

```
CONST
    siAsync           = 'asyn';    {asynchronous capability}
    siChannelAvailable = 'chav';    {number of channels available}
    siCompressionAvailable = 'cmav'; {compression types available}
    siCompressionFactor = 'cmfa';   {current compression factor}
    siCompressionType = 'comp';     {compression type}
    siContinuous      = 'cont';     {continuous recording}
    siDeviceBufferInfo = 'dbin';     {size of interrupt buffer}
    siDeviceConnected = 'dcon';     {input device connection status}
    siDeviceIcon       = 'icon';     {input device icon}
    siDeviceName       = 'name';     {input device name}
    siLevelMeterOnOff  = 'lmet';     {level meter state}
    siNumberChannels   = 'chan';     {current number of channels}
    siRecordingQuality  = 'qual';    {recording quality}
    siSampleRate       = 'srat';     {current sample rate}
```

Sound Input Manager

```

siSampleRateAvailable = 'srav';    {sample rates available}
siSampleSizeAvailable = 'ssav';    {sample sizes available}
siSampleSize          = 'ssiz';    {current sample size}
siTwosComplementOnOff = 'twos';    {two's complement state}

```

The Sound Input Manager defines several selectors that specifically help it interact with sound input device drivers. Your application should not use any of these selectors, but if you are implementing a sound input device driver, you need to support these selectors. They are:

```

CONST
siCloseDriver          = 'clos';    {release driver}
siInitializeDriver     = 'init';    {initialize driver}
siPauseRecording       = 'paus';    {pause recording}
siUserInterruptProc    = 'user';    {set sound input interrupt routine}

```

Finally, there are a number of sound input device information selectors that sound input device drivers can optionally support. If you are writing an application, you can use these selectors to interact with a sound input device driver, but you should be aware that some drivers might not support all of them. To determine if a driver supports one of these selectors, you can use the `SPBGetDeviceInfo` function. If no errors are returned, then the selector is supported when using the `SPBGetDeviceInfo` and the `SPBSetDeviceInfo` functions.

```

CONST
siActiveChannels       = 'chac';    {channels active}
siActiveLevels         = 'lmac';    {levels active}
siAGCOnOff             = 'agc ';    {automatic gain control state}
siCompressionHeader   = 'cmhd';    {get compression header}
siCompressionNames    = 'cnam';    {return compression type names}
siInputGain           = 'gain';    {input gain level}
siInputSource         = 'sour';    {input source selector}
siInputSourceNames    = 'snam';    {input source names}
siOptionsDialog       = 'optd';    {display options dialog box}
siPlayThruOnOff       = 'plth';    {play-through state}
siStereoInputGain     = 'sgai';    {stereo input gain level}
siVoxRecordInfo       = 'voxr';    {VOX record parameters}
siVoxStopInfo         = 'voxs';    {VOX stop parameters}

```

The format of the relevant data (either returned by the Sound Input Manager or provided by you) depends on the selector you provide. For example, if you want to determine the name of some sound input device, you can pass to the `SPBGetDeviceInfo` function the `siDeviceName` selector and a pointer to a 256-byte buffer. If the `SPBGetDeviceInfo` function can get the information, it fills that buffer with the name of the specified sound input device. Listing 3-2 illustrates one way you can determine the name of a particular sound input device.

Listing 3-2 Determining the name of a sound input device

```

FUNCTION MyGetDeviceName (myRefNum: LongInt; VAR dName: Str255): OSErr;
BEGIN
    MyGetDeviceName := SPBGetDeviceInfo(myRefNum, siDeviceName, Ptr(@dName));
END;

```

Note

You can get the name and icon of all connected sound input devices without using sound input information selectors by using the `SPBGetIndexedDevice` function, which is described on page 3-49. ♦

Some selectors cause the `SPBGetDeviceInfo` function to return data of other types. Listing 3-3 illustrates how to determine the number of channels, the sample rate, the sample size, and the compression type currently in use by a given sound input device. (The procedure defined in Listing 3-3 is called in the procedure defined in Listing 3-1.)

Listing 3-3 Determining some sound input device settings

```

PROCEDURE MyGetDeviceSettings (myRefNum: LongInt;
                               VAR numChannels: Integer;
                               VAR sampleRate: Fixed;
                               VAR sampleSize: Integer;
                               VAR compressionType: OSType);
VAR
    myErr: OSErr;
BEGIN
    {Get number of active channels.}
    myErr := SPBGetDeviceInfo (myRefNum, siNumberChannels, Ptr(@numChannels));
    {Get sample rate.}
    myErr := SPBGetDeviceInfo(myRefNum, siSampleRate, Ptr(@sampleRate));
    {Get sample size.}
    myErr := SPBGetDeviceInfo(myRefNum, siSampleSize, Ptr(@sampleSize));
    {Get compression type.}
    myErr := SPBGetDeviceInfo(myRefNum, siCompressionType,
                               Ptr(@compressionType));
END;

```

All of the selectors that return a handle allocate the memory for that handle in the current heap zone; you are responsible for disposing of that handle when you are done with it, and you should verify that there is enough memory for such a handle before calling the selector.

Writing a Sound Input Device Driver

This section describes what you need to do when you do write a sound input device driver. If you write a sound input device driver, you should set the `drvFlags` field of the sound input device driver's header to indicate that the driver can handle Status, Control, and Read requests. The driver header should also indicate that the driver needs to be locked.

IMPORTANT

You don't need to write a device driver to use sound input capabilities. ▲

After you create a device driver, you must write an extension that installs it. Before your extension installs the driver, it should pass the `Gestalt` function the `gestaltSoundAttr` attribute selector and inspect the `gestaltSoundIOMgrPresent` bit to determine if the sound input routines are available. If so, the extension should install the sound input device driver into the unit table just as any other driver must be installed.

After installing the driver, the extension must then make an Open request to the driver, so that the driver can perform any necessary initialization. In particular, the driver might set the `dctlStorage` field of the device control entry to a pointer or a handle to a block in the system heap containing all of the variables that it might need. Finally, the device driver signs into the Sound Input Manager by calling the `SPBSignInDevice` function.


Once signed in, a driver can receive Status, Control, and Read requests from the Sound Input Manager. On entry, the A0 register contains a pointer to a standard Device Manager parameter block, and the A1 register contains a pointer to the device control entry. For more information on using registers in a device driver, see *Inside Macintosh: Devices*.

Responding to Status and Control Requests

The Sound Input Manager supports sound input device information selectors by sending your device driver Status and Control requests. It uses Status requests to get information about your device; it uses Control requests to change settings of your sound input device.


The behavior of your sound input device driver in response to Status and Control requests depends on the value of the `csCode` field of the Device Manager control parameter block. If the `csCode` field contains 2, then the sound input information selector is passed in the first 4 bytes of the `csParam` field of the Device Manager control parameter block. For Status requests, the next 18 bytes can be used for your device driver to pass information back to an application. For Control requests, these 18 bytes are used by an application to pass data to your sound input device driver.

Figure 3-1 shows the contents of the `csParam` field of the Device Manager control parameter block for a sample Status request. The first four bytes of the `csParam` field contain the input selector 'srav', which is a request for the available sample rates. The next four bytes of the field contain a pointer to an application-supplied buffer in which to return the data (the number of rates available) from the Status request.

Figure 3-1 An example of the `csParam` field for a Status request

On exit from the Status request, your sound input device driver can respond in one of two ways. If you are returning fewer than 18 bytes of data, your device driver should specify in the first 4 bytes of the `csParam` field of the Device Manager control parameter block the number of bytes of data being returned and place the data in the following 18 bytes. In this case, the Sound Input Manager copies the data to the application-supplied buffer identified in Figure 3-1. If you are returning more than 18 bytes of data, your device driver should copy the data to the application-supplied buffer. In this case, your device driver needs to place a zero in the first 4 bytes of the `csParam` field to indicate to the Sound Input Manager that the data has already been copied to the application-supplied buffer.

Figure 3-2 shows the contents of the `csParam` field of the Device Manager control parameter block for a sample Control request. The first four bytes of the `csParam` field contain the input selector 'srat' which determines the sample rate for the sound input device. The next eighteen bytes contain the data, which in this example is the sample rate to set for your sound input device. This is a `Fixed` value of four bytes in length.

Figure 3-2 An example of the `csParam` field for a Control request

Note

Some sound input information selectors require your sound input device driver to allocate a handle in which to store information. In this case, your driver should attempt to allocate an appropriately sized handle in the current heap zone. If allocation fails, your driver should return the appropriate Memory Manager result code. ♦

Your sound input device driver must respond to a core set of selectors, but the remaining selectors defined by Apple are optional. Your device driver might also define private selectors to support proprietary features. (Selectors containing all lowercase letters, however, are reserved by Apple.) The section “Getting and Setting Sound Input Device Information” beginning on page 3-10 lists the core selectors and other selectors that have been defined.

If the `csCode` field contains 1 (which can occur only for Control requests), the Sound Input Manager is attempting to stop asynchronous recording; that is, it is issuing a `KillIO` request. In response to this, the driver should stop copying data to the application buffer, update the `ioActCount` field of the request parameter block, and return via an `RTS` instruction.

Before exiting after a Status and Control request, your sound input device driver should fill the `D0` register with the appropriate result code or `noErr`. To exit, your sound input device driver should check whether the Status and Control request was executed immediately or was queued.

Note

In current versions of system software, the Sound Input Manager always issues Status and Control requests immediately. This might change in future versions of system software. ♦

Your sound input device driver can determine whether a request is issued immediately by checking the `noQueueBit` in the `ioTrap` field of the Device Manager control parameter block. If the request was made immediately, the Control routine should return via an `RTS` instruction; if the request was queued, the Control routine should jump to the Device Manager’s `IODone` function via the global jump vector `JIODone`. You need to make sure that the `A0` and `A1` registers are set the same as they are on entry to the device driver or `JIODone` will fail.

Responding to Read Requests

When a sound input device receives a Read request, it must start recording and saving recorded data into the buffer specified by the `ioBuffer` field of the request parameter block. If that field is `NIL`, the driver should record but not save the data. During a Read request, your sound input device driver can access the sound parameter block that initiated recording through the `ioMisc` field of the request parameter block.

If a previous Control request has assigned a sound input interrupt routine to the device driver and your driver records asynchronously, then the driver must call the routine each time its internal buffer becomes filled, setting up registers as described in “Defining a Sound Input Interrupt Routine” on page 3-10. The buffer size that your device driver specifies in the `D1` register should indicate how much your device records during every

Sound Input Manager

interrupt. For example, a sound input device driver that uses the serial port might use a buffer as small as 3 bytes. For the built-in sound input port on the Macintosh LC and other Macintosh models, the buffer is 512 bytes long.

Your device driver should update the `ioActCount` field of the request parameter block with the actual number of bytes of sampled-sound data recorded. This allows the Sound Input Manager to monitor the activity of your device driver. Whether your device driver operates synchronously or asynchronously, it should complete recording by jumping to the Device Manager's `IODone` function via the global jump vector `JIODone`. You need to set the `D0` register to the appropriate result code before jumping to the Device Manager's `IODone` function.

Supporting Stereo Recording

Many sound input devices support recording stereo sounds (that is, sounds from two or more channels). If you are writing a device driver for a stereo device, you need to make sure that you support the `siNumberChannels`, `siActiveChannels`, and `siActiveLevels` selectors.

The `siNumberChannels` selector controls the number of sound input channels and thereby determines the format of the data stream your device driver produces. If the number of channels is 1, the driver should produce monophonic data in response to a Read request. If the number of channels is 2, the driver should produce interleaved stereo data in response to a Read request.

The `siActiveChannels` selector controls which of the available input channels are used for recording. The active channels are specified using a bitmap value. For example, the value `$01` indicates that the first channel (the left channel) is to be used. The value `$02` indicates that the second channel (the right channel) is to be used.

The `siNumberChannels` and `siActiveChannels` selectors together determine the exact format of the output data stream. If the current number of channels is 1 and the current active channel bitmap is `$01`, the driver should produce a stream of monophonic data containing samples only from the left input channel. If the current number of channels is 1 and the current active channel bitmap is `$02`, the driver should produce a stream of monophonic data containing samples only from the right input channel. If the current number of channels is 1 and the current active channel bitmap is `$03`, the driver should mix the right and left channels to produce a stream of monophonic data. If the current number of channels is 2 and the current active channel bitmap is `$03`, the driver should produce a stream of interleaved samples from the left and right input channels.

Note

If the `siActiveChannels` selector is never passed to a sound input device driver, it's recommended that the active channel default bitmap for both monophonic and stereo recording should be `$03`. When the active channel bitmap conflicts with the number of channels (for example, there are two channels but the active channel bitmap is `$01`), you should use the default value of `$03`. ♦

Supporting Continuous Recording

If your sound input device driver supports continuous recording, it must do more than respond to Status, Control, and Read requests. It must also, if continuous recording is on, begin recording into an internal ring buffer as soon as a Read request completes. The buffer should be made large enough so that the sound input device driver can support successive requests to the `SPBRecord` function in most circumstances; however, if your driver exhausts the internal buffer, your driver should begin recording again at the start of the buffer.

When the sound input device driver receives a subsequent Read request, it should record to the application's buffer first all of the data in the internal ring buffer and then as much fresh data as it can record during one interrupt.

If a Read terminates due to a `KillIO` request, your sound input device driver does not need to continue recording samples to the internal ring buffer until after the next uninterrupted Read request.

Sound Input Manager Reference

This section describes the constants, data structure, and the routines provided by the Sound Input Manager.

Constants

This section describes the constants you can use with the `SPBSetDeviceInfo` and `SPBGetDeviceInfo` functions to set or get device information. It also lists the `Gestalt` function sound attributes selector and the returned bit numbers that are relevant to the Sound Input Manager. All other constants defined by the Sound Input Manager are described at the appropriate location in this chapter. (For example, the constants that you can use to specify sound recording qualities are described in connection with the `SndRecord` function beginning on page 3-28.)

Gestalt Selector and Response Bits

You can pass the `gestaltSoundAttr` selector to the `Gestalt` function to determine information about the sound input capabilities of a Macintosh computer.

```
CONST
    gestaltSoundAttr          = 'snd ';    {sound attributes selector}
```

The `Gestalt` function returns information by setting or clearing bits in the response parameter. The bits relevant to the Sound Input Manager are defined by constants:

Sound Input Manager

CONST

```

gestaltSoundIOMgrPresent    = 3;    {sound input routines available}
gestaltBuiltInSoundInput    = 4;    {built-in input hw available}
gestaltHasSoundInputDevice  = 5;    {sound input device available}
gestaltPlayAndRecord        = 6;    {built-in hw can play while recording}
gestalt16BitSoundIO         = 7;    {built-in hw can handle 16-bit data}
gestaltStereoInput          = 8;    {built-in hw can record stereo sounds}
gestaltLineLevelInput       = 9;    {built-in input hw needs line level}

```

Constant descriptions

`gestaltSoundIOMgrPresent`

Set if the Sound Input Manager is available.

`gestaltBuiltInSoundInput`

Set if a built-in sound input device is available.

`gestaltHasSoundInputDevice`

Set if a sound input device is available. This device can be either built-in or external.

`gestaltPlayAndRecord`

Set if the built-in sound hardware is able to play and record sounds simultaneously. If this bit is clear, the built-in sound hardware can either play or record, but not do both at once. This bit is valid only if the `gestaltBuiltInSoundInput` bit is set, and it applies only to any built-in sound input and output hardware.

`gestalt16BitSoundIO`

Set if the built-in sound hardware is able to play and record 16-bit samples. This indicates that built-in hardware necessary to handle 16-bit data is available.

`gestaltStereoInput`

Set if the built-in sound hardware can record stereo sounds.

`gestaltLineLevelInput`

Set if the built-in sound input port requires line level input.

Note

For complete information about the `Gestalt` function, see the chapter “Gestalt Manager” in *Inside Macintosh: Operating System Utilities*. ♦

Sound Input Device Information Selectors

You can call the `SPBSetDeviceInfo` and `SPBGetDeviceInfo` functions to set or get information about a sound input device. You pass each of those functions a sound input device information selector in the `infoType` parameter to specify the type of information you need. The available device information selectors are defined by constants.

IMPORTANT

Some of these selectors are intended for use only by the Sound Input Manager and other parts of the system software that need to interact directly with sound input device drivers. (For example, the Sound Input Manager sends the `siCloseDriver` selector to a sound input device driver when it is closing the device.) In general, applications should not use these reserved selectors. ▲

CONST

<code>siActiveChannels</code>	= 'chac';	{channels active}
<code>siActiveLevels</code>	= 'lmac';	{levels active}
<code>siAGCOnOff</code>	= 'agc';	{automatic gain control state}
<code>siAsync</code>	= 'asyn';	{asynchronous capability}
<code>siChannelAvailable</code>	= 'chav';	{number of channels available}
<code>siCloseDriver</code>	= 'clos';	{reserved for internal use only}
<code>siCompressionAvailable</code>	= 'cmav';	{compression types available}
<code>siCompressionFactor</code>	= 'cmfa';	{current compression factor}
<code>siCompressionHeader</code>	= 'cmhd';	{return compression header}
<code>siCompressionNames</code>	= 'cnam';	{return compression type names}
<code>siCompressionType</code>	= 'comp';	{current compression type}
<code>siContinuous</code>	= 'cont';	{continuous recording}
<code>siDeviceBufferInfo</code>	= 'dbin';	{size of interrupt buffer}
<code>siDeviceConnected</code>	= 'dcon';	{input device connection status}
<code>siDeviceIcon</code>	= 'icon';	{input device icon}
<code>siDeviceName</code>	= 'name';	{input device name}
<code>siInitializeDriver</code>	= 'init';	{reserved for internal use only}
<code>siInputGain</code>	= 'gain';	{input gain level}
<code>siInputSource</code>	= 'sour';	{input source selector}
<code>siInputSourceNames</code>	= 'snam';	{input source names}
<code>siLevelMeterOnOff</code>	= 'lmet';	{level meter state}
<code>siNumberChannels</code>	= 'chan';	{current number of channels}
<code>siOptionsDialog</code>	= 'optd';	{display options dialog box}
<code>siPauseRecording</code>	= 'paus';	{reserved for internal use only}
<code>siPlayThruOnOff</code>	= 'plth';	{play-through state}
<code>siRecordingQuality</code>	= 'qual';	{recording quality}
<code>siSampleRate</code>	= 'srat';	{current sample rate}
<code>siSampleRateAvailable</code>	= 'srav';	{sample rates available}
<code>siSampleSize</code>	= 'ssiz';	{current sample size}
<code>siSampleSizeAvailable</code>	= 'ssav';	{sample sizes available}
<code>siStereoInputGain</code>	= 'sgai';	{stereo input gain level}
<code>siTwosComplementOnOff</code>	= 'twos';	{two's complement state}
<code>siUserInterruptProc</code>	= 'user';	{reserved for internal use only}
<code>siVoxRecordInfo</code>	= 'voxr';	{VOX record parameters}
<code>siVoxStopInfo</code>	= 'voxs';	{VOX stop parameters}

Sound Input Manager

Constant descriptions`siActiveChannels`

Get or set the channels to record from. When setting the active channels, the data passed in is a long integer that is interpreted as a bitmap describing the channels to record from. For example, if bit 0 is set, then the first channel is made active. The samples for each active channel are interleaved in the application's buffer. When reading the active channels, the data returned is a bitmap of the active channels.

`siActiveLevels`

Get the current signal level for each active channel. The `infoData` parameter points to an array of integers, the size of which depends on the number of active channels. You can determine how many channels are active by calling `SPBGetDeviceInfo` with the `siNumberChannels` selector.

`siAGCOnOff`

Get or set the current state of the automatic gain control feature. The `infoData` parameter points to an integer, which is 0 if gain control is off and 1 if it is on.

`siAsync`

Determine whether the driver supports asynchronous recording functions. The `infoData` parameter points to an integer, which is 0 if the driver supports synchronous calls only and 1 otherwise. Some sound input drivers do not support asynchronous recording at all, and some might support asynchronous recording only on certain hardware configurations.

`siChannelAvailable`

Get the maximum number of channels this device can record. The `infoData` parameter points to an integer, which is the number of available channels.

`siCloseDriver`

The Sound Input Manager sends this selector when it closes a device previously opened with write permission. The sound input device driver should stop any recording in progress, deallocate the input hardware, and initialize local variables to default settings. Your application should never issue this selector directly. The `infoData` parameter is unused with this selector.

`siCompressionAvailable`

Get the number and list of compression types this device can produce. The `infoData` parameter points to an integer, which is the number of compression types, followed by a handle. The handle references a list of compression types, each of type `OSType`.

`siCompressionFactor`

Get the compression factor of the current compression type. For example, the compression factor for MACE 3:1 compression is 3. If a sound input device driver supports only compression type 'NONE', the returned compression type is 1. The `infoData` parameter points to an integer, which is the compression factor.

`siCompressionHeader`

Get a compressed sound header for the current recording settings. Your application passes in a pointer to a compressed sound header

and the driver fills it in. Before calling `SPBGetDeviceInfo` with this selector, you should set the `numFrames` field of the compressed sound header to the number of bytes in the sound. When `SPBGetDeviceInfo` returns successfully, that field contains the number of sample frames in the sound. This selector is needed only by drivers that use compression types that are not directly supported by Apple. If you call this selector after recording a sound, your application can get enough information about the sound to play it or save it in a file. The `infoData` parameter points to a compressed sound header.

`siCompressionNames`

Get a list of names of the compression types supported by the sound input device. In response to a `Status` call, a sound input device driver returns, in the location specified by the `infoData` parameter, a handle to a block of memory that contains the names of all compression types supported by the driver. It is the driver's responsibility to allocate that block of memory, but it should not release it. The software issuing this selector is responsible for disposing of the handle. As a result, a device driver must detach any resource handles (by calling `DetachResource`) before returning them to the caller. The data in the handle has the same format as an `'STR#'` resource: a two-byte count of the strings in the resource, followed by the strings themselves. The strings should occur in the same order as the compression types returned by the `siCompressionAvailable` selector. If the driver does not support compression, it returns `siUnknownInfoType`. If the driver supports compression but for some reason not all compression types are currently selectable, it returns a list of all available compression types.

`siCompressionType`

Get or set the compression type. Some devices allow the incoming samples to be compressed before being placed in your application's input buffer. The `infoData` parameter points to a buffer of type `OSType`, which is the compression type.

`siContinuous`

Get or set the state of continuous recording from this device. If recording is being turned off, the driver stops recording samples to its internal buffer. Only sound input device drivers that support asynchronous recording support continuous recording. The `infoData` parameter points to an integer, which is the state of continuous recording (0 is off, 1 is on).

`siDeviceBufferInfo`

Get the size of the device's internal buffer. This information can be useful when you want to modify sound input data at interrupt time. Note, however, that if a driver is recording continuously, then the size of the buffer passed to your sound input interrupt routine might be greater than the size this selector returns because data recorded between calls to `SPBRecord` as well as recorded during calls to `SPBRecord` will be sent to your interrupt routine. The `infoData` parameter points to a long integer, which is the size of the device's internal buffer.

Sound Input Manager

`siDeviceConnected`

Get the state of the device connection. The `infoData` parameter points to an integer, which is one of the following constants:

CONST

```

    siDeviceIsConnected      = 1;
    siDeviceNotConnected     = 0;
    siDontKnowIfConnected    = -1;

```

The `siDeviceIsConnected` constant indicates that the device is connected and ready. The `siDeviceNotConnected` constant indicates that the device is not connected. The `siDontKnowIfConnected` constant indicates that the Sound Input Manager cannot determine whether the device is connected.

`siDeviceIcon`

Get the device's icon and icon mask. In response to a `Status` call, a sound input device driver should return, in the location specified by the `infoData` parameter, a handle to a block of memory that contains the icon and its mask in the format of an 'ICN#' resource. It is the driver's responsibility to allocate that block of memory, but it should not release it. The software issuing this selector is responsible for disposing of the handle. As a result, a device driver should detach any resource handles (by calling `DetachResource`) before returning them to the caller.

`siDeviceName`

Get the name of the sound input device. Your application must pass a pointer to a buffer that will be filled in with the device's name. The buffer needs to be large enough to hold a `Str255` data type.

`siInitializeDriver`

The Sound Input Manager sends this selector when it opens a sound input device with write permission. The sound input device driver initializes local variables and prepares to start recording. If possible, the driver initializes the device to a sampling rate of 22 kHz, a sample size of 8 bits, mono recording, no compression, automatic gain control on, and all other features off. Your application should never issue this selector directly. The `infoData` parameter is unused with this selector.

`siInputGain`

Get and set the current sound input gain. If the available hardware allows adjustment of the recording gain, this selector lets you get and set the gain. In response to a `Status` call, a sound input driver returns the current gain setting. In response to a `Control` call, a sound input driver sets the gain level used for all subsequent recording to the specified value. The `infoData` parameter points to a 4-byte value of type `Fixed` ranging from 0.5 to 1.5, where 1.5 specifies maximum gain.

`siInputSource`

Get and set the current sound input source. If the available hardware allows recording from more than one source, this selector lets you get and set the source. In response to a `Status` call, a sound input driver returns the current source value; if the driver supports only one source, it returns `siUnknownInfoType`. In response to a `Control` call, a sound input driver sets the source of all subsequent

recording to the value passed in. If the value is less than 1 or greater than the number of input sources, the driver returns `paramErr`; if the driver supports only one source, it returns `siUnknownInfoType`. The `infoData` parameter points to an integer, which is the index of the current sound input source.

`siInputSourceNames`

Get a list of the names of all the sound input sources supported by the sound input device. In response to a `Status` call, a sound input device driver returns, in the location specified by the `infoData` parameter, a handle to a block of memory that contains the names of all sound sources supported by the driver. It is the driver's responsibility to allocate that block of memory, but it should not release it. The software issuing this selector is responsible for disposing of the handle. As a result, a device driver must detach any resource handles (by calling `DetachResource`) before returning them to the caller. The data in the handle has the same format as an `'STR#'` resource: a two-byte count of the strings in the resource, followed by the strings themselves. The strings should occur in the same order as the input sources returned by the `siInputSource` selector. If the driver supports only one source, it returns `siUnknownInfoType`. If the driver supports more than one source but for some reason not all of them are currently selectable, it returns a list of all available input sources.

`siLevelMeterOnOff`

Get or set the current state of the level meter. For calls to set the level meter, the `infoData` parameter points to an integer that indicates whether the level meter is off (0) or on (1). To get the level meter setting, the `infoData` parameter points to two integers; the first integer indicates the state of the level meter, and the second integer contains the level value of the meter. The level meter setting is an integer that ranges from 0 (no volume) to 255 (full volume).

`siNumberChannels`

Get or set the number of channels this device is to record. The `infoData` parameter points to an integer, which indicates the number of channels. Note that this selector determines the format of the data stream output by the driver. If the number of channels is 1, the driver should output monophonic data in response to a `Read` call. If the number of channels is 2, the driver should output interleaved stereo data.

`siOptionsDialog`

Determine whether the driver supports an Options dialog box (`SPBGetDeviceInfo`) or cause the driver to display the Options dialog box (`SPBSetDeviceInfo`). This dialog box is designed to allow the user to configure device-specific features of the sound input hardware. With `SPBGetDeviceInfo`, the `infoData` parameter points to an integer, which indicates whether the driver supports an Options dialog box (1 if it supports it, 0 otherwise). With `SPBSetDeviceInfo`, the `infoData` parameter is unused.

Sound Input Manager

`siPauseRecording`

The Sound Input Manager uses this selector to get or set the current pause state. The sound input device driver continues recording but does not store the sampled data in a buffer. Your application should never issue this selector directly. The `infoData` parameter points to an integer, which indicates the state of pausing (0 is off, 1 is on).

`siPlayThruOnOff`

Get or set the current play-through state and volume. The `infoData` parameter points to an integer, which indicates the current play-through volume (1 to 7). If that integer is 0, then play-through is off.

`siRecordingQuality`

Get or set the current quality of recorded sound. The `infoData` parameter points to a buffer of type `OSType`, which is the recording quality. Currently three qualities are supported, defined by these constants:

```
CONST
    siBestQuality           = 'best';
    siBetterQuality        = 'betr';
    siGoodQuality          = 'good';
```

These qualities are defined by the sound input device driver. Usually *best* means monaural, 8-bit, 22 kHz, sound with no compression.

`siSampleRate`

Get or set the sample rate to be produced by this device. The sample rate must be in the range 0 to 65535.65535 Hz. The sample rate is declared as a `Fixed` data type. In order to accommodate sample rates greater than 32 kHz, the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768. The `infoData` parameter points to a buffer of type `Fixed`, which is the sample rate.

`siSampleRateAvailable`

Get the range of sample rates this device can produce. The `infoData` parameter points to an integer, which is the number of sample rates the device supports, followed by a handle. The handle references a list of sample rates, each of type `Fixed`. If the device can record a range of sample rates, the number of sample rates is set to 0 and the handle contains two rates, the minimum and the maximum of the range of sample rates. Otherwise, a list is returned that contains the sample rates supported. In order to accommodate sample rates greater than 32 kHz, the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768.

`siSampleSize`

Get or set the sample size to be produced by this device. Because some compression formats require specific sample sizes, this selector might return an error when compression is used. The `infoData` parameter points to an integer, which is the sample size.

Sound Input Manager

`siSampleSizeAvailable`

Get the range of sample sizes this device can produce. The `infoData` parameter points to an integer, which is the number of sample sizes the device supports, followed by a handle. The handle references a list of sample sizes, each of type `Integer`.

`siStereoInputGain`

Get and set the current stereo sound input gain. If the available hardware allows adjustment of the recording gain, this selector lets you get and set the gain for each of two channels (left or right). In response to a `Status` call, a sound input driver should return the current gain setting for the specified channel. In response to a `Control` call, a sound input driver should set the gain level used for all subsequent recording to the specified value. The `infoData` parameter points to two 4-byte values of type `Fixed` ranging from 0.5 to 1.5, where 1.5 specifies maximum gain. The first of these values is equivalent to the gain for the left channel and the second value is equivalent to the gain for the right channel.

`siTwosComplementOnOff`

Get or set the current state of the two's complement feature. This selector only applies to 8-bit data. (16-bit samples are always stored in two's complement format.) If on, the driver stores all samples in the application buffer as two's complement values (that is, -128 to 127). Otherwise, the driver stores the samples as offset binary values (that is, 0 to 255). The `infoData` parameter points to an integer, which is the current state of the two's complement feature (1 if two's complement output is desired, 0 otherwise).

`siUserInterruptProc`

The Sound Input Manager sends this selector to specify the sound input interrupt routine that the sound input device driver should call. Your application should never issue this selector directly. The `infoData` parameter points to a procedure pointer, which is the address of the sound input interrupt routine.

`siVoxRecordInfo`

Get or set the current VOX recording parameters. The `infoData` parameter points to two integers. The first integer indicates whether VOX recording is on or off (0 if off, 1 if on). The second integer indicates the VOX record trigger value. Trigger values range from 0 to 255 (0 is trigger immediately, 255 is trigger only on full volume).

`siVoxStopInfo`

Get or set the current VOX stopping parameters. The `infoData` parameter points to three integers. The first integer indicates whether VOX stopping is on or off (0 if off, 1 if on). The second integer indicates the VOX stop trigger value. Trigger values range from 0 to 255 (255 is stop immediately, 0 is stop only on total silence). The third integer indicates how many milliseconds the trigger value must be continuously valid for recording to be stopped. Delay values range from 0 to 65,535.

Data Structures

This section describes the sound input parameter block.

Sound Input Parameter Blocks

The `SPBRecord` and `SPBRecordToFile` functions require a pointer to a sound input parameter block that defines characteristics of the recording. If you define a sound input completion routine or a sound input interrupt routine, your routine receives a pointer to a sound input parameter block. If you are using only the Sound Input Manager's high-level `SndRecord` and `SndRecordToFile` functions, the operation of sound input parameter blocks is transparent to your application. A sound input parameter block is defined by the `SPB` data type.

```

TYPE SPB =
RECORD
    inRefNum:      LongInt;    {reference number of input device}
    count:         LongInt;    {number of bytes to record}
    milliseconds: LongInt;    {number of milliseconds to record}
    bufferLength: LongInt;    {length of buffer to record into}
    bufferPtr:     Ptr;        {pointer to buffer to record into}
    completionRoutine: ProcPtr; {pointer to a completion routine}
    interruptRoutine: ProcPtr; {pointer to an interrupt routine}
    userLong:      LongInt;    {for application's use}
    error:         OSErr;      {error returned after recording}
    unused1:       LongInt;    {reserved}
END;
```

Field descriptions

<code>inRefNum</code>	The reference number of the sound input device (as received from the <code>SPBOpenDevice</code> function) from which the recording is to occur.
<code>count</code>	On input, the number of bytes to record. On output, the number of bytes actually recorded. If this field specifies a longer recording time than the <code>milliseconds</code> field, then the <code>milliseconds</code> field is ignored on input.
<code>milliseconds</code>	On input, the number of milliseconds to record. On output, the number of milliseconds actually recorded. If this field specifies a longer recording time than the <code>count</code> field, then the <code>count</code> field is ignored on input.
<code>bufferLength</code>	The length of the buffer into which recorded sound data is placed. The recording time specified by the <code>count</code> or <code>milliseconds</code> field is truncated to fit into this length, if necessary.
<code>bufferPtr</code>	A pointer to the buffer into which recorded data is placed. If this field is <code>NIL</code> , then the <code>count</code> , <code>milliseconds</code> , and <code>bufferLength</code> fields are ignored and the recording will continue indefinitely until the <code>SPBStopRecording</code> function is called. However, the data is

Sound Input Manager

not stored anywhere, so setting this field to `NIL` is useful only if you want to do something in a sound input interrupt routine but do not want to save the recorded sound.

`completionRoutine`

A pointer to a completion routine that is called when the recording terminates as a result of your calling the `SPBStopRecording` function or when the limit specified by the `count` or `milliseconds` field is reached. The completion routine executes only if `SPBRecord` is called asynchronously and therefore is called at interrupt time.

`interruptRoutine`

A pointer to a routine that is called by asynchronous recording devices when their internal buffers are full. You can define a sound input interrupt routine to modify uncompressed sound samples before they are placed into the buffer specified in the `bufferPtr` parameter. The interrupt routine executes only if `SPBRecord` is called asynchronously and therefore is called at interrupt time.

`userLong`

A long integer available for the application's own use. You can use this field, for instance, to pass a handle to an application-defined structure to the completion routine or to the interrupt routine.

`error`

On exit, the error that occurred during recording. This field contains a value greater than 0 while recording unless an error occurs, in which case it contains a value less than 0 that indicates an operating system error. Your application can poll this field to check on the status of an asynchronous recording. If recording terminates without an error, this field contains 0.

`unused1`

Reserved for use by Apple. You should always initialize this field to 0.

Sound Input Manager Routines

This section describes the routines provided by the Sound Input Manager. You can use these routines to

- record sounds using the sound recording dialog box
- open and close sound input devices
- record sounds directly from sound input devices
- get information about sound input devices and change device settings
- construct sound resource and file headers
- register sound input devices with the Sound Input Manager
- convert recording times between millisecond and byte values
- obtain information about the version of the Sound Input Manager that is running

The section “Application-Defined Routines” on page 3-53 describes the format of sound input completion routines and sound input interrupt routines.

Recording Sounds

The Sound Input Manager provides two high-level sound input functions, `SndRecord` and `SndRecordToFile`, for recording sound. These input routines are analogous to the two Sound Manager functions `SndPlay` and `SndStartFilePlay`. By using these high-level routines, you can be assured that your application presents a user interface that is consistent with that displayed by other applications doing sound input. Both `SndRecord` and `SndRecordToFile` attempt to record sound data from the sound input hardware currently selected in the Sound In control panel.

SndRecord

You can use the `SndRecord` function to record sound resources into memory.

```
FUNCTION SndRecord (filterProc: ProcPtr; corner: Point;
                  quality: OSType; VAR sndHandle: Handle):
    OSErr;
```

`filterProc`

A pointer to an event filter function that determines how user actions in the sound recording dialog box are filtered (similar to the `filterProc` parameter specified in a call to the `ModalDialog` procedure). By specifying your own filter function, you can override or add to the default actions of the items in the dialog box. If `filterProc` isn't `NIL`, `SndRecord` filters events by calling the function that `filterProc` points to.

`corner`

The horizontal and vertical coordinates of the upper-left corner of the sound recording dialog box (in global coordinates).

`quality`

The desired quality of the recorded sound.

`sndHandle`

On entry, a handle to some storage space or `NIL`. On exit, a handle to a valid sound resource (or unchanged, if the call did not execute successfully).

DESCRIPTION

The `SndRecord` function records sound into memory. The recorded data has the structure of a format 1 'snd' resource and can later be played using the `SndPlay` function or can be stored as a resource. `SndRecord` displays a sound recording dialog box and is always called synchronously. Controls in the dialog box allow the user to start, stop, pause, and resume sound recording, as well as to play back the recorded sound. The dialog box also lists the remaining recording time and the current microphone sound level.

The `quality` parameter defines the desired quality of the recorded sound. Currently, three values are recognized for the `quality` parameter:

Sound Input Manager

CONST

```

    siBestQuality      = 'best';    {the best quality available}
    siBetterQuality    = 'betr';    {a quality better than good}
    siGoodQuality      = 'good';    {a good quality}

```

The precise meanings of these parameters are defined by the sound input device driver. For Apple-supplied drivers, this parameter determines whether the recorded sound is to be compressed, and if so, whether at a 6:1 or a 3:1 ratio. The quality `siBestQuality` does not compress the sound and provides the best quality output, but at the expense of increased memory use. The quality `siBetterQuality` is suitable for most nonvoice recording, and `siGoodQuality` is suitable for voice recording.

The `sndHandle` parameter is a handle to some storage space. If the handle is `NIL`, the Sound Input Manager allocates a handle of the largest amount of space that it can find in your application's heap and returns this handle in the `sndHandle` parameter. The Sound Input Manager resizes the handle when the user clicks the Save button in the sound recording dialog box. If the `sndHandle` parameter passed to `SndRecord` is not `NIL`, the Sound Input Manager simply stores the recorded data in the location specified by that handle.

SPECIAL CONSIDERATIONS

Because the `SndRecord` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndRecord` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$08040014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>userCanceledErr</code>	-128	User canceled the operation
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siUnknownQuality</code>	-232	Unknown quality

SEE ALSO

See the chapter “Dialog Manager” in *Inside Macintosh: Macintosh Toolbox Essentials* for a complete description of event filter functions.

SndRecordToFile

You can use `SndRecordToFile` to record sound data into a file.

```
FUNCTION SndRecordToFile (filterProc: ProcPtr; corner: Point;
                        quality: OSType;
                        fRefNum: Integer): OSErr;
```

<code>filterProc</code>	A pointer to a function that determines how user actions in the sound recording dialog box are filtered.
<code>corner</code>	The horizontal and vertical coordinates of the upper-left corner of the sound recording dialog box (in global coordinates).
<code>quality</code>	The desired quality of the recorded sound, as described on page 3-28.
<code>fRefNum</code>	The file reference number of an open file to save the audio data in.

DESCRIPTION

The `SndRecordToFile` function works just like `SndRecord` except that it stores the sound input data into a file. The resulting file is in either AIFF or AIFF-C format and contains the information necessary to play the file by using the Sound Manager's `SndStartFilePlay` function. The `SndRecordToFile` function is always called synchronously.

Your application must open the file specified in the `fRefNum` parameter before calling the `SndRecordToFile` function. Your application must close the file sometime after calling `SndRecordToFile`.

SPECIAL CONSIDERATIONS

Because the `SndRecordToFile` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SndRecordToFile` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$07080014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>userCanceledErr</code>	-128	User canceled the operation
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siUnknownQuality</code>	-232	Unknown quality

Opening and Closing Sound Input Devices

You can use the `SPBOpenDevice` function to open the default sound input device that the user has selected in the Sound In control panel or to open a specific sound input device. You must open a device before you can record from it by using `SPBRecord`, but the Sound Input Manager's high-level routines automatically open the default sound input device. You can close a sound input device by calling the `SPBCloseDevice` function.

SPBOpenDevice

You can use the `SPBOpenDevice` function to open a sound input device.

```
FUNCTION SPBOpenDevice (deviceName: Str255; permission: Integer;
                       VAR inRefNum: LongInt): OSErr;
```

`deviceName`

The name of the sound input device to open, or the empty string if the default sound input device is to be opened.

`permission`

A flag that indicates whether subsequent operations with that device are to be read/write or read-only.

`inRefNum`

On exit, if the function is successful, a device reference number for the open sound input device.

DESCRIPTION

The `SPBOpenDevice` function attempts to open a sound input device having the name indicated by the `deviceName` parameter. If `SPBOpenDevice` succeeds, it returns a device reference number in the `inRefNum` parameter. The `permission` parameter indicates whether subsequent operations with that device are to be read/write or read-only. If the device is not already in use, read/write permission is granted; otherwise, only read-only operations are allowed. To make any recording requests or to call the `SPBSetDeviceInfo` function, read/write permission must be available. Use these constants to request the appropriate permission:

```
CONST
```

```
    siReadPermission    = 0;    {open device for reading}
    siWritePermission   = 1;    {open device for reading/writing}
```

You can request that the current default sound input device be opened by passing either a zero-length string or a `NIL` string as the `deviceName` parameter. If only one sound input device is installed, that device is used. Generally you should open the default device unless you specifically want to use some other device. You can get a list of the available devices by calling the `SPBGetIndexedDevice` function.

SPECIAL CONSIDERATIONS

Because the `SPBOpenDevice` function allocates memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBOpenDevice` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$05180014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>permErr</code>	-54	Device already open for writing
<code>siBadDeviceName</code>	-228	Invalid device name

SPBCloseDevice

You can use the `SPBCloseDevice` function to close a sound input device.

```
FUNCTION SPBCloseDevice (inRefNum: LongInt): OSErr;
```

`inRefNum` The device reference number of the sound input device to close.

DESCRIPTION

The `SPBCloseDevice` function closes a device that was previously opened by `SPBOpenDevice` and whose device reference number is specified in the `inRefNum` parameter.

SPECIAL CONSIDERATIONS

Because the `SPBCloseDevice` function moves or purges memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBCloseDevice` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$021C0014</code>

RESULT CODES

noErr	0	No error
siBadRefNum	-229	Invalid reference number

Recording Sounds Directly From Sound Input Devices

The Sound Input Manager provides a number of routines that allow you to begin, pause, resume, and stop recording directly from a sound input device. These low-level routines do not display the sound recording dialog box to the user.

SPBRecord

You can use the `SPBRecord` function to record audio data into memory, either synchronously or asynchronously.

```
FUNCTION SPBRecord (inParamPtr: SPBPtr; asynchFlag: Boolean):
    OSErr;
```

`inParamPtr` A pointer to a sound input parameter block.

`asynchFlag` A Boolean value that specifies whether the recording occurs asynchronously (`TRUE`) or synchronously (`FALSE`).

You specify values and receive return values in the sound input parameter block.

Parameter block

→	<code>inRefNum</code>	LongInt	A reference number of a sound input device.
↔	<code>count</code>	LongInt	The number of bytes of recording.
↔	<code>milliseconds</code>	LongInt	The number of milliseconds of recording.
→	<code>bufferLength</code>	LongInt	The length of the buffer beginning at <code>bufferPtr</code> .
→	<code>bufferPtr</code>	Ptr	A pointer to a buffer for sampled-sound data.
→	<code>completionRoutine</code>	ProcPtr	A pointer to a completion routine.
→	<code>interruptRoutine</code>	ProcPtr	A pointer to an interrupt routine.
→	<code>userLong</code>	LongInt	Free for application's use.
←	<code>error</code>	OSErr	The error value returned after recording.
→	<code>unused1</code>	LongInt	Reserved.

Field descriptions

<code>inRefNum</code>	The device reference number of the sound input device, as obtained from the <code>SPBOpenDevice</code> function.
<code>count</code>	On input, the number of bytes to record. If this field indicates a longer recording time than the <code>milliseconds</code> field, then the

Sound Input Manager

	<code>milliseconds</code> field is ignored. On output, this field indicates the number of bytes actually recorded.
<code>milliseconds</code>	On input, the number of milliseconds to record. If this field indicates a longer recording time than the <code>count</code> field, then the <code>count</code> field is ignored. On output, this field indicates the number of milliseconds actually recorded.
<code>bufferLength</code>	The number of bytes in the buffer specified by the <code>bufferPtr</code> parameter. If this buffer length is too small to contain the amount of sampled-sound data specified in the <code>count</code> and <code>milliseconds</code> fields, then recording time is truncated so that the sampled-sound data fits in the buffer.
<code>bufferPtr</code>	A pointer to the buffer for the sampled-sound data, or <code>NIL</code> if you wish to record sampled-sound data without saving it. On exit, this buffer contains the sampled-sound data, which is interleaved for stereo sound on a sample basis (or on a packet basis if the data is compressed). This buffer contains only sampled-sound data, so if you need a sampled sound header, you should set that up in a buffer before calling <code>SPBRecord</code> and then record into the buffer following the sound header.
<code>completionRoutine</code>	A pointer to a completion routine. This routine is called when the recording terminates (either after you call the <code>SPBStopRecording</code> function or when the prescribed limit is reached). The completion routine is called only for asynchronous recording.
<code>interruptRoutine</code>	A pointer to an interrupt routine. The interrupt routine specified in the <code>interruptRoutine</code> field is called by asynchronous recording devices when their internal buffers are full.
<code>userLong</code>	A long integer that your application can use to pass data to your application's completion or interrupt routines.
<code>error</code>	On exit, a value greater than 0 while recording unless an error occurs, in which case it contains a value less than 0 that indicates an operating system error. Your application can poll this field to check on the status of an asynchronous recording. If recording terminates without an error, this field contains 0.
<code>unused1</code>	Reserved. You should set this field to 0 before calling <code>SPBRecord</code> .

DESCRIPTION

The `SPBRecord` function starts recording into memory from a device specified in a sound input parameter block. The sound data recorded is stored in the buffer specified by the `bufferPtr` and `bufferLength` fields of the parameter block. Recording lasts the longer of the times specified by the `count` and `milliseconds` fields of the parameter block, or until the buffer is filled. Recording is asynchronous if the `asynchFlag` parameter is `TRUE` and the specified sound input device supports asynchronous recording.

Sound Input Manager

If the `bufferPtr` field of the parameter block contains `NIL`, then the `count`, `milliseconds`, and `bufferLength` fields are ignored, and the recording continues indefinitely until you call the `SPBStopRecording` function. In this case, the audio data is not saved anywhere; this feature is useful only if you want to do something in your interrupt routine and do not want to save the audio data. However, if the recording is synchronous and `bufferPtr` is `NIL`, `SPBRecord` returns the result code `siNoBufferSpecified`.

The `SPBRecord` function returns the value that the `error` field of the parameter block contains when recording finishes.

SPECIAL CONSIDERATIONS

You can call the `SPBRecord` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBRecord` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$03200014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siNoSoundInHardware</code>	-220	No sound input hardware available
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siNoBufferSpecified</code>	-222	No buffer specified
<code>siDeviceBusyErr</code>	-227	Sound input device is busy

SEE ALSO

For an example of the use of the `SPBRecord` function, see Listing 3-1.

SPBRecordToFile

You can use the `SPBRecordToFile` function to record audio data into a file, either synchronously or asynchronously.

```
FUNCTION SPBRecordToFile (fRefNum: Integer; inParamPtr: SPBPtr;
                          asynchFlag: Boolean): OSErr;
```

`fRefNum` The file reference number of an open file in which to place the recorded sound data.

`inParamPtr` A pointer to a sound input parameter block.

Sound Input Manager

asynchFlag

A Boolean value that specifies whether the recording occurs asynchronously (TRUE) or synchronously (FALSE).

Parameter block

→	inRefNum	LongInt	A reference number of a sound input device.
↔	count	LongInt	The number of bytes of recording.
↔	milliseconds	LongInt	The number of milliseconds of recording.
→	completionRoutine	ProcPtr	A pointer to a completion routine.
→	interruptRoutine	ProcPtr	Unused.
→	userLong	LongInt	Free for application's use.
←	error	OSErr	The error value returned after recording.
→	unused1	LongInt	Reserved.

Field descriptions

inRefNum	The device reference number of the sound input device, as obtained from the <code>SPBOpenDevice</code> function.
count	On input, the number of bytes to record. If this field indicates a longer recording time than the <code>milliseconds</code> field, then the <code>milliseconds</code> field is ignored. On output, the number of bytes actually recorded.
milliseconds	On input, the number of milliseconds to record. If this field indicates a longer recording time than the <code>count</code> field, then the <code>count</code> field is ignored. On output, the number of milliseconds actually recorded.
completionRoutine	A pointer to a completion routine. This routine is called when the recording terminates (after you call the <code>SPBStopRecording</code> function, when the prescribed limit is reached, or after an error occurs). The completion routine is called only for asynchronous recording.
interruptRoutine	Unused. You should set this field to <code>NIL</code> before calling <code>SPBRecordToFile</code> .
userLong	A long integer that your application can use to pass data to your application's completion or interrupt routines.
error	On exit, the error that occurred during recording. This field contains the number 1 while recording unless an error occurs, in which case it contains a value less than 0 that indicates an operating system error. Your application can poll this field to check on the status of an asynchronous recording. If recording terminates without an error, this field contains 0.
unused1	Reserved. You should set this field to 0 before calling the <code>SPBRecordToFile</code> function.

DESCRIPTION

The `SPBRecordToFile` function starts recording from the specified device into a file. The sound data recorded is simply stored in the file, so it is up to your application to insert whatever headers are needed to play the sound with the Sound Manager. Your application must open the file specified by the `fRefNum` parameter with write access before calling `SPBRecordToFile`, and it must eventually close that file.

The fields in the parameter block specified by the `inParamPtr` parameter are identical to the fields in the parameter block passed to the `SPBRecord` function, except that the `bufferLength` and `bufferPtr` fields are not used. The `interruptRoutine` field is ignored by `SPBRecordToFile` because `SPBRecordToFile` copies data returned by the sound input device driver to disk during the sound input interrupt routine, but you should initialize this field to `NIL`.

The `SPBRecordToFile` function writes samples to disk in the same format that they are read in from the sound input device. If compression is enabled, then the samples written to the file are compressed. Multiple channels of sound are interleaved on a sample basis (or, for compressed sound data, on a packet basis). When you are recording 8-bit audio data to an AIFF file, you must set the `siTwosComplementOnOff` flag to so that the data is stored on disk in the two's-complement format. If you don't store the data in this format, it sounds distorted when you play it back.

If any errors occur during the file writing process, recording is suspended. All File Manager errors are returned through the function's return value if the routine is called synchronously. If the routine is called asynchronously and the completion routine is not `NIL`, the completion routine is called and is passed a single parameter on the stack that points to the sound input parameter block; any errors are returned in the `error` field of the sound input parameter block.

The `SPBRecordToFile` function returns the value that the `error` field of the parameter block contains when recording finishes.

SPECIAL CONSIDERATIONS

Because the `SPBRecordToFile` function moves or purges memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBRecordToFile` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$04240014</code>

Sound Input Manager

RESULT CODES

noErr	0	No error
permErr	-54	Attempt to open locked file for writing
siNoSoundInHardware	-220	No sound input hardware available
siBadSoundInDevice	-221	Invalid sound input device
siHardDriveTooSlow	-224	Hard drive too slow to record

SPBPauseRecording

You can use the `SPBPauseRecording` function to pause recording from a sound input device.

```
FUNCTION SPBPauseRecording (inRefNum: LongInt): OSErr;
```

`inRefNum` The device reference number of the sound input device, as obtained from the `SPBOpenDevice` function.

DESCRIPTION

The `SPBPauseRecording` function pauses recording from the device specified by the `inRefNum` parameter. The recording must be asynchronous for this call to have any effect.

SPECIAL CONSIDERATIONS

You can call the `SPBPauseRecording` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBPauseRecording` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$02280014</code>

RESULT CODES

noErr	0	No error
siBadSoundInDevice	-221	Invalid sound input device

SPBResumeRecording

You can use the `SPBResumeRecording` function to resume recording from a sound input device.

```
FUNCTION SPBResumeRecording (inRefNum: LongInt): OSErr;
```

`inRefNum` The device reference number of the sound input device, as obtained from the `SPBOpenDevice` function.

DESCRIPTION

The `SPBResumeRecording` function resumes recording from the device specified by the `inRefNum` parameter. Recording on that device must previously have been paused by a call to the `SPBPauseRecording` function for `SPBResumeRecording` to have any effect.

SPECIAL CONSIDERATIONS

You can call the `SPBResumeRecording` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBResumeRecording` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$022C0014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device

SPBStopRecording

You can use the `SPBStopRecording` function to end a recording from a sound input device.

```
FUNCTION SPBStopRecording (inRefNum: LongInt): OSErr;
```

`inRefNum` The device reference number of the sound input device, as obtained from the `SPBOpenDevice` function.

Sound Input Manager

DESCRIPTION

The `SPBStopRecording` function stops recording from the device specified by the `inRefNum` parameter. The recording must be asynchronous for `SPBStopRecording` to have any effect. When you call `SPBStopRecording`, the sound input completion routine specified in the `completionRoutine` field of the sound input parameter block is called and the `error` field of that parameter block is set to `abortErr`. If you are writing a device driver, you will receive a `KillIOStatus` call. See the section “Writing a Sound Input Device Driver” beginning on page 3-13 for more information.

SPECIAL CONSIDERATIONS

You can call the `SPBStopRecording` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBStopRecording` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$02300014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device

SPBGetRecordingStatus

You can use `SPBGetRecordingStatus` to obtain recording status information about a sound input device.

```
FUNCTION SPBGetRecordingStatus (inRefNum: LongInt;
                               VAR recordingStatus: Integer;
                               VAR meterLevel: Integer;
                               VAR totalSamplesToRecord: LongInt;
                               VAR numberOfSamplesRecorded: LongInt;
                               VAR totalMsecsToRecord: LongInt;
                               VAR numberOfMsecsRecorded: LongInt):
    OSErr;
```

`inRefNum` The device reference number of the sound input device, as obtained from the `SPBOpenDevice` function.

`recordingStatus` The status of the recording. While the input device is recording, this parameter is set to a number greater than 0. When a recording terminates without an error, this parameter is set to 0. When an error occurs during

Sound Input Manager

recording or the recording has been terminated by a call to the `SPBStopRecording` function, this parameter is less than 0 and contains an error code.

`meterLevel`

The current input signal level. This level ranges from 0 to 255.

`totalSamplesToRecord`

The total number of samples to record, including those samples already recorded.

`numberOfSamplesRecorded`

The number of samples already recorded.

`totalMsecsToRecord`

The total duration of recording time, including recording time already elapsed.

`numberOfMsecsRecorded`

The amount of recording time that has elapsed.

DESCRIPTION

The `SPBGetRecordingStatus` function returns, in its second through seventh parameters, information about the recording on the device specified by the `inRefNum` parameter.

SPECIAL CONSIDERATIONS

You can call the `SPBGetRecordingStatus` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBGetRecordingStatus` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0E340014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device

Manipulating Device Settings

You can use the two functions `SPBGetDeviceInfo` and `SPBSetDeviceInfo` to read and change the settings of a sound input device.

SPBGetDeviceInfo

You can use the `SPBGetDeviceInfo` function to get information about the settings of a sound input device.

```
FUNCTION SPBGetDeviceInfo (inRefNum: LongInt; infoType: OSType;
                          infoData: Ptr): OSErr;
```

<code>inRefNum</code>	The device reference number of the sound input device, as obtained from the <code>SPBOpenDevice</code> function.
<code>infoType</code>	A sound input device information selector that specifies the type of information you need.
<code>infoData</code>	A pointer to a buffer in which information should be returned. This buffer must be large enough for the type of information specified in the <code>infoType</code> parameter.

DESCRIPTION

The `SPBGetDeviceInfo` function returns information about the sound input device specified by the `inRefNum` parameter. The type of information you want is specified in the `infoType` parameter. The available sound input device information selectors are listed in “Sound Input Device Information Selectors” beginning on page 3-18. The information is copied into the buffer specified by the `infoData` parameter.

SPECIAL CONSIDERATIONS

Because the `SPBGetDeviceInfo` function might move memory, you should not call it at interrupt time. Check the selector description of the selector you want to use to see if it moves memory before calling the `SPBGetDeviceInfo` function. Most of the selectors do not move memory and are therefore safe to use at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBGetDeviceInfo` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$06380014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siUnknownInfoType</code>	-231	Unknown type of information

SEE ALSO

Listing 3-2 on page 3-12 shows an example that uses the `SPBGetDeviceInfo` function to get the name of a sound input device driver.

SPBSetDeviceInfo

You can use the `SPBSetDeviceInfo` function to set information in a sound input device.

```
FUNCTION SPBSetDeviceInfo (inRefNum: LongInt; infoType: OSType;
                          infoData: Ptr): OSErr;
```

<code>inRefNum</code>	The device reference number of the sound input device, as obtained from the <code>SPBOpenDevice</code> function.
<code>infoType</code>	A sound input device information selector that specifies the type of information you need.
<code>infoData</code>	A pointer to a buffer. This buffer can contain information on entry, and information might be returned on exit. This buffer must be large enough for the type of information specified in the <code>infoType</code> parameter, and the data in the buffer must be set to appropriate values if information needs to be passed in to the <code>SPBSetDeviceInfo</code> function.

DESCRIPTION

The `SPBSetDeviceInfo` function sets information about the sound input device specified by the `inRefNum` parameter, based on the data in the buffer specified by the `infoData` parameter.

The type of setting you wish to change is specified in the `infoType` parameter. The sound input device information selectors are listed in “Sound Input Device Information Selectors” beginning on page 3-18.

SPECIAL CONSIDERATIONS

Because the `SPBSetDeviceInfo` function might move memory, you should not call it at interrupt time. Check the selector description of the selector you want to use to see if it moves memory before calling the `SPBGetDeviceInfo` function. Most of the selectors do not move memory and are therefore safe to use at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBSetDeviceInfo` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$063C0014</code>

Sound Input Manager

RESULT CODES

<code>noErr</code>	0	No error
<code>permErr</code>	-54	Attempt to open locked file for writing
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siDeviceBusyErr</code>	-227	Sound input device is busy
<code>siUnknownInfoType</code>	-231	Unknown type of information

Constructing Sound Resource and File Headers

The Sound Input Manager provides two functions, `SetupSndHeader` and `SetupAIFFHeader`, to help you set up headers for sound resources and sound files.

SetupSndHeader

You can use the `SetupSndHeader` function to construct a sound resource containing sampled sound that can be passed to the `SndPlay` function.

```
FUNCTION SetupSndHeader (sndHandle: Handle;
                        numChannels: Integer;
                        sampleRate: Fixed;
                        sampleSize: Integer;
                        compressionType: OSType;
                        baseFrequency: Integer;
                        numBytes: LongInt;
                        VAR headerLen: Integer): OSErr;
```

`sndHandle` A handle to a block of memory that is at least large enough to store the sound resource header information. The handle is not resized in any way upon successful completion of `SetupSndHeader`. The `SetupSndHeader` function simply fills the relocatable block specified by this parameter with the header information needed for a format 1 'snd' resource, including the sound resource header, the list of sound commands, and a sampled sound header. It is your application's responsibility to append the desired sampled-sound data.

`numChannels` The number of channels for the sound; one channel is equivalent to monaural sound and two channels are equivalent to stereo sound.

`sampleRate` The rate at which the sound was recorded. The sample rate is declared as a `Fixed` data type. In order to accommodate sample rates greater than 32 kHz, the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768.

`sampleSize` The sample size for the original sound (that is, bits per sample).

Sound Input Manager

<code>compressionType</code>	The compression type for the sound ('NONE', 'MAC3', 'MAC6', or other third-party types).
<code>baseFrequency</code>	The base frequency for the sound, expressed as a MIDI note value.
<code>numBytes</code>	The number of bytes of audio data that are to be stored in the handle. (This value is not necessarily the same as the number of samples in the sound.)
<code>headerLen</code>	On exit, the size (in bytes) of the 'snd' resource header that is created. In no case will this length exceed 100 bytes. This field allows you to put the audio data right after the header in the relocatable block specified by the <code>sndHandle</code> parameter. The value returned depends on the type of sound header created.

DESCRIPTION

The `SetupSndHeader` function creates a format 1 'snd' resource for a sampled sound. The resource contains a sound resource header that links the sound to the sampled synthesizer, a single sound command (a `bufferCmd` command to play the accompanying data), and a sampled sound header. You can use `SetupSndHeader` to construct a sampled sound header that can be passed to the Sound Manager's `SndPlay` function or stored as an 'snd' resource. After calling the `SetupSndHeader` function, your application should place the sampled-sound data directly after the sampled sound header so that, in essence, the sampled sound header's final field contains the sound data.

The sampled sound is in one of three formats depending on several of the parameters passed. Table 3-1 shows how `SetupSndHeader` determines what kind of sound header to create.

Table 3-1 The sampled sound header format used by `SetupSndHeader`

compressionType	numChannels	sampleSize	Sampled sound header format
'NONE'	1	8	SoundHeader
'NONE'	1	16	ExtSoundHeader
'NONE'	2	any	ExtSoundHeader
not 'NONE'	any	any	CmpSoundHeader

A good way to use this function is to create a handle in which you want to store a sampled sound, then call `SetupSndHeader` with the `numBytes` parameter set to 0 to see how much room the header for that sound will occupy and hence where to append the audio data. Then record the data into the handle and call `SetupSndHeader` again with `numBytes` set to the correct amount of sound data recorded. The handle filled out in this way can be passed to `SndPlay` to play the sound.

SPECIAL CONSIDERATIONS

You cannot call the `SetupSndHeader` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SetupSndHeader` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0D480014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siInvalidCompression</code>	-223	Invalid compression type

SEE ALSO

For an example that uses the `SetupSndHeader` function to set up a sound header before recording, see Listing 3-1 on page 3-7.

SetupAIFFHeader

You can use the `SetupAIFFHeader` function to set up a file that can subsequently be played by `SndStartFilePlay`.

```
FUNCTION SetupAIFFHeader (fRefNum: Integer;
                          numChannels: Integer;
                          sampleRate: Fixed;
                          sampleSize: Integer;
                          compressionType: OSType;
                          numBytes: LongInt;
                          numFrames: LongInt): OSErr;
```

`fRefNum` A file reference number of a file that is open for writing.

`numChannels` The number of channels for the sound; one channel is equivalent to monaural sound and two channels are equivalent to stereo sound.

`sampleRate` The rate at which the sound was recorded. The sample rate is declared as a `Fixed` data type. In order to accommodate sample rates greater than 32 kHz, the most significant bit is not treated as a sign bit; instead, that bit is interpreted as having the value 32,768.

`sampleSize` The sample size for the original sound (that is, bits per sample).

Sound Input Manager

<code>compressionType</code>	The compression type for the sound ('NONE', 'MAC3', 'MAC6', or other third-party types).
<code>numBytes</code>	The number of bytes of audio data that are to be stored in the Common Chunk of the AIFF or AIFF-C file.
<code>numFrames</code>	The number of sample frames for the sample sound. If you are using a compression type defined by Apple, you can pass 0 in this field and the appropriate value for this field will be computed automatically.

DESCRIPTION

The `SetupAIFFHeader` function creates an AIFF or AIFF-C file header, depending on the parameters passed to it:

- Uncompressed sounds of any type are stored in AIFF format (that is, the `compressionType` parameter is 'NONE').
- Compressed sounds of any type are stored in AIFF-C format (that is, the `compressionType` parameter is different from 'NONE').

Note

The `SetupAIFFHeader` function might format a sound file as an AIFF file even if the File Manager file type of a file is 'AIFC'. The Sound Manager will still play such files correctly. ♦

The AIFF header information is written starting at the current file position of the file specified by the `fRefNum` parameter, and the file position is left at the end of the header upon completion. The `SetupAIFFHeader` function creates a Form Chunk, a Format Version Chunk, a Common Chunk, and a Sound Data chunk, but it does not put any sound data at the end of the Sound Data Chunk.

A good way to use this routine is to create a file that you want to store a sound in, then call `SetupAIFFHeader` with `numBytes` set to 0 to position the file to be ready to write the audio data. Then record the data to the file, set the file position to the beginning of the file, and call `SetupAIFFHeader` again with `numBytes` set to the correct amount of sound data recorded. The file created in this way can be passed to the `SndStartFilePlay` function to play the sound.

SPECIAL CONSIDERATIONS

If recording produces an odd number of bytes of sound data, you must add a pad byte to make the total number of bytes even.

Because the `SetupAIFFHeader` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SetupAIFFHeader` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0B4C0014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siInvalidCompression</code>	-223	Invalid compression type

Registering Sound Input Devices

Sound input device drivers must call the `SPBSignInDevice` function to register with the Sound Input Manager before they can use its sound input services. You might call this routine at system startup time from within an extension to install a sound input device driver. Your application can generate a list of registered sound input devices by using the `SPBGetIndexedDevice` function. You can cancel the registration of your driver, thus removing it from the Sound control panel and making it inaccessible, by calling the `SPBSignOutDevice` function.

SPBSignInDevice

You can register a sound input device by calling the `SPBSignInDevice` function.

```
FUNCTION SPBSignInDevice (deviceRefNum: Integer;
                        deviceName: Str255): OSErr;
```

`deviceRefNum`

The device driver reference number of the sound input device to register with the Sound Input Manager.

`deviceName`

The device's name as it is to appear to the user in the Sound In control panel (which is not the name of the driver used by the Device Manager).

DESCRIPTION

The `SPBSignInDevice` function registers with the Sound Input Manager the device whose driver reference number is `deviceRefNum`.

The `deviceName` parameter specifies this device's name as it is to appear to the user in the Sound In control panel (which is not the name of the driver itself). Accordingly, the name should be as descriptive as possible. You should call `SPBSignInDevice` after you have already opened your driver by calling normal Device Manager routines.

SPECIAL CONSIDERATIONS

Because the `SPBSignInDevice` function moves or purges memory, you should not call it at interrupt time. You can, however, call it at system startup time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBSignInDevice` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$030C0014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device

SPBGetIndexedDevice

You can use the `SPBGetIndexedDevice` function to help generate a list of sound input devices.

```
FUNCTION SPBGetIndexedDevice (count: Integer;
                              VAR deviceName: Str255;
                              VAR deviceIconHandle: Handle):
    OSErr;
```

`count` The index number of the sound input device you wish to obtain information about.

`deviceName` On exit, the name of the sound input device specified by the `count` parameter.

`deviceIconHandle` On exit, a handle to the icon of the sound input device specified by the `count` parameter. The memory for this icon is allocated automatically, but your application must dispose of it.

DESCRIPTION

The `SPBGetIndexedDevice` function returns the name and icon of the device whose index is specified in the `count` parameter. Your application can create a list of sound input devices by calling this function with a count starting at 1 and incrementing it by 1 until the function returns `siBadSoundInDevice`.

Because the Sound In control panel allows the user to select a sound input device, most applications should not use this function. Your application might need to use this function if it allows the user to record from more than one sound input device at once.

SPECIAL CONSIDERATIONS

Because the `SPBGetIndexedDevice` function allocates memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBGetIndexedDevice` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$05140014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device

SPBSignOutDevice

You can use the `SPBSignOutDevice` function to cancel the registration of a device you have previously registered with the `SPBSignInDevice` function.

```
FUNCTION SPBSignOutDevice (deviceRefNum: Integer): OSErr;
```

`deviceRefNum`

The driver reference number of the device you wish to sign out.

DESCRIPTION

The `SPBSignOutDevice` function cancels the registration of the device whose driver reference number is `deviceRefNum`; the device is unregistered from the Sound Input Manager's list of available sound input devices and no longer appears in the Sound In control panel.

Ordinarily, you should not need to use the `SPBSignOutDevice` function. You might use it if your device driver detects that a sound input device is not functioning correctly or has been disconnected.

SPECIAL CONSIDERATIONS

Because the `SPBSignOutDevice` function moves or purges memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBSignOutDevice` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$01100014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siDeviceBusyErr</code>	-227	Sound input device is busy

Converting Between Milliseconds and Bytes

The Sound Input Manager provides two routines that allow you to convert between millisecond and byte recording values.

SPBMillisecondsToBytes

You can use the `SPBMillisecondsToBytes` function to determine how many bytes a recording of a certain duration will use.

```
FUNCTION SPBMillisecondsToBytes (inRefNum: LongInt;
                                VAR milliseconds: LongInt): OSErr;
```

inRefNum The device reference number of the sound input device, as obtained from the `SPBOpenDevice` function.

milliseconds On entry, the duration of the recording in milliseconds. On exit, the number of bytes that sampled-sound data would occupy for a recording of the specified duration on the device specified by the `inRefNum` parameter.

DESCRIPTION

The `SPBMillisecondsToBytes` function reports how many bytes are required to store a recording of duration `milliseconds`, given the input device's current sample rate, sample size, number of channels, and compression factor.

SPECIAL CONSIDERATIONS

You can call the `SPBMillisecondsToBytes` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBMillisecondsToBytes` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$04400014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device

SPBBytesToMilliseconds

You can use the `SPBBytesToMilliseconds` function to determine the maximum duration of a recording that can fit in a buffer of a certain size.

```
FUNCTION SPBBytesToMilliseconds (inRefNum: LongInt;
                                VAR byteCount: LongInt): OSErr;
```

<code>inRefNum</code>	The device reference number of the sound input device, as obtained from the <code>SPBOpenDevice</code> function.
<code>byteCount</code>	On entry, a value in bytes. On exit, the number of milliseconds of recording on the device specified by the <code>inRefNum</code> parameter that would be necessary to fill a buffer of such a size.

DESCRIPTION

The `SPBBytesToMilliseconds` function reports how many milliseconds of audio data can be recorded in a buffer that is `byteCount` bytes long, given the input device's current sample rate, sample size, number of channels, and compression factor.

SPECIAL CONSIDERATIONS

You can call the `SPBBytesToMilliseconds` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBBytesToMilliseconds` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$04440014</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siBadSoundInDevice</code>	-221	Invalid sound input device

Obtaining Information

The `SPBVersion` function allows you to determine the version of the Sound Input Manager.

SPBVersion

You can use the `SPBVersion` function to determine the version of the sound input tools available on a machine.

```
FUNCTION SPBVersion: NumVersion;
```

DESCRIPTION

The `SPBVersion` function returns a version number that contains the same information as in the first 4 bytes of a 'vers' resource or a `NumVersion` data type. For a description of the version record, see the chapter “Sound Manager” in this book.

SPECIAL CONSIDERATIONS

You can call the `SPBVersion` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SPBVersion` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$00000014</code>

SEE ALSO

For a complete discussion of 'vers' resources, see the chapter “Finder Interface” in *Inside Macintosh: Macintosh Toolbox Essentials*.

Application-Defined Routines

This section describes the routines that your application or device driver might need to define. Your application can define a sound input completion routine to perform an action when recording finishes, and your application can define a sound input interrupt routine to manipulate sound data during recording.

Sound Input Completion Routines

You can specify a sound input completion routine in the `completionRoutine` field of a sound input parameter block that your application uses to initiate asynchronous recording directly from a device.

MySICompletionRoutine

A sound input completion routine has the following syntax:

```
PROCEDURE MySICompletionRoutine (inParamPtr: SPBPtr);
```

`inParamPtr`

A pointer to the sound input parameter block that was used to initiate an asynchronous recording.

DESCRIPTION

The Sound Input Manager executes your sound input completion routine after recording terminates either because your application has called the `SPBStopRecording` function or because the prescribed limit is reached. The completion routine is called only for asynchronous recording.

A common use of a sound input completion routine is to set a global variable that alerts the application that it should dispose of a sound input parameter block that it had allocated for an asynchronous sound recording.

SPECIAL CONSIDERATIONS

Because a sound input completion routine is executed at interrupt time, it should not allocate, move, or purge memory (either directly or indirectly) and should not depend on the validity of handles to unlocked blocks.

If your sound input completion routine accesses your application's global variables, it must ensure that the A5 register contains the address of the boundary between the application global variables and the application parameters. Your application can pass the value of the A5 register to the sound input completion routine in the `userLong` field of the sound input parameter block. For more information on ensuring the validity of the A5 register, see the chapter "Memory Management Utilities" in *Inside Macintosh: Memory*.

Your sound input completion routine can determine whether an error occurred during recording by examining the `error` field of the sound input parameter block specified by `inParamPtr`. Your sound input completion routine can change the value of that field to alert the application that some other error has occurred.

ASSEMBLY-LANGUAGE INFORMATION

Because a sound input completion routine is called at interrupt time, it must preserve all registers other than A0–A1 and D0–D2.

RESULT CODES

<code>noErr</code>	0	No error
<code>abortErr</code>	-27	Asynchronous recording was cancelled
<code>siNoSoundInHardware</code>	-220	No sound input hardware available
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siNoBufferSpecified</code>	-222	No buffer specified
<code>siDeviceBusyErr</code>	-227	Sound input device is busy

Sound Input Interrupt Routines

You can specify a sound input interrupt routine in the `interruptRoutine` field of the sound input parameter block that your application uses to initiate asynchronous recording directly from a device. Because the `SPBRecordToFile` function uses sound input interrupt routines to enable it to record sound data to disk during recording, you can use sound input interrupt routines only with the `SPBRecord` function.

MySIInterruptRoutine

A sound input interrupt routine has the following syntax:

```
PROCEDURE MySIInterruptRoutine;
```

DESCRIPTION

A sound input device driver executes the sound input interrupt routine associated with an asynchronous sound recording whenever the driver's internal buffers are full. The internal buffers contain raw samples taken directly from the input device. The interrupt routine can thus modify the samples in the buffer in any way it requires. After your sound input interrupt routine finishes processing the data, the sound input device driver compresses the data (if compression is enabled) and copies the data into your application's buffer.

SPECIAL CONSIDERATIONS

If your sound input interrupt routine accesses your application's global variables, it must ensure that the A5 register contains the address of the boundary between the application global variables and the application parameters. Your application can pass the value of the A5 register to the sound input interrupt routine in the `userLong` field of the sound input parameter block. For more information on ensuring the validity of the A5 register, see the chapter "Memory Management Utilities" in *Inside Macintosh: Memory*.

ASSEMBLY-LANGUAGE INFORMATION

Sound input interrupt routines are sometimes written in assembly language to maximize real-time performance in recording sound. On entry, registers are set up as follows:

Registers on entry

A0	Address of the sound parameter block passed to <code>SPBRecord</code>
A1	Address of the start of the sample buffer
D0	Peak amplitude for sample buffer if metering is on
D1	Size of the sample buffer in bytes

If you write a sound input interrupt routine in a high-level language like Pascal or C, you might need to write inline code to copy variables from the registers into local variables that your application defines.

Because a sound input interrupt routine is called at interrupt time, it must preserve all registers.

Summary of the Sound Input Manager

Pascal Summary

Constants

```

CONST
  gestaltSoundAttr          = 'snd ';{sound attributes selector}

  {Gestalt response bit flags related to sound input}
  gestaltSoundIOMgrPresent  = 3;      {sound input routines available}
  gestaltBuiltInSoundInput  = 4;      {built-in input hw available}
  gestaltHasSoundInputDevice = 5;      {sound input device available}
  gestaltPlayAndRecord      = 6;      {built-in hw can play while recording}
  gestalt16BitSoundIO       = 7;      {built-in hw can handle 16-bit data}
  gestaltStereoInput        = 8;      {built-in hw can record stereo sounds}
  gestaltLineLevelInput     = 9;      {built-in input hw needs line level}

  {available information selectors for sound input device drivers}
  siActiveChannels          = 'chac';  {channels active}
  siActiveLevels            = 'lmac';  {levels active}
  siAGCOnOff                = 'agc ';  {automatic gain control state}
  siAsync                   = 'asyn';  {asynchronous capability}
  siChannelAvailable        = 'chav';  {number of channels available}
  siCompressionAvailable    = 'cmav';  {compression types available}
  siCompressionFactor       = 'cmfa';  {current compression factor}
  siCompressionHeader       = 'cmhd';  {return compression header}
  siCompressionNames        = 'cnam';  {return compression type names}
  siCompressionType         = 'comp';  {current compression type}
  siContinuous              = 'cont';  {continuous recording}
  siDeviceBufferInfo        = 'dbin';  {size of interrupt buffer}
  siDeviceConnected         = 'dcon';  {input device connection status}
  siDeviceIcon              = 'icon';  {input device icon}
  siDeviceName              = 'name';  {input device name}
  siInputGain               = 'gain';  {input gain level}
  siInputSource              = 'sour';  {input source selector}
  siInputSourceNames        = 'snam';  {input source names}
  siLevelMeterOnOff         = 'lmet';  {level meter state}
  siNumberChannels          = 'chan';  {current number of channels}

```

Sound Input Manager

```

siOptionsDialog      = 'optd';    {display options dialog box}
siPlayThruOnOff     = 'plth';    {play-through state}
siRecordingQuality   = 'qual';    {recording quality}
siSampleRate        = 'srat';    {current sample rate}
siSampleRateAvailable = 'srav';   {sample rates available}
siSampleSize        = 'ssiz';    {current sample size}
siSampleSizeAvailable = 'ssav';   {sample sizes available}
siStereoInputGain   = 'sgai';    {stereo input gain level}
siTwosComplementOnOff = 'twos';  {two's complement state}
siVoxRecordInfo     = 'voxr';    {VOX record parameters}
siVoxStopInfo       = 'voxs';    {VOX stop parameters}

{internal information selectors for sound input device drivers}
siCloseDriver       = 'clos';    {release driver}
siInitializeDriver  = 'init';    {initialize driver}
siPauseRecording    = 'paus';    {pause recording}
siUserInterruptProc = 'user';    {set sound input interrupt routine}

{sound-recording qualities}
siBestQuality       = 'best';    {the best quality available}
siBetterQuality     = 'betr';    {a quality better than good}
siGoodQuality       = 'good';    {a good quality}

{sound input device permissions}
siReadPermission    = 0;         {open device for reading}
siWritePermission   = 1;         {open device for reading/writing}

{device-connection states}
siDeviceIsConnected = 1;         {device is connected and ready}
siDeviceNotConnected = 0;        {device is not connected}
siDontKnowIfConnected = -1;      {can't tell if device is connected}

```

Data Types

Sound Input Parameter Block

```

TYPE SPB =
RECORD
    inRefNum:      LongInt;    {reference number of input device}
    count:        LongInt;    {number of bytes to record}
    milliseconds: LongInt;    {number of milliseconds to record}
    bufferLength: LongInt;    {length of buffer to record into}
    bufferPtr:    Ptr;        {pointer to buffer to record into}
    completionRoutine: ProcPtr; {pointer to a completion routine}

```

Sound Input Manager

```

interruptRoutine: ProcPtr;    {pointer to an interrupt routine}
userLong:         LongInt;    {for application's use}
error:           OSErr;      {error returned after recording}
unused1:         LongInt;    {reserved}
END;
SPBPtr = ^SPB;

```

Sound Input Manager Routines
Recording Sounds

```

FUNCTION SndRecord          (filterProc: ProcPtr; corner: Point;
                             quality: OSType; VAR sndHandle: Handle): OSErr;
FUNCTION SndRecordToFile   (filterProc: ProcPtr; corner: Point;
                             quality: OSType; fRefNum: Integer): OSErr;

```

Opening and Closing Sound Input Devices

```

FUNCTION SPBOpenDevice      (deviceName: Str255; permission: Integer;
                             VAR inRefNum: LongInt): OSErr;
FUNCTION SPBCloseDevice    (inRefNum: LongInt): OSErr;

```

Recording Sounds Directly From Sound Input Devices

```

FUNCTION SPBRecord         (inParamPtr: SPBPtr; asynchFlag: Boolean):
                             OSErr;
FUNCTION SPBRecordToFile   (fRefNum: Integer; inParamPtr: SPBPtr;
                             asynchFlag: Boolean): OSErr;
FUNCTION SPBPauseRecording (inRefNum: LongInt): OSErr;
FUNCTION SPBResumeRecording (inRefNum: LongInt): OSErr;
FUNCTION SPBStopRecording  (inRefNum: LongInt): OSErr;
FUNCTION SPBGetRecordingStatus
                             (inRefNum: LongInt;
                              VAR recordingStatus: Integer;
                              VAR meterLevel: Integer;
                              VAR totalSamplesToRecord: LongInt;
                              VAR numberOfSamplesRecorded: LongInt;
                              VAR totalMsecsToRecord: LongInt;
                              VAR numberOfMsecsRecorded: LongInt): OSErr;

```

Manipulating Device Settings

```

FUNCTION SPBGetDeviceInfo   (inRefNum: LongInt; infoType: OSType;
                             infoData: Ptr): OSErr;

```

Sound Input Manager

```
FUNCTION SPBSetDeviceInfo (inRefNum: LongInt; infoType: OSType;
                          infoData: Ptr): OSErr;
```

Constructing Sound Resource and File Headers

```
FUNCTION SetupSndHeader (sndHandle: Handle; numChannels: Integer;
                        sampleRate: Fixed; sampleSize: Integer;
                        compressionType: OSType;
                        baseFrequency: Integer; numBytes: LongInt;
                        VAR headerLen: Integer): OSErr;
```

```
FUNCTION SetupAIFFHeader (fRefNum: Integer; numChannels: Integer;
                          sampleRate: Fixed; sampleSize: Integer;
                          compressionType: OSType; numBytes: LongInt;
                          numFrames: LongInt): OSErr;
```

Registering Sound Input Devices

```
FUNCTION SPBSignInDevice (deviceRefNum: Integer; deviceName: Str255):
                          OSErr;
```

```
FUNCTION SPBGetIndexedDevice (count: Integer; VAR deviceName: Str255;
                              VAR deviceIconHandle: Handle): OSErr;
```

```
FUNCTION SPBSignOutDevice (deviceRefNum: Integer): OSErr;
```

Converting Between Milliseconds and Bytes

```
FUNCTION SPBMillisecondsToBytes (inRefNum: LongInt; VAR milliseconds: LongInt):
                                OSErr;
```

```
FUNCTION SPBBytesToMilliseconds (inRefNum: LongInt; VAR byteCount: LongInt):
                                OSErr;
```

Obtaining Information

```
FUNCTION SPBVersion : NumVersion;
```

Application-Defined Routines

```
PROCEDURE MySICompletionRoutine (inParamPtr: SPBPtr);
```

```
PROCEDURE MySIInterruptRoutine;
```

C Summary

Constants

```

#define gestaltSoundAttr    'snd ' /*sound attributes selector*/

enum {
    /*Gestalt response bit flags related to sound input*/
    gestaltSoundIOMgrPresent = 3, /*sound input routines available*/
    gestaltBuiltInSoundInput = 4, /*built-in input hw available*/
    gestaltHasSoundInputDevice = 5, /*sound input device available*/
    gestaltPlayAndRecord      = 6, /*built-in hw can play while recording*/
    gestalt16BitSoundIO       = 7, /*built-in hw can handle 16-bit data*/
    gestaltStereoInput        = 8, /*built-in hw can record stereo sounds*/
    gestaltLineLevelInput     = 9  /*built-in input hw needs line level*/
};

/*available information selectors for sound input device drivers*/
#define siActiveChannels      'chac' /*channels active*/
#define siActiveLevels       'lmac' /*levels active*/
#define siAGCOnOff          'agc ' /*automatic gain control state*/
#define siAsync              'asyn' /*asynchronous capability*/
#define siChannelAvailable   'chav' /*number of channels available*/
#define siCompressionAvailable 'cmav' /*compression types available*/
#define siCompressionFactor   'cmfa' /*current compression factor*/
#define siCompressionHeader   'cmhd' /*return compression header*/
#define siCompressionNames    'cnam' /*return compression type names*/
#define siCompressionType     'comp' /*current compression type*/
#define siContinuous         'cont' /*continuous recording*/
#define siDeviceBufferInfo    'dbin' /*size of interrupt buffer*/
#define siDeviceConnected     'dcon' /*input device connection status*/
#define siDeviceIcon         'icon' /*input device icon*/
#define siDeviceName         'name' /*input device name*/
#define siInputGain          'gain' /*input gain level*/
#define siInputSource         'sour' /*input source selector*/
#define siInputSourceNames    'snam' /*input source names*/
#define siLevelMeterOnOff     'lmet' /*level meter state*/
#define siNumberChannels      'chan' /*current number of channels*/
#define siOptionsDialog       'optd' /*display options dialog box*/
#define siPlayThruOnOff       'plth' /*play-through state*/
#define siRecordingQuality     'qual' /*recording quality*/
#define siSampleRate          'srat' /*current sample rate*/
#define siSampleRateAvailable 'srav' /*sample rates available*/

```

Sound Input Manager

```

#define siSampleSize      'ssiz' /*current sample size*/
#define siSampleSizeAvailable 'ssav' /*sample sizes available*/
#define siStereoInputGain  'sgai' /*stereo input gain level*/
#define siTwosComplementOnOff 'twos' /*two's complement state*/
#define siVoxRecordInfo    'voxr' /*VOX record parameters*/
#define siVoxStopInfo     'voxs' /*VOX stop parameters*/

/*internal information selectors for sound input device drivers*/
#define siCloseDriver      'clos' /*release driver*/
#define siInitializeDriver 'init' /*initialize driver*/
#define siPauseRecording   'paus' /*pause recording*/
#define siUserInterruptProc 'user' /*set sound input interrupt routine*/

/*sound-recording qualities*/
#define siBestQuality      'best' /*the best quality available*/
#define siBetterQuality    'betr' /*a quality better than good*/
#define siGoodQuality      'good' /*a good quality*/

/*sound input device permissions*/
enum {
    siReadPermission      = 0, /*open device for reading*/
    siWritePermission     = 1  /*open device for reading/writing*/
};

/*device-connection states*/
enum {
    siDeviceIsConnected   = 1, /*device is connected and ready*/
    siDeviceNotConnected   = 0, /*device is not connected*/
    siDontKnowIfConnected = -1 /*can't tell if device is connected*/
};

```

Data Types

Sound Input Parameter Block

```

struct SPB {
    long          inRefNum; /*reference number of input device*/
    unsigned long count; /*number of bytes to record*/
    unsigned long milliseconds; /*number of milliseconds to record*/
    unsigned long bufferLength; /*length of buffer to record into*/
    Ptr           bufferPtr; /*pointer to buffer to record into*/
    ProcPtr       completionRoutine;
                /*pointer to a completion routine*/
    ProcPtr       interruptRoutine;
};

```


Sound Input Manager

```

                                /*pointer to an interrupt routine*/
    long                userLong;    /*for application's use*/
    OSErr               error;       /*error returned after recording*/
    long                unused1;     /*reserved*/
};
typedef struct SPB SPB;
typedef SPB *SPBPtr;

```

Sound Input Manager Routines

Recording Sounds

```

pascal OSErr SndRecord      (ModalFilterProcPtr filterProc, Point corner,
                             OSType quality, Handle *sndHandle);
pascal OSErr SndRecordToFile
                             (ModalFilterProcPtr filterProc, Point corner,
                             OSType quality, short fRefNum);

```

Opening and Closing Sound Input Devices

```

pascal OSErr SPBOpenDevice  (ConstStr255Param deviceName, short permission,
                             long *inRefNum);
pascal OSErr SPBCloseDevice
                             (long inRefNum);

```

Recording Sounds Directly From Sound Input Devices

```

pascal OSErr SPBRecord      (SPBPtr inParamPtr, Boolean asynchFlag);
pascal OSErr SPBRecordToFile
                             (short fRefNum, SPBPtr inParamPtr,
                             Boolean asynchFlag);
pascal OSErr SPBPauseRecording
                             (long inRefNum);
pascal OSErr SPBResumeRecording
                             (long inRefNum);
pascal OSErr SPBStopRecording
                             (long inRefNum);
pascal OSErr SPBGetRecordingStatus
                             (long inRefNum, short *recordingStatus,
                             short *meterLevel,
                             unsigned long *totalSamplesToRecord,
                             unsigned long *numberOfSamplesRecorded,
                             unsigned long *totalMsecsToRecord,
                             unsigned long *numberOfMsecsRecorded);

```

Manipulating Device Settings

```
pascal OSErr SPBGetDeviceInfo
                                (long inRefNum, OSType infoType,
                                char *infoData);

pascal OSErr SPBSetDeviceInfo
                                (long inRefNum, OSType infoType,
                                char *infoData);
```

Constructing Sound Resource and File Headers

```
pascal OSErr SetupSndHeader
                                (Handle sndHandle, short numChannels,
                                Fixed sampleRate, short sampleSize,
                                OSType compressionType, short baseFrequency,
                                unsigned long numBytes, short *headerLen);

pascal OSErr SetupAIFFHeader
                                (short fRefNum, short numChannels,
                                Fixed sampleRate, short sampleSize,
                                OSType compressionType,
                                unsigned long numBytes,
                                unsigned long numFrames);
```

Registering Sound Input Devices

```
pascal OSErr SPBSignInDevice
                                (short deviceRefNum,
                                ConstStr255Param deviceName);

pascal OSErr SPBGetIndexedDevice
                                (short count, Str255 deviceName,
                                Handle *deviceIconHandle);

pascal OSErr SPBSignOutDevice
                                (short deviceRefNum);
```

Converting Between Milliseconds and Bytes

```
pascal OSErr SPBMillisecondsToBytes
                                (long inRefNum, long *milliseconds);

pascal OSErr SPBBytesToMilliseconds
                                (long inRefNum, long *byteCount);
```

Obtaining Information

```
pascal NumVersion SPBVersion
                                (void);
```

Application-Defined Routines

```
pascal void MySICompletionRoutine
                (SPBPtr inParamPtr);

pascal void MySIInterruptRoutine
                (void);
```

Assembly-Language Summary

Data Structures

Sound Input Parameter Block Data Structure

0	inRefNum	long	The input device reference number
4	count	long	The number of bytes to record
8	milliseconds	long	The number of milliseconds to record
12	bufferLength	long	The length of the buffer
16	bufferPtr	long	The address of the buffer
20	completionRoutine	long	A pointer to a completion routine
24	interruptRoutine	long	A pointer to an interrupt routine
28	userLong	long	For application's use
32	error	word	The error value returned after recording
36	unused1	long	Reserved

Trap Macros

Trap Macros Requiring Routine Selectors`_SoundDispatch`

Selector	Routine
\$00000014	SPBVersion
\$01100014	SPBSignInDevice
\$021C0014	SPBCloseDevice
\$02280014	SPBPauseRecording
\$022C0014	SPBResumeRecording
\$02300014	SPBStopRecording
\$030C0014	SPBSignInDevice
\$03200014	SPBRecord
\$04240014	SPBRecordToFile
\$04400014	SPBMillisecondsToBytes
\$04440014	SPBBytesToMilliseconds
\$05140014	SPBGetIndexedDevice
\$05180014	SPBOpenDevice
\$06380014	SPBGetDeviceInfo
\$063C0014	SPBSetDeviceInfo
\$07080014	SndRecordToFile
\$08040014	SndRecord
\$0B4C0014	SetupAIFFHeader
\$0D480014	SetupSndHeader
\$0E340014	SPBGetRecordingStatus

Result Codes

<code>noErr</code>	0	No error
<code>abortErr</code>	-27	Asynchronous recording was cancelled
<code>permErr</code>	-54	Attempt to open locked file for writing
<code>userCanceledErr</code>	-128	User canceled the operation
<code>siNoSoundInHardware</code>	-220	No sound input hardware available
<code>siBadSoundInDevice</code>	-221	Invalid sound input device
<code>siNoBufferSpecified</code>	-222	No buffer specified
<code>siInvalidCompression</code>	-223	Invalid compression type
<code>siHardDriveTooSlow</code>	-224	Hard drive too slow to record
<code>siInvalidSampleRate</code>	-225	Invalid sample rate
<code>siInvalidSampleSize</code>	-226	Invalid sample size
<code>siDeviceBusyErr</code>	-227	Sound input device is busy
<code>siBadDeviceName</code>	-228	Invalid device name

Sound Input Manager

siBadRefNum	-229	Invalid reference number
siInputDeviceErr	-230	Input device hardware failure
siUnknownInfoType	-231	Unknown type of information
siUnknownQuality	-232	Unknown quality

Speech Manager

Contents

About the Speech Manager	4-4
Voices	4-5
Speech Attributes	4-6
Speech Channels	4-9
Callback Routines	4-10
Using the Speech Manager	4-11
Checking for Speech Manager Capabilities	4-12
Creating, Using, and Disposing of a Speech Channel	4-13
Working With Different Voices	4-14
Adjusting Speech Attributes	4-16
Pausing Speech	4-18
Implementing Callback Procedures	4-19
Writing Embedded Speech Commands	4-23
Embedded Command Delimiters	4-23
Syntax of Embedded Speech Commands	4-24
Examples of Embedded Speech Commands	4-30
Phonemic Representation of Speech	4-32
Phonemic Symbols	4-33
Prosodic Control Symbols	4-34
Including Pronunciation Dictionaries	4-36
Speech Manager Reference	4-39
Constants	4-39
Speech Information Selectors	4-39
Data Structures	4-45
Voice Specification Records	4-46
Voice Description Records	4-47
Voice File Information Records	4-48
Speech Status Information Records	4-48
Speech Error Information Records	4-49
Speech Version Information Records	4-50

Phoneme Information Records	4-52
Phoneme Descriptor Records	4-53
Speech Extension Data Records	4-53
Delimiter Information Records	4-54
Speech Manager Routines	4-54
Starting, Stopping, and Pausing Speech	4-55
Obtaining Information About Voices	4-63
Managing Speech Channels	4-69
Obtaining Information About Speech	4-71
Changing Speech Attributes	4-73
Converting Text To Phonemes	4-79
Installing a Pronunciation Dictionary	4-80
Application-Defined Routines	4-82
Text-Done Callback Procedure	4-82
Speech-Done Callback Procedure	4-84
Synchronization Callback Procedure	4-85
Error Callback Procedure	4-86
Phoneme Callback Procedure	4-87
Word Callback Procedure	4-88
Resources	4-89
The Pronunciation Dictionary Resource	4-89
Summary of the Speech Manager	4-94
Pascal Summary	4-94
Constants	4-94
Data Structures	4-95
Speech Manager Routines	4-98
Application-Defined Routines	4-100
C Summary	4-100
Constants	4-100
Data Types	4-102
Speech Manager Routines	4-105
Application-Defined Routines	4-106
Assembly-Language Information	4-107
Data Structures	4-107
Trap Macros	4-109
Result Codes	4-110

Speech Manager

This chapter describes the Speech Manager, the part of the Macintosh system software that provides a standardized method for Macintosh applications to generate synthesized speech.

You need to read this chapter if you want your application to be able to generate speech. For example, you may want your application to incorporate the capability to speak its dialog box messages to the user. A word-processing application might use the Speech Manager to implement a command that speaks a selected section of a document to the user. A multimedia application might use the Speech Manager to provide a narration of a QuickTime movie instead of including sampled-sound data on a movie track. Because sound samples can take up large amounts of room on disk, using text in place of sampled sound is extremely efficient.

If you are developing an application that needs only to generate speech from strings, then the information on speech contained in the chapter “Introduction to Sound on the Macintosh” in this book might be sufficient. If, however, you need to be able to manipulate the speech output or customize it to make it easier for your users to understand, you should read this chapter.

The Speech Manager is not available in all system software versions. It was introduced with the Macintosh computers with audio visual capabilities in the summer of 1993. It will continue to be incorporated into future versions of system software. You should use the `Gestalt` function to ensure that the speech services you need are available before calling them. See the discussion in the section “Checking for Speech Manager Capabilities” beginning on page 4-12 for details.

The Speech Manager and the Sound Manager adopt many of the same metaphors in the processes of sound production and speech generation. You should be aware that the Speech Manager’s approach often differs in subtle but important ways from that of the Sound Manager. Reading the chapter “Sound Manager” in this book might help you to learn to use the Speech Manager, but it is not required.

Also, while the Speech Manager uses the Sound Manager, your application should not attempt to directly access any Sound Manager data structures used by the Speech Manager. Because the Speech Manager is likely to be a rapidly evolving portion of system software, relying on Speech Manager data structures not explicitly documented in this chapter is likely to pose compatibility problems for your application.

This chapter begins with an introduction to the speech generation process and then discusses how you can

- check for the availability of the Speech Manager
- create and dispose of speech channels
- generate speech with different voices
- obtain information about and change speech channel settings
- start and stop speech production
- synchronize speech production with other activities by using callback procedures
- embed Speech Manager commands within text to make it more understandable

Speech Manager


- convert text into phonemes and allow the user to enter phonetic text directly
- create, install, and manipulate customized pronunciation dictionaries

About the Speech Manager

You can use the Speech Manager to incorporate synthesized speech into your application. This section provides an overview and describes the basic concepts of the Speech Manager, and it outlines the process that the Speech Manager uses to convert text into speech. The Speech Manager converts text into sound data, which it passes to the Sound Manager to play through the current sound output device. The Speech Manager's interaction with the Sound Manager is transparent to your application, so you don't need to be familiar with the Sound Manager to take advantage of the Speech Manager's capabilities.

Figure 4-1 illustrates the speech generation process. Your application can initiate speech generation by passing a string or a buffer of text to the Speech Manager. The Speech Manager is responsible for sending the text to a **speech synthesizer**, a component that contains executable code that manages all communication between the Speech Manager and the Sound Manager. A synthesizer is usually contained in a resource in a file within the System Folder. A synthesizer is like a speech engine. It uses built-in dictionaries and pronunciation rules to help determine how to pronounce text. You can provide custom pronunciation dictionaries as described in the section "Including Pronunciation Dictionaries" beginning on page 4-36.

Figure 4-1 The speech generation process



As Figure 4-1 suggests, the Speech Manager is simply a dispatch mechanism that allows your application to take advantage of the capabilities of whatever speech synthesizers, voices, and hardware are installed. The Speech Manager itself does not do any of the work of converting text into speech; it just provides a convenient programming interface that manages access to speech synthesizers and, indirectly, to the sound hardware. The


Speech Manager

Speech Manager uses the Component Manager to access whatever speech synthesizers are available and allows applications to take maximum advantage of a computer's speech facilities without knowing what those facilities are. Because the Speech Manager's routines work on all voices and synthesizers, you will not need to rewrite your application to take advantage of improvements in speech technology.

Voices

Your application can use the system default voice to generate speech or it can specify that the Speech Manager use a particular voice that is available on the current computer system. A **voice** is a set of characteristics defined in parameters that specify a particular quality of speech. Just as different people's voices have different tonal qualities, so too can different voices have different qualities. A synthesized voice might sound male or female and might sound like an adult or a child. Some voices sound distinctively synthetic, while others sound more like real people. Figure 4-2 shows how the Speech Manager uses speech channels to synthesize speech with different voices.

Figure 4-2 The Speech Manager and multiple voices



As speech-synthesizing technology develops, the voices that your application can access are likely to sound more and more human. Each voice is designed to work with a particular speech synthesizer and can be customized in specific ways to create different effects.

Voices are usually stored in one of three places. The Speech Manager will first look in the application's resources file chain when attempting to locate a voice specification record. Then the Speech Manager will look in the System Folder and then the Extensions folder. Voices stored in the System Folder or Extensions folder are normally available to all

Speech Manager

applications. Voices stored in the resource fork of an application file are private to that application and will not work if the synthesizers they depend on are not installed on a user's system.

Most of the time, your application designates the voice that speaks text, and usually that is the default voice. Based on the needs of your users and the way in which you expect them to use voices in your application you can provide access to voices in a number of different ways. You could include access to selecting voices in a dialog box that is available from a menu item such as Voices... Any application that allows users to choose among voices requires additional information about the available voices beyond the information provided by a voice specification record (described in detail on page 4-46), whose data should never be presented to the user. Such additional information might include the name of the voice as well as what script and language it supports.

Applications can use the `GetVoiceDescription` function (described in detail on page 4-66) with a voice specification record to obtain such information in a voice description record (described in detail on page 4-47). You might provide access to voices through a control panel. For information about implementing control panels, see *Inside Macintosh: More Macintosh Toolbox*. Or, you could implement a voices menu in your application's main menu bar, if you think that users will want to change the voice often and you have the room available. It's not a good idea to implement a hierarchical Voices menu since hierarchical menus are harder to use. For more information about choosing a user interface for your application, see *Macintosh Human Interface Guidelines*.


Speech Attributes

Any given person has only one voice, but can alter the characteristics of his or her speech in a number of different ways. For example, a person can speak slowly or quickly and with a low or a high pitch. Similarly, the Speech Manager provides routines that allow you to modify these and other speech attributes, regardless of which voice is in use. A **speech attribute** is a setting defined for a class of voices or for all voices that affects the quality of speech produced by the Speech Manager. The Speech Manager provides routines to directly alter two speech attributes—speech rate and speech pitch. These routines are described in the section “Changing Speech Attributes” beginning on page 4-73. You can change two other speech attributes—pitch modulation and speech volume—by using the mechanism of speech information selectors, which is described in the section “Speech Information Selectors” beginning on page 4-39.

The **speech rate** of a speech channel is the approximate number of words of text that the synthesizer should say in one minute. Slower speech rates make the speech easier to understand, but can be annoyingly tedious to listen to. Some applications, such as aids for the visually impaired, require very fast speech rates. Speech rates are expressed as fixed-point values. Each speech synthesizer determines its own range of speech rates. The **speech pitch** of a speech channel represents the middle pitch of the voice, roughly corresponding to the key in which a song is played. It is a fixed-point value in the range of 0.000 through 127.000, where 60.000 corresponds to middle C on a conventional piano. Each 1.000-unit change in a value corresponds to a musical half step. This is the same scale used in specifying MIDI note values, as described in the chapter “Sound Manager”

in this book. Figure 4-3 shows a piano keyboard with the corresponding MIDI note values.

Figure 4-3 MIDI note values and corresponding piano keys



MIDI note values differ from speech pitch values in that they are always integral and have a wider range than speech pitch values. On the scale used to measure both MIDI note values and speech pitches, a change of +12 units corresponds to doubling the frequency (an increase of one octave), while a change of -12 units corresponds to halving the frequency (a decrease of one octave). A **frequency** is a precise indication of the number of hertz of a sound wave at any instant. If you need to convert between speech pitches and hertz, note that a speech pitch of 60.000 corresponds to 261.625 Hz. Meanwhile, when a speech pitch value rises by one unit, the corresponding hertz value is multiplied by the twelfth root of 2, defined by the Sound Manager constant `twelfthRootTwo`. The following formula thus converts a speech pitch into hertz:

$$\text{hertz} = \text{twelfthRootTwo}^{(\text{pitch} - 60.000)} * 261.625$$

In order to calculate speech pitch in terms of hertz, you can use the following formula:

$$\text{pitch} = 60 + (\ln(\text{hertz}) - \ln(261.625)) / \ln(\text{twelfthRootTwo})$$


Typical voice frequencies might range from around 90 hertz for a low-pitched male voice to about 300 hertz for a high-pitched child's voice. These frequencies correspond to approximate pitch values in the ranges of 30.000 to 40.000 and 55.000 to 65.000, respectively.

You can determine the current speech pitch on a speech channel by calling the `GetSpeechPitch` function, described on page 4-75. You can change the current pitch by calling the `SetSpeechPitch` function, described on page 4-76. You can also determine the current speech rate and change it by using the `GetSpeechRate` function, described on page 4-73 and the `SetSpeechRate` function, described on page 4-74. Changes in speech pitch and speech rate are effective immediately (as soon as the synthesizer can respond), even if they occur in the middle of a word.

Speech Manager

Pitch is the listener's subjective interpretation of speech's average frequency. The speech pitch specified is a baseline value corresponding to a particular frequency, from which the actual frequency of generated speech varies with the rises and falls of the intonation of speech. When a person speaks, there is a tune to the speech. Often you are more aware of the singsong quality, or change in the range of speech pitch, of a language that you don't know rather than one that you speak. The synthesizer must generate this tune in order to sound more human-like. Speech pitch is always described by a set of numbers that specify the range of pitch of the tune a synthesizer generates. This set of numbers can be the middle pitch and how far to deviate from that pitch or it can be the set of pitches within which the semi-tones of the tune can vary. Figure 4-4 shows an example of the range of pitches produced as the phrase "The cat sat on the mat." is spoken.

Figure 4-4 An example of pitch range for a voice



To simulate the variability in frequency of human speech, the Speech Manager defines the speech attribute of pitch modulation. The **pitch modulation** of a speech channel is the maximum amount by which the actual frequency of speech generated may deviate from the speech pitch.

Pitch modulation is also expressed as a fixed-point value in the range of 0.000 to 100.000. A pitch modulation value of 0.000 corresponds to a monotone in which all speech is generated at the frequency corresponding to the speech pitch. Speech generated at this pitch modulation would sound unnaturally robotic. Given a speech pitch value of 46.000, a pitch modulation of 2.000 would mean that the widest possible range of pitches corresponding to the actual frequency of generated text would be 44.000 to 48.000.

In some synthesizers, the actual pitch modulation may be restricted to a certain range. For example, if a synthesizer supported the full range of pitch modulations, a pitch modulation of 100.000 would result in unintelligible speech. In fact, however, some synthesizers, even with such a setting, produce speech that sounds virtually monotone. Even within a synthesizer, different voices might have different valid pitch modulation ranges. The Speech Manager provides no mechanism for obtaining the range of valid

pitch modulations, although some synthesizers may allow applications designed to work with those synthesizers to obtain such ranges.

You can obtain the pitch modulation by using the `GetSpeechInfo` function with the `soPitchMod` speech information selector, and you can change the pitch modulation by using the `SetSpeechInfo` function with the same selector. Speech information selectors are described in “Speech Information Selectors” beginning on page 4-39.

The **speech volume** of a speech channel is the average amplitude at which the channel generates speech. Volumes are expressed in fixed-point units ranging from 0.0 through 1.0. A value of 0.0 corresponds to silence, and a value of 1.0 corresponds to the maximum possible volume. Volume units lie on a scale that is linear with amplitude or voltage. A doubling of perceived loudness corresponds to a doubling of the volume.

Note that just as a speech synthesizer does not generate speech at a constant frequency, it does not generate speech at a constant amplitude. Even when the speech rate is high, brief pauses break up a steady stream of speech. The speech volume is, like speech pitch, an indicator of an average. There is no way to determine or change the modulation of speech volume.

A final speech attribute is **prosody**, the rhythm, modulation, and emphasis patterns of speech. There is no simple mechanism for your application to determine what rhythmic patterns a speech synthesizer is applying to speech. However, you can exert some control over prosody by using prosodic control symbols, discussed in “Prosodic Control Symbols” on page 4-34. Also, you can disable **ending prosody**, the modulation that distinguishes the end of a sentence or statement in normal speech, by using the `SpeakBuffer` function, described on page 4-57.

Speech Channels

To indicate to the Speech Manager which voice or attributes you would like it to use in generating speech, your application must use a speech channel. A **speech channel** is a data structure that the Speech Manager uses when processing text; it can be associated with a particular voice and particular speech attributes. Because multiple speech channels can coexist, your application can create several different vocal environments (to simulate a conversation, for example). Because a synthesizer can be associated with only one language and region, your application would need to create a separate speech channel to process each language in bilingual or multilingual text. (Currently, however, only English-producing synthesizers are available.)

Different speech channels can even generate speech simultaneously, subject to processor capabilities and Sound Manager limitations. This capability should be used with restraint, however, because it can be hard for the user to understand any speech when more than one channel is generating speech at a time. In general, your application should generate speech only at the specific request of the user and should allow the user to turn off speech output. At the very least, your application should include an option that allows the user to view text instead of hearing it. Some users might have trouble understanding speech generated by the Speech Manager, and others might have a

Speech Manager

hearing deficit. Even users who are able to clearly understand computer-synthesized speech might prefer to read rather than hear.

Using the Speech Manager, you can identify how many voices are available and sort through an index of the voices to get information about a specified voice such as its gender, age, or the synthesizer with which it is associated. In general, your application does not need to know which speech synthesizer it is using, and in most cases, you do not need to be concerned with which speech synthesizer a voice is associated. Sometimes, however, a speech synthesizer may provide special capabilities beyond that provided by the Speech Manager. For example, a speech synthesizer might allow you to select an option to speak numbers in a nonstandard way. The Speech Manager allows you to determine which synthesizer is associated with a voice for these circumstances and provides hooks that allow your application to take advantage of synthesizer-specific capabilities.

In general, your application can achieve the best results by not making assumptions about which synthesizers might be available. The user of a 2 MB Macintosh Classic might use a synthesizer with low RAM requirements, while the user of a 20 MB Macintosh Quadra 950 might take advantage of a synthesizer that provides better audio quality at the expense of memory usage. The Speech Manager makes it easy to accommodate both kinds of users. Currently there are three synthesizers available with the Speech Manager. Each synthesizer has its own RAM requirements. To be compatible with all three synthesizers, you must reserve enough space in your application's heap to accommodate their requirements. In general, reserving around 250 KB per channel that you anticipate using provides enough space for the MacinTalk Pro synthesizer.

Callback Routines

The Speech Manager allows you to implement callback routines. With callback routines, you can synchronize speech with other actions. You can use callback routines to obtain information about when a synthesizer has finished speaking a phoneme, reaches a word ending, or finishes speaking. Using this feature, you could highlight text as it is being spoken or synchronize the speech production with a QuickTime movie or animation of a mouth speaking.

You can also customize speech that your application generates with the Speech Manager by embedding commands in text strings stored in resources in your application or by programmatically embedding commands in commonly spoken text.

The next section of this chapter shows you how to implement the most commonly used features of the Speech Manager. It demonstrates how you use the `SpeakString` function to convert a text string into speech without allocating a speech channel, how you can customize speech, how you can obtain more control over speech by allocating speech channels, and how you can make speech easier to understand by embedding commands within text strings. It also shows how to install a custom dictionary to provide more accurate pronunciation of less common words such as names.

Using the Speech Manager

You can use the Speech Manager simply to convert Pascal-style strings into speech. This simple technique is described in the chapter “Introduction to Sound on the Macintosh” in this book. This section shows how you can take advantage of more features of the Speech Manager.

Before you can generate synthetic speech on a Macintosh computer, you need to make sure that the Speech Manager is installed. “Checking for Speech Manager Capabilities” beginning on page 4-12 shows how to check for the availability of the Speech Manager. It also demonstrates how to use the `SpeakString` function to generate synthesized speech in the most straightforward way.

To take advantage of most of the Speech Manager’s features, you must allocate a speech channel to pass to Speech Manager functions and dispose of the speech channel when you are finished using it. “Creating, Using, and Disposing of a Speech Channel” beginning on page 4-13 demonstrates how you do this and shows how you can use the `SpeakText` function to start speech generation from a buffer of text. Some applications permit users to choose a voice from those available to be used for speech generation. The `CountVoices`, `GetIndVoice`, and `GetVoiceDescription` functions support this capability. “Working With Different Voices” beginning on page 4-14 shows how you can use these functions to choose among available voices.

You can also use the `SpeakText` function to customize some attributes of speech generation. “Adjusting Speech Attributes” beginning on page 4-16 shows how you can do this. When you start synthesizing speech, you may need a way to stop speech from being generated. You can use the `StopSpeech` function to stop speech immediately, or you can use the `StopSpeechAt` function to choose exactly where you want speech stopped. You can stop speech temporarily and then resume it again using the `PauseSpeechAt` and `ContinueSpeech` functions. “Pausing Speech” beginning on page 4-18 shows how to pause or stop speech production and begin it again.

You might need to synchronize speech generation with other activities. For example, your application might include an on screen animation that must be synchronized with speech generation, or your application might need to determine when the Speech Manager has finished processing text on a speech channel so that it can unlock a handle or release some memory. “Implementing Callback Procedures” beginning on page 4-19 shows how you can accomplish these goals.

If your application uses embedded speech commands to obtain exacting control over speech generation, you should read “Writing Embedded Speech Commands” beginning on page 4-23. This section describes the complete syntax of embedded commands, and provides a guide to all embedded commands supported by the Speech Manager.

The Speech Manager allows you to enter phonemic text directly. If your application speaks only text that the user writes, this feature is unlikely to be useful to you, because you cannot anticipate what the user might enter. However, if there are a few or many sentences that your application frequently converts into speech, it might be useful to

Speech Manager

represent parts of these sentences phonemically rather than textually. “Phonemic Representation of Speech” beginning on page 4-32 describes how to convert text to phonemes.

Some applications might allow the user to use pronunciation dictionaries to override the default pronunciations of certain words. “Including Pronunciation Dictionaries” beginning on page 4-36 explains how you can create a new pronunciation dictionary resource or install an existing pronunciation dictionary resource into a speech channel. The section also explains how you can provide the user with the default phonemic pronunciation of text by using the `TextToPhonemes` function.

Checking for Speech Manager Capabilities

Because the Speech Manager is not available in all system software versions, you should always check for speech capabilities before attempting to use them. Listing 4-1 defines a function that determines whether the Speech Manager is available.

Listing 4-1 Checking for speech generation capabilities

```

FUNCTION MySpeechMgrPresent: OSErr;
VAR
    myErr:      OSErr;
    myFeature:  LongInt;           {feature being tested}
BEGIN
    {Test Speech Manager present bit.}
    myerr := Gestalt(gestaltSpeechAttr, myFeature);
    IF (myErr = noErr) AND (BTst(myFeature, gestaltSpeechMgrPresent)) THEN
    BEGIN
        myErr := SpeakString('The Speech Manager is working and');
        {Wait until synthesizer is done speaking.}
        WHILE (SpeechBusy <> 0) DO
        BEGIN
            {do nothing}
        END;

        myErr := SpeakString('is almost done. ');
        {Wait until synthesizer is done speaking.}
        WHILE (SpeechBusy <> 0) DO
        BEGIN
            {do nothing}
        END;
        MySpeechMgrPresent := myErr;
    END;
END;

```

The `MySpeechMgrPresent` function defined in Listing 4-1 uses the `Gestalt` function to determine whether the Speech Manager is available. The `MySpeechMgrPresent`

Speech Manager

function tests the `gestaltSpeechMgrPresent` bit, and, if the Speech Manager is present, the `MySpeechMgrPresent` function speaks the string passed to the `SpeakString` function. If the `Gestalt` function cannot obtain the desired information and returns a result code other than `noErr`, the `MySpeechMgrPresent` function assumes that the Speech Manager is not available.

The `SpeakString` function uses an implied speech channel, that is, the speech channel is automatically created and disposed of by the Speech Manager. The `SpeakString` function is useful when you need to synthesize Pascal-style strings of fewer than 256 characters. If you need to process text that is longer than 255 characters, then you must allocate a speech channel and use one of the routines that can generate speech in a channel such as the `SpeakText` or `SpeakBuffer` function. These routines are much more flexible in that they allow you to speak more text, customize the speech using speech selectors, or alter the generated speech by changing its modulation, pitch, rate, or voice.

Creating, Using, and Disposing of a Speech Channel

To take advantage of most of the Speech Manager's capabilities, you must pass a speech channel to Speech Manager functions. You use the `NewSpeechChannel` function to create a speech channel. After you are done using a speech channel, you must dispose of it by using the `DisposeSpeechChannel` function. Listing 4-2 shows how to create a speech channel, start speaking text with the `SpeakText` function, stop speaking text with the `StopSpeech` function, and then dispose of the speech channel when the speaking is finished.

Listing 4-2 Speaking text with a speech channel

```
FUNCTION MyUseSpeechChannel: OSErr;
VAR
    myErr:    OSErr;
    myErr2:  OSErr;
    myStr:    Str255;           {text to be spoken}
BEGIN
    myStr := 'Hold the mouse button down to stop speech.';
    myErr := NewSpeechChannel(NIL, gChannel);   {create the channel}
    IF (myErr = noErr) THEN
        BEGIN                               {speak the string}
            myErr := SpeakText(gChannel, @myStr[1], Length(myStr));
            WHILE (SpeechBusy <> 0) DO       {wait until speaking is done}
                BEGIN
                    IF (Button) THEN
                        myErr := StopSpeech(gChannel);   {stop speech at mouse down}
                END;
            IF (gChannel <> NIL) THEN
```

Speech Manager

```

    myErr2 := DisposeSpeechChannel(gChannel);{get rid of channel}
END;
IF (myErr = noErr) THEN
    MyUseSpeechChannel := myErr2
ELSE
    MyUseSpeechChannel := myErr;
END;

```

The `MyUseSpeechChannel` function defined in Listing 4-2 creates a default speech channel using the default system voice. You pass `NIL` in the first parameter to use the system default voice. You must also pass a global variable to `NewSpeechChannel` in which is returned a valid speech channel. Once the channel exists, then you can use the `SpeakText` function to generate speech. To generate synthesized speech, you pass in the channel allocated by `NewSpeechChannel` in the first parameter, and then you pass a pointer to the text that you want to speak as well as the length of the text that you want the Speech Manager to attempt to speak. That is, you can pass a pointer to a buffer of text that is 500 bytes long, but specify that only the first 10 bytes get spoken. Then `MyUseSpeechChannel` uses the `SpeechBusy` function in a `WHILE` loop to allow the text to be completely spoken before disposing of the channel.

When the designated action to stop the speaking occurs, which in this example is the user pressing the mouse button, `MyUseSpeechChannel` halts speech production. In this case, the `StopSpeech` function stops the speech immediately (as soon as the synthesizer can). You need to pass `StopSpeech` the variable that identifies the channel on which the speech is currently being synthesized. If you want to have more control over when the speech is stopped, you can use the `StopSpeechAt` function, which allows you to stop speech immediately, at the end of a word, or at the end of a sentence. See the description of the `StopSpeechAt` function on page 4-60 for more information.

Once you are done using the speech channel that was created with `NewSpeechChannel`, you must dispose of it. The `MyUseSpeechChannel` function calls `DisposeSpeechChannel` with the global variable that identifies the channel currently in use.

Working With Different Voices

When you work with speech channels, you can set a voice for a particular channel. When you set a voice, you may want to filter out certain of its characteristics in order to identify the one you want. For example, in an educational software application for elementary school students, you may want to use only children's voices. In order to choose the voice you want, you get a **voice description record** that contains information about a voice such as the size of the voice, the name of the voice, the age and gender of the voice, and the synthesizer with which it works. You can get the number of available voices using the `CountVoices` function. You can cycle through the available voices and identify the one you want to use by using the `GetIndVoice` function. Then you fill out a voice description record using the `GetVoiceDescription` function. Listing 4-3 shows how to get identifying information about a voice.

Listing 4-3 Getting a description of a voice

```

FUNCTION MyInstallBoysVoice: OSErr;
VAR
    myErr:          OSErr;
    myIndex:        Integer;
    myNumVoices:    Integer;
    myVoice:        VoiceSpec;
    myFound:        VoiceSpec;
    myInfo:         VoiceDescription;
BEGIN
    myFound := NIL;
    myErr := CountVoices(myNumVoices);           {count voices}
    IF myErr = noErr THEN
        BEGIN
            FOR myIndex := 0 to myNumVoices DO   {loop through all voices}
                BEGIN
                    myErr := GetIndVoice(myIndex, @myVoice);
                    IF myErr = noErr THEN
                        BEGIN
                            myErr := GetVoiceDescription(@myVoice, @myInfo, sizeof(myInfo));
                            IF myErr = noErr THEN           {check if a boy's voice}
                                IF (myVoice.age < 16) AND (myVoice.gender = kMale) THEN
                                    myFound := myVoice;
                                END;
                            END; {FOR}
                        IF myFound <> NIL THEN           {install boy's voice}
                            myErr := NewSpeechChannel(@myFound, gChannel);
                        END;
                    MyInstallBoysVoice := myErr;       {return result code}
                END;
            END;
        END;
    END;
END;

```

The `MyGetVoiceInfo` function checks to see how many voices are available. Once you have identified the list of available voices, you can index through the voices to select one about which you want to get information. You pass the number of the voice index in the first parameter of the `GetIndVoice` function. (This number cannot be larger than the number of voices.) `GetIndVoice` returns a **voice specification record** in the location specified in the second parameter—in this case, in the location of the pointer `@myVoice`. This sample cycles through the available voices looking for a male child's voice.

The voice specification record contains two identifiers: the creator identification of the required synthesizer and the voice identification of the voice. In order to get specific information about the voice you want to use, you need to call the `GetVoiceDescription` function. You need to pass a pointer to the voice specification record in the first parameter of the `GetVoiceDescription` function.

Speech Manager

`GetVoiceDescription` returns the voice description record in the location pointed to in the second parameter, `@info`. The voice description record contains information about the voice such as its age or gender.

To specify which voice you want to use, you pass a pointer to the voice specification record as the first parameter to `NewSpeechChannel`. In this case, when the male child's voice is identified, it's voice specification record is passed to `NewSpeechChannel`, which allocates a channel with the specified voice. Note that this sample code contains limited error checking.

Adjusting Speech Attributes

Speech attributes are settings defined for a class of voices or for all voices that affect the quality of speech produced by the Speech Manager. In general, an application should not try to second-guess the developers of a voice or synthesizer by arbitrarily setting a speech attribute. However, there are some cases in which you would want to adjust the rate of speech (how many words per minute are spoken) or the speech pitch (the listener's subjective interpretation of speech's average frequency). Listing 4-4 shows how to adjust the speech pitch and speech rate of a particular channel.

Listing 4-4 Changing the speech rate and pitch

```

FUNCTION MyAdjustSpeechAttributes: OSErr;
VAR
    myErr:      OSErr;
    myErr2:     OSErr;
    myPitch:    Fixed;
    myRate:     Fixed;
    myStr:      Str255;
BEGIN
    myStr := 'This is the old pitch and rate.';
    myErr := NewSpeechChannel(NIL, gChannel);    {allocate a channel}
    IF myErr = noErr THEN
        BEGIN                                {speak a string}
            myErr := SpeakText(gChannel, @myStr[1], Length(myStr));
            WHILE (SpeechBusy <> 0) DO        {wait for speech to finish}
                BEGIN
                    END;
                {Find the current speech pitch.}
            myErr := GetSpeechPitch(gChannel, @myPitch);
            myPitch := myPitch * 2;           {double the pitch}
            IF myErr = noErr THEN
                myErr := SetSpeechPitch(gChannel, myPitch); {change the pitch}
        END;
    END;
END;

```

Speech Manager

```

{Find the current speech rate.}
IF myErr = noErr THEN
    myErr := GetSpeechRate(gChannel, @myRate);
myRate := myRate * 2;           {double the rate}
IF myErr = noErr THEN
    myErr := SetSpeechRate(gChannel, myRate);   {change the rate}
{Speak a string with new attributes.}
myStr := 'This is the new pitch and rate.';
myErr := SpeakText(gChannel, @myStr[1], Length(myStr));
WHILE (SpeechBusy <> 0) DO      {wait for speech to finish}
BEGIN
END;
{Dispose of the speech channel.}
IF gChannel <> NIL THEN
    myErr2 := DisposeSpeechChannel(gChannel);
END;
IF myErr = noErr THEN
    MyAdjustSpeechAttributes := myErr2
ELSE
    MyAdjustSpeechAttributes := myErr;
END;

```

The `MyAdjustSpeechAttributes` function first allocates a speech channel, as demonstrated previously. Then the `MyAdjustSpeechAttributes` function speaks a string to demonstrate the default speech rate and pitch for the default system voice. After the speech synthesis is finished, `MyAdjustSpeechAttributes` calls the `GetSpeechPitch` function with a valid speech channel and a pointer to a fixed-point value in which the value of the current speech pitch is returned. Then `MyAdjustSpeechAttributes` doubles the value of the speech pitch by multiplying and passes the new value to the `SetSpeechPitch` function.

`MyAdjustSpeechAttributes` repeats this sequence to determine the speech rate using the `GetSpeechRate` function, doubles the rate, and sets a new speech rate by passing the new rate value to the `SetSpeechRate` function. Next, `MyAdjustSpeechAttributes` calls `SpeakText` again to demonstrate the new speech pitch and rate. Creating a loop with the `SpeechBusy` function allows the synthesizer to finish speaking its text, and then `MyAdjustSpeechAttributes` disposes of the active channel.

When you set a rate value, each synthesizer may or may not be able to support that exact value. A synthesizer will attempt to set the value you specify, but it may substitute a value that it can support that is the closest it can come to your value. Don't be alarmed if `GetSpeechRate` returns a value other than the one you thought you set. The value returned is the closest value to the one set that the synthesizer is capable of reproducing.

Pausing Speech

When you start synthesizing speech, you may need a way to stop speech that is being generated. For example, your application might support a Stop Speech menu command to let users stop speech when they want to. Also, you should usually stop speech when you receive a suspend event. You can use `StopSpeech` to stop speech immediately, or you can use `StopSpeechAt` to choose exactly where you want speech stopped. You can also stop speech temporarily and then resume it again using the `PauseSpeechAt` and `ContinueSpeech` functions. Listing 4-5 shows how you might do this.

Listing 4-5 Pausing and continuing speech production

```

FUNCTION MyPauseAndContinueSpeech: OSErr;
VAR
    myErr, myErr2:    OSErr;
    myStr:           Str255;
BEGIN
    gChannel := NIL;
    myStr := 'Hold the mouse button down to test pause speech at immediate.';
    myErr := NewSpeechChannel(NIL, gChannel);    {open speech channel}
    IF myErr = noErr THEN
        BEGIN
            {speak some text}
            myErr := SpeakText(gChannel, @myStr[1], Length(myStr));
            WHILE (SpeechBusy <> 0) DO          {wait for speech to finish}
                IF (Button) THEN
                    BEGIN
                        {stop speech immediately}
                        myErr := PauseSpeechAt(gChannel, kImmediate);
                        IF myErr = noErr THEN
                            WHILE (Button) DO    {while mouse button is down, do nothing}
                                BEGIN
                                    END;          {on mouse up, resume speaking}
                                myErr := ContinueSpeech(gChannel);
                            END;
                        IF gChannel <> NIL THEN    {dispose of channel}
                            myErr2 := DisposeSpeechChannel(gChannel);
                        END;
                    IF myErr = noErr THEN
                        MyPauseAndContinueSpeech := myErr2
                    ELSE
                        MyPauseAndContinueSpeech := myErr;
                END;
            END;
        END;
    END;

```

The `MyPauseAndContinueSpeech` function defined in Listing 4-5 begins by allocating a speech channel using the default system voice. It then begins to speak some text.

Speech Manager

`MyPauseAndContinueSpeech` uses a busy loop to allow the speech to be completely spoken before finishing the subroutine. Then, when the designated action occurs, in this case the mouse button being depressed by a user, `MyPauseAndContinueSpeech` calls `PauseSpeechAt` with the currently active channel and a constant that defines where to stop the speech. This example uses the constant `kImmediate` to indicate that the speech should cease wherever it is currently being processed by the synthesizer. There are also constants that define the end of a word and the end of a sentence as appropriate stopping places.

When the mouse button is released, `MyPauseAndContinueSpeech` calls the `ContinueSpeech` function with the variable identifying the paused speech channel. When paused immediately, the synthesizer resumes speaking at the beginning of the word that was interrupted. While the speech is being generated, `MyPauseAndContinueSpeech` continues to call `SpeechBusy` to determine if the channel is still being used to process speech. When the channel is no longer busy, `MyPauseAndContinueSpeech` calls `DisposeSpeechChannel` to release the memory used by the speech channel.

Implementing Callback Procedures

The Speech Manager makes it easy for you to synchronize other activities to speech generation by allowing you to install various types of callback procedures on a speech channel. A **callback procedure** is a procedure that executes whenever a certain type of event is about to occur or has occurred. For example, you might use a word callback procedure to ensure that whenever the Speech Manager is about to speak a word, the word is visible onscreen. Callback procedures also allow you to synchronize more mundane activities with the Speech Manager; for example, you might need to know when you can dispose of a certain text buffer that you had asked the Speech Manager to speak. This section provides an overview of the different callback procedures that you can define.

The `soTextDoneCallback` and `soSpeechDoneCallback` speech information selectors allow you to designate text-done and speech-done callback procedures. A **text-done callback procedure** executes whenever the Speech Manager finishes processing a buffer of text to be spoken. This procedure usually executes before the Speech Manager has finished generating speech from the text and indeed often before it has started. The text-done callback procedure provides a mechanism that allows you to specify to the Speech Manager an additional buffer of text to be spoken, so that speech is generated continuously. Once your text-done callback procedure executes, you can release the memory occupied by the text buffer processed. A **speech-done callback procedure** does not execute until after the Speech Manager has completed generating speech from a buffer of text.

If your application uses or supports embedded speech commands, it may need to use the `soSyncCallback` and `soErrorCallback` speech information selectors to designate a synchronization callback procedure or an error callback procedure. A **synchronization callback procedure** executes whenever the Speech Manager encounters a synchronization command embedded within a text buffer to be spoken.

Speech Manager

An **error callback procedure** executes whenever the Speech Manager encounters an error when attempting to process an embedded speech command. The Speech Manager passes information about the synchronization message or type of error to your callback procedure. If your application does not use synchronization or error callback procedures, it can obtain information about synchronization or error messages by continually polling the speech channel by using the `GetSpeechInfo` function with the `soErrors` or `soRecentSync` selectors.

The `soPhonemeCallback` and `soWordCallback` speech information selectors allow you to designate a phoneme callback procedure and a word callback procedure, respectively. A **phoneme callback procedure** executes whenever a phoneme is about to be spoken on a speech channel. A **word callback procedure** executes whenever a word is about to be spoken on a speech channel.

Since callback procedures execute at interrupt time they face several restrictions, as discussed in detail in *Inside Macintosh: Processes*. Most significantly, your callback procedure must not allocate or move memory or call any Toolbox or Operating System routine that might do so. Thus, typically a callback procedure simply sets a flag variable; for example, a phoneme callback procedure might change a variable that indicates which phoneme is being spoken. Your application can then poll this flag variable each time through its main event loop and perform whatever activity is desired if it finds that the flag variable has changed. Remember to design callback procedures to execute quickly.

Because they execute at interrupt time, callback procedures also cannot access application global variables unless the A5 register contains the value of the application's A5, as discussed in *Inside Macintosh: Memory*. Fortunately, the Speech Manager provides a mechanism that makes it easy to ensure that A5 is set correctly. Your application can call the `SetSpeechInfo` function with the `soCurrentA5` selector to pass the application's A5 in the `speechInfo` parameter to the Speech Manager. The Speech Manager will then set the A5 register to the passed value whenever it executes an application-defined callback procedure for that speech channel.

Sometimes your application might wish to provide a callback procedure with additional information beyond that which can be provided by examining application global variables. For example, a callback procedure might need to know from which document speech is being generated. Your application can use the `SetSpeechInfo` function with the `soRefCon` selector to specify a 4-byte reference constant value—for example, a handle to a document record—that the Speech Manager passes to all callback procedures on a particular speech channel. Your application can use the same callback procedure on multiple speech channels, for each of which the Speech Manager can pass a different value to the callback procedure. Thus, as long as your application never uses a single speech channel to generate speech on multiple documents simultaneously, it can use the reference constant value mechanism to pass document-specific information to a callback procedure. Typically, you use the reference constant to contain a pointer or handle to more extensive information that the callback procedure would require.

Listing 4-6 shows how you can indicate to the Speech Manager both the value to which it should set the A5 register when it executes a callback procedure on a particular speech channel and the reference constant value to pass to that callback procedure.

Listing 4-6 Setting up a speech channel for callbacks

```

FUNCTION MySetupCallbacks (chan: SpeechChannel; refCon: LongInt): OSErr;
VAR
    myA5:      LongInt;          {application's A5}
    myErr:     OSErr;
BEGIN
    myA5 := SetCurrentA5;        {get application's A5}

    {Pass A5 value to speech channel.}
    myErr := SetSpeechInfo(chan, soCurrentA5, Ptr(myA5));
    IF myErr = noErr THEN      {set the reference constant}
        myErr := SetSpeechInfo(chan, soRefCon, Ptr(refCon));

    MySetupCallbacks := myErr;
END;

```

The `MySetupCallbacks` function defined in Listing 4-6 uses the `SetSpeechInfo` function with both the `soCurrentA5` and the `soRefCon` selectors to prepare a specific speech channel for callbacks. Note that your application can call `MySetupCallbacks` as many times as desired for any particular speech channel; you might do this if you want to change the reference constant value to be passed to the speech channel.

Unlike other selectors, the `soCurrentA5` and `soRefCon` selectors do not require that you pass a pointer to the information you are specifying in the `speechInfo` parameter. Because an application's A5 value and a speech channel's reference constant value are always each 4 bytes long (the same size as the `speechInfo` parameter), your application passes these values directly, casting them to pointer values.

After your application sets up the A5 register and defines a reference constant value, it can install the appropriate type or types of callback procedure. Listing 4-7 shows how you might install a word callback procedure.

Listing 4-7 Installing a word callback procedure

```

PROCEDURE MyInstallWordCallback (chan: SpeechChannel; callbackProc: ProcPtr;
                                refCon: LongInt);
VAR
    myErr:     OSErr;
BEGIN
    myErr := MySetupCallbacks(chan, refCon);    {set up callbacks}
    myErr := SetSpeechInfo(chan, soWordCallBack, callbackProc);
    IF myErr <> noErr THEN
        DoError(myErr);                        {respond to an error}
END;

```

Speech Manager

The `MyInstallWordCallback` procedure defined in Listing 4-7 first prepares for callbacks by calling the `MySetupCallbacks` function defined in Listing 4-6 for the speech channel and reference constant value specified by the `chan` and `refCon` parameters, respectively. Then it installs the callback procedure specified by the `callbackProc` parameter by using the `SetSpeechInfo` function with the `soWordCallBack` speech information selector. If, for example, you want to pass to your word callback procedure a pointer to the window containing the document being used for speech generation, you might call the `MyInstallWordCallback` procedure like this:

```
MyInstallWordCallback(mySpeechChan, @MyWordCallBack, LongInt(myWindow));
```

Listing 4-8 defines a simple word callback procedure.

Listing 4-8 A typical word callback procedure

```
PROCEDURE MyWordCallback (chan: SpeechChannel; refCon: LongInt;
                          wordPos: LongInt; wordLen: Integer);
BEGIN
  gWindowBeingRead := WindowPtr(refCon);
  gWordPos := wordPos;
  gWordLen := wordLen;
END;
```

▲ **WARNING**

Callback procedures are called at interrupt time and therefore must not attempt to allocate, move, or dispose of memory; dereference an unlocked handle; or call other routines that do so. Also, a callback procedure is a Pascal procedure and must preserve all registers other than A0–A1 and D0–D2. ▲

Because of the restrictions on callback procedures, a typical callback procedure usually just sets global flag variables based on the information passed to it. In Listing 4-8, the callback procedure copies information from the `refCon`, `wordPos`, and `wordLen` parameters to the three global variables `gWindowBeingRead`, `gWordPos`, and `gWordLen`. You can then call a routine to check the values of these global variables once each time through your application's event loop and respond appropriately if the `gWindowBeingRead` global variable is not `NIL`. (Your application would have to initialize the variable to `NIL`.) For example, the routine might ensure that the word about to be spoken is visible onscreen and scroll the document appropriately if it is not.

Although they have different uses, speech-done callback procedures, synchronization callback procedures, error callback procedures, and phoneme callback procedures are typically defined in ways similar to that of the word callback procedure in Listing 4-8. See "Application-Defined Routines" beginning on page 4-82 for complete information on callback routines.

Text-done callback procedures are usually more complex than the other types. You can use a text-done callback procedure simply to determine when the Speech Manager has completed processing a buffer of input text. The callback procedure can just set a global flag variable that is inspected once each time through the application's main event loop; when the flag variable indicates that the input buffer processing is complete, you can dispose of the input buffer.

Writing Embedded Speech Commands

Embedded speech commands allow you to customize the quality of speech output by fine tuning it. You can make speech much easier to understand than the default way in which text is spoken by a synthesizer. An **embedded speech command** is a command embedded within a text buffer to be spoken by the Speech Manager that causes the Speech Manager to take a certain action. For example, you could use an embedded speech command to emphasize a particular word in a text string to make it stand out to the user.

An advantage of this technique is that your application needs to call only the standard functions that generate speech: `SpeakString`, `SpeakText`, or `SpeakBuffer`. To change the way a phrase is generated, you do not need to change any of your application's code; you merely need to change the embedded command text. Your application can also use embedded speech commands even if it speaks text created by the user, as opposed to a limited set of phrases. Before passing text to the Speech Manager, your application could embed various commands within the text. For example, a word-processing application might embed commands that tell the Speech Manager to put extra emphasis around words that the user has boldfaced or underlined.

Embedded Command Delimiters

When processing input text data, speech synthesizers look for special sequences of characters called **command delimiters**. These character sequences are usually defined to be unusual pairings of printable characters that would not normally appear in the text. When a begin command delimiter string is encountered in the text, the following characters are assumed to contain one or more commands. The synthesizer will attempt to parse and process these commands until an end command delimiter string is encountered. By default, the begin command delimiter string is “[”, and the end command delimiter string is “] ”. You can change the command delimiters if necessary, but you should be sure to use printable characters that are not in common use. Be sure to change the default delimiters back to the assigned characters when you are done with the speech processing for which you changed the delimiters. For example, if your application needs to speak text that naturally contains the default delimiter characters, then it should temporarily change the delimiters to sequences not included in the text. Or, if your application does not wish to support embedded speech commands, then it can disable such processing by setting both the begin command delimiter and the end command delimiter to 2 `NIL` bytes.

Syntax of Embedded Speech Commands

This section describes the syntax of embedded speech commands in detail. All embedded speech commands must be enclosed by the begin command delimiter and the end command delimiter, as follows:

```
[[emph +]]
```

All speech commands require parameters immediately following the speech command. The parameter to the speech emphasis command above is the plus sign. The format of the parameter depends on the command issued. Numeric type parameters include fixed-point numbers, bytes, integers, and 32-bit values. Hexadecimal numbers may be entered using either Pascal or C syntax; \$1A22 and 0x1A22 are both acceptable.

A common type of parameter is an operating-system type parameter, used generally to specify a particular selector. For example,

```
[[inpt PHON]]
```

changes the text-processing mode so that the Speech Manager interprets text to be composed of phonemes.

Some commands allow you to specify an absolute value by including just a number as the parameter or to specify a relative value by adding a + or – character. For example, the following command raises the speech volume by 0.1:

```
[[volm +0.1]]
```

Your application can place multiple commands within a single set of delimiters by using semicolons—for example:

```
[[volm 0.3 ; rate 165]]
```

It is suggested that you precede all other embedded speech commands by a format version command. This command indicates to speech synthesizers the format version to be used by all subsequent embedded speech commands. The current format version is 1. You could write a format version command for the current format version like this:

```
[[vers $00000001]]
```

Table 4-1 provides a formalization of the embedded command syntax structure, subject to these conventions:

- Items enclosed in angle brackets (< and >) represent logical units that either are defined further below in the table or are atomic units that should be self-explanatory, in which case the explanations are provided in *italic* type. All logical units are listed in the first column.
- Items enclosed in single brackets ([and]) are optional.
- Items followed by an ellipsis (...) may be repeated one or more times.
- For items separated by a vertical bar (|), any one of the listed items may be used.

- Multiple space characters between tokens may be used if desired.
- Multiple commands within a single set of parameters should be separated by semicolons.

Table 4-1 The embedded command syntax structure

Identifier	Syntax
<i>CommandBlock</i>	<i><BeginDelimiter></i> <i><CommandList></i> <i><EndDelimiter></i>
<i>BeginDelimiter</i>	<i><String1></i> <i><String2></i>
<i>EndDelimiter</i>	<i><String1></i> <i><String2></i>
<i>CommandList</i>	<i><Command></i> [; <i><Command></i>]...
<i>Command</i>	<i><CommandSelector></i> [<i>parameter</i>]...
<i>CommandSelector</i>	<i><OSType></i>
<i>Parameter</i>	<i><OSType></i> <i><String1></i> <i><String2></i> <i><StringN></i> <i><FixedPointValue></i> <i><32BitValue></i> <i><16BitValue></i> <i><8BitValue></i>
<i>String1</i>	<i><Character></i>
<i>String2</i>	<i><Character></i> <i><Character></i>
<i>StringN</i>	[<i><Character></i> ...]
<i>OSType</i>	<i><Character></i> <i><Character></i> <i><Character></i> <i><Character></i>
<i>32BitValue</i>	<i><OSType></i> <i><LongInt></i> <i><HexLongInt></i>
<i>16BitValue</i>	<i><Integer></i> <i><HexInteger></i>
<i>8BitValue</i>	<i><Byte></i> <i><HexByte></i>
<i>FixedPointValue</i>	<i><Decimal number: 0.0000 ≤ N ≤ 65,535.9999></i>
<i>LongInt</i>	<i><Decimal number: 0 ≤ N ≤ 4,294,967,295></i>
<i>HexLongInt</i>	<i><Hex number: 0x00000000 ≤ N ≤ 0xFFFFFFFF></i>
<i>Integer</i>	<i><Decimal number: 0 ≤ N ≤ 65,535></i>
<i>HexInteger</i>	<i><Hex number: 0x0000 ≤ N ≤ 0xFFFF></i>
<i>Character</i>	<i><Any printable character (for example, A, b, *, #, x)></i>
<i>Byte</i>	<i><Decimal number: 0 ≤ N ≤ 255></i>
<i>HexByte</i>	<i><Hex number: 0x00 ≤ N ≤ 0xFF></i>

Table 4-2 outlines the set of currently defined embedded speech commands in alphabetical order and uses the same syntax conventions as Table 4-1. Note that when writing embedded speech commands, you omit the symbols like angle brackets and ellipses that are used here for explanatory purposes.

Table 4-2 Embedded speech commands

Command and selector	Command syntax and description
Character mode (char)	<p>char NORM LTRL</p> <p>The character mode command sets the word-speaking mode of the speech channel. When <code>NORM</code> mode is selected, the synthesizer attempts to automatically convert words into speech. This is the most basic function of the text-to-speech synthesizer. When <code>LTRL</code> mode is selected, the synthesizer speaks every word, number, and symbol character by character. Embedded command processing continues to function normally, however.</p> <p>This embedded speech command is analogous to the <code>soCharacterMode</code> speech information selector.</p>
Comment (cmnt)	<p>cmnt [<i><Character></i>...]</p> <p>The comment command is ignored by speech synthesizers. It enables a developer to insert a comment that will not be spoken into a text stream for documentation purposes. Note that all characters following the <code>cmnt</code> selector up to <i><EndDelimiter></i> are part of the comment.</p>
Delimiter (dlim)	<p>dlim <i><BeginDelimiter></i> <i><EndDelimiter></i></p> <p>The delimiter command changes the character sequences that mark the beginning and end of all subsequent commands to the character sequences specified. The new delimiters take effect after the command list containing this command has been completely processed. If the delimiter strings are empty, an error is generated.</p> <p>This embedded speech command is analogous to the <code>soCommandDelimiter</code> speech information selector.</p>
Emphasis (emph)	<p>emph + -</p> <p>The emphasis command causes the next word to be spoken with either greater emphasis or less emphasis than would normally be used. Using <code>+</code> will force added emphasis, while using <code>-</code> will force reduced emphasis. For an illustration of using the emphasis command, see the section “Examples of Embedded Speech Commands” beginning on page 4-30.</p>

Table 4-2 Embedded speech commands (continued)

Command and selector	Command syntax and description
Input mode (inpt)	<p data-bbox="711 399 964 424">inpt TEXT PHON</p> <p data-bbox="711 445 1455 677">The input mode command switches the input-processing mode to either normal text mode or phoneme mode. Passing TEXT sets the mode to text mode; passing PHON sets the mode to phoneme mode. Some speech synthesizers might define additional speech input mode selectors. In phoneme mode, characters are interpreted as representing phonemes, as described in “Phonemic Representation of Speech” on page 4-32.</p> <p data-bbox="711 698 1333 752">This embedded speech command is analogous to the soInputMode speech information selector.</p>
Number mode (nbr)	<p data-bbox="711 772 938 797">nbr NORM LTRL</p> <p data-bbox="711 818 1455 1083">The number mode command sets the number-speaking mode of the speech synthesizer. When NORM mode is selected, the synthesizer attempts to automatically speak numeric strings as intelligently as possible. When LTRL mode is selected, numeric strings are spoken digit by digit. When the word-speaking mode is set to literal via the character mode command or the soCharacterMode speech information selector, numbers are spoken digit by digit regardless of the current number-speaking mode.</p> <p data-bbox="711 1104 1333 1162">This embedded speech command is analogous to the soNumberMode speech information selector.</p>
Baseline pitch (pbas)	<p data-bbox="711 1183 1130 1207">pbas [+ -] <FixedPointValue></p> <p data-bbox="711 1228 1455 1369">The baseline pitch command changes the current speech pitch for the speech channel to the fixed point value specified. If the pitch number is preceded by a + or – character, the speech pitch is adjusted relative to its current value. Base pitch values are always positive numbers in the range from 1.000 to 127.000.</p> <p data-bbox="711 1390 1455 1506">This embedded speech command is analogous to the soPitchBase speech information selector. For a discussion of speech pitch, see the section “Speech Attributes” beginning on page 4-6.</p>

continued

Table 4-2 Embedded speech commands (continued)

Command and selector	Command syntax and description
Pitch modulation (pmod)	<p data-bbox="631 395 1049 422">pmod [+ -] <FixedPointValue></p> <p data-bbox="631 443 1377 675">The pitch modulation command changes the modulation range for the speech channel based on the modulation depth fixed-point value specified. The actual pitch of generated speech might vary from the baseline pitch up or down as much as the modulation depth. If the modulation depth number is preceded by a + or - character, the pitch modulation is adjusted relative to its current value. Speech pitches fall in the range of 0.000 to 127.000.</p> <p data-bbox="631 696 1360 810">This embedded speech command is analogous to the soPitchMod speech information selector. For a discussion of speech pitch, see the section “Speech Attributes” beginning on page 4-6.</p>
Speech rate (rate)	<p data-bbox="631 830 1049 857">rate [+ -] <FixedPointValue></p> <p data-bbox="631 878 1377 1079">The speech rate command sets the speech rate in words per minute on the speech channel to the fixed-point value specified. If the rate value is preceded by a + or - character, the speech rate is adjusted relative to its current value. Speech rates fall in the range 0.000 to 65535.999, which translate into 50 to 500 words per minute. Normal human speech rates are around 180 to 220 words per minute.</p> <p data-bbox="631 1100 1377 1189">This embedded speech command is analogous to the soRate speech information selector. For a discussion of speech rate, see the section “Speech Attributes” beginning on page 4-6.</p>
Reset (rset)	<p data-bbox="631 1210 862 1236">rset <32BitValue></p> <p data-bbox="631 1257 1377 1340">The reset command will reset the speech channel’s voice and speech attributes back to default values. The parameter has no effect; it should be set to 0.</p> <p data-bbox="631 1361 1377 1417">This embedded speech command is analogous to the soReset speech information selector.</p>
Silence (slnc)	<p data-bbox="631 1437 862 1464">slnc <32BitValue></p> <p data-bbox="631 1485 1377 1659">The silence command causes the synthesizer to generate silence for the number of milliseconds specified. The timing of the silence will vary widely between synthesizers. For an illustration of using the silence command, see the section “Examples of Embedded Speech Commands” beginning on page 4-30.</p>

Table 4-2 Embedded speech commands (continued)

Command and selector	Command syntax and description
Synchronization (sync)	<p>sync <32BitValue></p> <p>The synchronization command causes the application's synchronization callback procedure to be executed. The callback is made as the audio corresponding to the next word begins to sound. The callback procedure is passed the 32-bit value specified in the command. Synchronization callback procedures are described in "Synchronization Callback Procedure" beginning on page 4-85.</p>
Format version (vers)	<p>vers <32BitValue></p> <p>The format version command informs the speech synthesizer of the format version that subsequent embedded speech commands will use. This command is optional but is recommended to ensure that embedded speech commands are compatible with all versions of the Speech Manager. The current format version is \$0001.</p>
Speech volume (volm)	<p>volm [+ -] <FixedPointValue></p> <p>The speech volume command changes the speech volume on the speech channel to the fixed-point value specified. If the volume value is preceded by a + or - character, the speech volume is adjusted relative to its current value. Volumes are expressed in fixed-point units ranging from 0.000 through 1.000. A value of 0.0 corresponds to silence, and a value of 1.0 corresponds to the maximum possible volume. Volume units lie on a scale that is linear with amplitude or voltage. A doubling of perceived loudness corresponds to a doubling of the volume.</p> <p>This embedded speech command is analogous to the soVolume speech information selector.</p>
Synthesizer-specific (xtnd)	<p>xtnd <OSType> [<Parameter>...]</p> <p>The synthesizer-specific command enables synthesizer-specific commands to be embedded in the input text stream. Synthesizer-specific speech commands are processed by the speech synthesizer whose creator ID is specified in the first parameter and by other speech synthesizers that support commands aimed at the synthesizer with the specified creator ID. The format of the data following the parameter is entirely dependent on the synthesizer being used.</p> <p>This embedded speech command is analogous to the soSynthExtension speech information selector, described in "Speech Information Selectors" beginning on page 4-39.</p>

While embedded speech commands are being processed, several types of errors might be detected and reported to your application. If you have enabled error callbacks by

Speech Manager

using the `SetSpeechInfo` function with the `soErrorCallback` selector, the error callback procedure will be executed once for every error that is detected, as described in “Error Callback Procedure” beginning on page 4-86. If you have not enabled error callbacks, you can still obtain information about the errors encountered by calling the `GetSpeechInfo` function with the `soErrors` selector. The following errors might be detected during processing of embedded speech commands:

<code>badParmVal</code>	-245	Parameter value is invalid
<code>badCmdText</code>	-246	Embedded command syntax or parameter problem
<code>unimplCmd</code>	-247	Embedded command is not implemented on synthesizer
<code>unimplMsg</code>	-248	Unimplemented message
<code>badVoiceID</code>	-250	Specified voice has not been preloaded
<code>badParmCount</code>	-252	Incorrect number of embedded command arguments

Examples of Embedded Speech Commands

If you use just a few of the embedded speech commands, you can markedly increase the understandability of text spoken by your application. Your application knows more about the speech being produced than a speech synthesizer does. A synthesizer speaks text according to a predetermined set of rules about language production. Therefore, the voices available on a Macintosh computer with the Speech Manager installed sound very synthetic and sometimes robotic because the pronunciation rules are formalized. You can make the speech produced by the synthesizer sound a lot more human by observing some simple rules of human speech and embedding speech commands in text according to these conventions. The techniques presented in this section could be applied when your application is having a dialog with the user or speaking some error messages or announcements.

The most common technique humans use in speaking is to emphasizing or deemphasizing words in a sentence. This change in emphasis marks for the listener new and important information by highlighting it vocally, making it easier for the listener to recognize important or different words in a sentence. For example, in a calendar-scheduling program, your application might speak a list of appointments for a day. The following text strings would all be spoken with the same tune and rhythm.

```
At 4pm you have a meeting with Kim Silver.
At 6pm you have a meeting with Tim Johnson.
At 7pm you have a meeting with Mark Smith.
```

The example that follows shows how you use embedded speech commands to deemphasize repeated words in similar sentences and highlight new information in a sentence. The first sentence of the following example sounds fairly acceptable. The second sentence deemphasizes the repeated words *have* and *meeting* to point out the new information—with whom the meeting is. The choice of which words to emphasize or deemphasize is based on what was spoken in the preceding sentence. To use the embedded command `emph` (emphasis), you insert it followed by a plus or minus sign before the word you want emphasized or deemphasized. The `emph` command lasts for a duration of one word.

Speech Manager

At 4:15 you have a meeting with Ray Chiang.

At 6:30, you `[[emph -]]` have a `[[emph -]]` meeting with William Ortiz.

At 7pm, you `[[emph -]]` have a `[[emph -]]` meeting with Eric Braz Ford.

As shown in the next example, you can further enhance this text by spelling out the numbers so that you can emphasize changes in increments of time. For example, the following sentences deemphasize the repeated word *six* to highlight the difference between the meetings; which both occur between six and seven o'clock.

At four fifteen you have a meeting with Lori Kaplan.

At six `[[emph -]]` fifteen, you `[[emph -]]` have a `[[emph -]]` meeting with Tim Monroe.

At `[[emph -]]` six thirty, you `[[emph -]]` have a `[[emph -]]` meeting with Michael Abrams.

Another use of the emphasis embedded command is to make confusing, boring, or mechanical sounding text more understandable. One example of this is strings of nouns that refer to one entity (called complex nominals) that when spoken differently have a different meaning.

1a. Steel warehouse.

1b. Steel `[[emph -]]` warehouse.

2a. French teachers.

2b. French `[[emph -]]` teachers.

In the first example, phrase 1a, *steel warehouse*, refers to a warehouse made of steel, in which anything could be stored. But phrase 1b describes a warehouse of unspecified construction in which steel is stored. In the second example, phrase 2a, *French teachers*, refers to teachers from France who teach any subject. In the same example, phrase 2b specifies people from anywhere who teach French classes. You can use this technique of deemphasizing words in phrases to help users correctly understand the meaning of text spoken from your application.

You use the `emph` command to emphasize words in order to contrast them. You contrast words that are similar to words found later in a sentence to help distinguish new information.

You have `[[emph +]]` 3 text `[[emph -]]` messages, two fax `[[emph -]]` messages, and `[[emph +]]` one `[[emph +]]` voice `[[emph -]]` message.

This example emphasizes the words related to the number of messages and type of messages to help the listener discern the different kinds of information being presented.

Speech Manager

Another common speaking technique that humans use is to pause before starting to speak about a new idea or before beginning a new paragraph. Adding an `slnc` (silence) command before beginning to speak a new idea or paragraph makes the synthetic voice sound like a person does when taking a breath in between ideas. This technique works best if you also raise the pitch range (using the `pmod` and `pbas` embedded commands) of the first sentence of the new paragraph. You must remember to lower the pitch range to achieve the desired effect.

```
[[emph -; pmod +1; pbas +1]] Good morning! [[pmod -1; pbas -1]]
This is a [[emph +]] newer [[emph -]] version of Apple's speech
synthesis. The previous [[emph -]] version has already been
[[emph -]] adopted by many developers. Users have sent us many
positive [[emph +]] reports.
```

```
[[slnc 500; pmod +1; pbas +1]]
This newer [[emph -]] version has better signal [[emph -]]
processing [[pmod -1; pbas -1]], new pitch [[emph -]] contours,
and a new compression. It still doesn't [[emph -]] sound perfect,
but people find it easier to understand.
```

This example deemphasizes the first word of the utterance, but raises the pitch to make the greeting sound more like a human would speak it. Then words are emphasized or deemphasized according to the techniques discussed previously. Silence is introduced before the new paragraph to signal a change in thought process. The pitch is raised and then lowered again after the first phrase. Note that you don't have to wait a full sentence before changing the pitch back to its previous value. It's best to work with these techniques until you find the most human-sounding utterances.

Phonemic Representation of Speech

The Speech Manager allows your application to process text phonemically. If your application speaks only text that the user writes, this feature is unlikely to be useful to you, because you cannot anticipate what the user might enter. However, if there are a few or many sentences that your application frequently converts into speech, it might be useful to represent parts of these sentences phonemically rather than textually.

It might be useful to convert your text into phonemes during application development in order to be able to reduce the amount of memory required to speak. If your application does not require the text-to-phoneme conversion portion of the speech synthesizer, significantly less RAM might be required to speak with some synthesizers.

Additionally, you might be able to use a higher quality text-to-phoneme conversion process (even one that does not work in real time) to generate precise phonemic information. This data can then be used with any speech synthesizer to produce better speech. For example, you might convert textual to phonemic data on a future version of the Speech Manager that performs such conversions more accurately than the Speech Manager currently does; that phonemic data could then be used to generate speech with

Speech Manager

any version of the Speech Manager. The Speech Manager's `TextToPhonemes` function provides an easy method for converting text into its default phonemic equivalent.

To help the Speech Manager differentiate a textual representation of a word from a phonemic representation, you must embed commands in text that inform the Speech Manager to change into a mode in which it interprets a buffer of text as a phonemic representation of speech, in which particular combinations of letters represent particular phonemes. (You can also use the `SetSpeechInfo` function to change to phoneme mode.) To indicate to the Speech Manager that subsequent text is a phonemic representation of text to be spoken, embed the `[[inpt PHON]]` command within a string or buffer that your application passes to one of the `SpeakString`, `SpeakText`, or `SpeakBuffer` functions. To indicate that the Speech Manager should revert to textual interpretation of a text buffer, embed the `[[inpt TEXT]]` command. For example, passing the string

```
Hello, I am [[inpt PHON]]mAYkAXl[[inpt TEXT]], the talking
computer.
```

to `SpeakString`, `SpeakText`, or `SpeakBuffer` would result in the generation of the sentence, "Hello, I am Michael, the talking computer."

Some, but not all, speech synthesizers allow you to embed a command that causes the Speech Manager to interpret a buffer of text as a series of allophones.

Phonemic Symbols

Table 4-3 summarizes the set of standard phonemes recognized by American English speech synthesizers. Other languages and dialects require different phoneme inventories. Phonemes divide into two groups: vowels and consonants. All vowel symbols are pairs of uppercase letters. For simple consonants the symbol is that lowercase consonant; for blends and complex consonants, the symbol is in uppercase. Within the example words, the individual sounds being exemplified appear in boldface.

Table 4-3 American English phoneme symbols

Symbol	Example	Opcode	Symbol	Example	Opcode
%	silence	0	D	them	21
@	breath intake	1	f	fin	22
AE	bat	2	g	gain	23
EY	bait	3	h	hat	24
AO	caught	4	J	jump	25
AX	about	5	k	kin	26
IY	beet	6	l	limb	27
EH	bet	7	m	mat	28

continued

Table 4-3 American English phoneme symbols (continued)

Symbol	Example	Opcode	Symbol	Example	Opcode
IH	bit	8	n	nat	29
AY	bite	9	N	tang	30
IX	roses	10	p	pin	31
AA	cot	11	r	ran	32
UW	boot	12	s	sin	33
UH	book	13	S	shin	34
UX	bud	14	t	tin	35
OW	boat	15	T	thin	36
AW	bout	16	v	van	37
OY	boy	17	w	wet	38
b	bin	18	y	yet	39
C	chin	19	z	zen	40
d	din	20	Z	measure	41

You can obtain information similar to that in Table 4-3 for whatever language a synthesizer supports by using the `GetSpeechInfo` function on a channel using the synthesizer with the `soPhonemeSymbols` selector. The information is returned in a phoneme descriptor record, whose structure is described on page 4-53.

Prosodic Control Symbols

The symbols listed in Table 4-4 are recognized as modifiers to the basic phonemes described in the preceding section. You can use them to more precisely control the quality of speech that is described in terms of raw phonemes.

Table 4-4 Prosodic control symbols

Type	Symbol	Symbol name	Description or illustration of effect
Lexical stress:			Marks stress within a word (optional)
Primary stress	1		AEnt2IHsIXp1EYSAXn (“anticipation”)
Secondary stress	2		
Syllable breaks:			Marks syllable breaks within a word (optional)
Syllable mark	=	(equal)	AEn=t2IH=sIX=p1EY=SAXn (“an-ti-ci-pa-tion”)
Word prominence:			Placed before the affected word
Destressed	~	(asciitilde)	Used for words with minimal informational content

Table 4-4 Prosodic control symbols (continued)

Type	Symbol	Symbol name	Description or illustration of effect
Normal stress	_	(underscore)	Used for information-bearing words
Emphatic stress	+	(plus)	Used for words requiring special emphasis
Prosodic:			Placed before the affected phoneme
Pitch rise	/	(slash)	Pitch will rise on the following phoneme
Pitch fall	\	(backslash)	Pitch will fall on the following phoneme
Lengthen phoneme	>	(greater)	Lengthens the duration of the following phoneme
Shorten phoneme	<	(less)	Shortens the duration of the following phoneme

Note

Like all other phonemes, the “silence” phoneme (%) and the “breath intake” phoneme (@) can be lengthened or shortened using the > and < symbols. ♦

The prosodic control symbols (/ , \ , < , and >) can be concatenated to provide exaggerated or cumulative effects. The specific nature of the effect is dependent on the speech synthesizer. Speech synthesizers also often extend or enhance the controls described in the table.

Table 4-5 indicates the effect of punctuation marks on sentence prosody. In particular, the table shows the effect of punctuation marks on speech pitch and indicates to what extent the punctuation marks cause a pause. Note that because some languages might not use these punctuation marks, some synthesizers might not interpret them correctly. In general, speech synthesizers strive to mimic the pauses and changes in pitch of actual speakers in response to punctuation marks, so to obtain best results, you can punctuate according to standard grammatical rules.

Table 4-5 Effect of punctuation marks on English-language synthesizers

Symbol	Symbol name	Effect of punctuation mark	Effect on Timing
&	(ampersand)	Forces no addition of silence between phonemes	No additional effect
:	(colon)	End of clause, no change in pitch	Short pause follows
,	(comma)	Continuation rise in pitch	Short pause follows
...	(ellipsis)	End of clause, no change in pitch	Pause follows
!	(exclam)	End-of-sentence sharp fall in pitch	Pause follows
-	(hyphen)	End of clause, no change in pitch	Short pause follows
((parenleft)	Start reduced pitch range	Short pause precedes

continued

Table 4-5 Effect of punctuation marks on English-language synthesizers (continued)

Symbol	Symbol name	Effect of punctuation mark	Effect on Timing
)	(parenright)	End reduced pitch range	Short pause follows
.	(period)	End-of-sentence fall in pitch	Pause follows
?	(question)	End-of-sentence rise in pitch	Pause follows
“ ,	(quotedblleft, quotesingleleft)	Varies depending on context	Varies
” ,	(quotedblright, quotesingleright)	Varies depending on context	Varies
;	(semicolon)	Continuation rise in pitch	Short pause follows

Specific pitch contours associated with these punctuation marks might vary according to other considerations in the analysis of the text. For example, if a question is rhetorical or begins with a word recognized by the synthesizer to be a question word, the pitch might fall at the question mark. Consequently the above effects should be regarded as only guidelines and not absolute. This also applies to the timing effects, which will vary according to the current rate setting.

Including Pronunciation Dictionaries

No matter how sophisticated a speech synthesis system is, there will always be words that it does not automatically pronounce correctly. A clear instance of words that are often mispronounced is the class of proper nouns (names of people, place names, and so on). The Speech Manager supports pronunciation dictionaries which allow applications to override the default pronunciations of words. A **pronunciation dictionary** is a list of words along with their associated pronunciations stored in a resource of resource type 'dict'.

The application is free to store dictionaries in either the resource fork or the data fork of a file. The application is responsible for loading the individual dictionaries into RAM and then passing a handle to the dictionary data to the Speech Manager. The initial release of the Speech Manager, however, does not include any routines that can add entries to dictionaries or manipulate them in other ways. The Speech Manager does include a routine, the `UseDictionary` function, that you can use to install one or more pronunciation dictionaries in a speech channel.

A multimedia application might store such a pronunciation dictionary resource in its own resource fork to specify the pronunciations of selected words used in a narration. A word-processing application, meanwhile, could allow a user to add words to a pronunciation dictionary stored in the resource fork of a text file. Or, a text-services application dedicated to speech generation might include large specialized dictionaries—for example, of medical terms—to specify pronunciation of words in particular subject

areas. Because the Speech Manager allows your application to install as many pronunciation dictionaries as desired in a speech channel, it can use pronunciation dictionaries in one or more of these ways.

Note

The Dictionary Manager, described in *Inside Macintosh: Text*, cannot be used with pronunciation dictionaries. ♦

Whenever a speech synthesizer needs to determine the proper phonemic representation for a particular word, it first looks for the word in its pronunciation dictionaries. Pronunciation dictionary entries contain information that enables precise conversion between text and the correct phoneme codes, as described in “Phonemic Representation of Speech” beginning on page 4-32. Pronunciation dictionary entries also provide stress, intonation, and other information to help speech synthesizers produce more natural speech, as described in “Prosodic Control Symbols” beginning on page 4-34. Note that you cannot use punctuation marks (as described in Table 4-5) in pronunciation dictionaries.

A single pronunciation dictionary entry cannot be used to specify the pronunciation of an entire phrase, because the Speech Manager checks its pronunciation dictionary on a word-by-word basis. Thus, the textual portion of a pronunciation dictionary entry must not contain any spaces.

If the pronunciation dictionaries installed in a speech channel do not include an indication of how a word should be pronounced, then the Speech Manager uses its own pronunciation rules and internal dictionary to pronounce the words. In general, you need to create a dictionary only for unusual words that your application requires but the Speech Manager ordinarily pronounces incorrectly. You might also allow a user who is not pleased with the default pronunciation of a word to add the correct pronunciation to a pronunciation dictionary. You can create a dictionary using MPW Rez or another appropriate tool. See “The Pronunciation Dictionary Resource” beginning on page 4-89 for a discussion of the format of the pronunciation dictionary resource and the meaning of its fields.

To install a pronunciation dictionary resource in a speech channel, you must read the resource into memory and pass it to the `UseDictionary` function. Because the `UseDictionary` function requires that you specify a speech channel, you might need to reinstall the dictionary whenever your application allocates a new speech channel or whenever it resets an existing speech channel. Listing 4-9 shows how you can use the `UseDictionary` function to install a pronunciation dictionary resource in a speech channel.

Listing 4-9 Installing a pronunciation dictionary resource into a speech channel

```
PROCEDURE MyUseDictionary (chan: SpeechChannel; resID: Integer);
VAR
    myDict:      Handle;           {handle to dictionary data}
    myErr:      OSErr;
```

Speech Manager

```

BEGIN
  myDict := GetResource('dict', resID);      {load the dictionary}
  IF (myDict <> NIL) AND (ResError = noErr) THEN
  BEGIN
    myErr := UseDictionary(chan, myDict);    {install the dictionary}
    IF myErr <> noErr THEN
      DoError(myErr);                       {respond to an error}
    ReleaseResource(myDict);               {release the resource}
  END;
END;

```

The `MyUseDictionary` procedure defined in Listing 4-9 attempts to find a resource of resource type 'dict' with resource ID `resID` and uses the Resource Manager to read it into memory. If your application stores pronunciation dictionaries in the data fork of files, it can instead use analogous File Manager routines to read the data. If the data is read in correctly, `MyUseDictionary` calls the `UseDictionary` function to install the dictionary on the specified speech channel. Because the speech synthesizer copies all necessary data from the dictionary to its internal buffers, the application is free to release the memory occupied by the dictionary, as illustrated by the `ReleaseResource` call.

The pronunciation dictionary resource in Listing 4-10 consists of pronunciation dictionary entries in Rez format. Each entry specifies a word in textual format and its phonemic equivalent.

Listing 4-10 A sample pronunciation dictionary resource

```

resource 'dict' (1, "TestDict") {
  smRoman, langEnglish, verUS, ThisSecond,
  {
    pron, {tx, "ROOSEVELT",   ph, "_1EHf_d1IY_1AAr"},
    pron, {tx, "CHELSEA",     ph, "_C1EHls2IY"},
    pron, {tx, "AMHERST",    ph, "_2UXmAXrst"},
    pron, {tx, "REDSOX",     ph, "_r1EHd_s1AAks"},
    pron, {tx, "HALLOWEEN",  ph, "_h1AA12OW_w1IYn"},
    pron, {tx, "FELIX",      ph, "_f1IY12IHks_D2UX_k1AEt"},
    pron, {tx, "WEDNESDAY",  ph, "_m1IHd_w1IYk"},
  },
};

```

Note that you are not restricted to using pronunciations similar to those of the words listed. Typically, however, pronunciation dictionaries contain entries for words that the Speech Manager pronounces unsatisfactorily.

Also, note that a pronunciation dictionary's entries need not be in any particular order. In particular, you should not assume that a pronunciation dictionary is in alphabetical order unless your application creates the dictionary and maintains that order.

The pronunciation dictionary resource header consists of nine fields, of which four must be explicitly defined in a Rez definition such as the one in Listing 4-10. The first three of these fields specify the script, language, and region code of the language for which the pronunciation dictionary is designed. Note that you must create a separate pronunciation dictionary for each region, language, or script. The fourth field of a pronunciation dictionary is the date the pronunciation dictionary was last modified, in terms of seconds since midnight, January 1, 1904. In Listing 4-10, it is assumed that the constant `ThisSecond` is defined to be such a date. For information on obtaining information about the current date in this format, see *Inside Macintosh: Operating System Utilities*.

Speech Manager Reference

This section describes the constants, data structures, routines, and resources that are specific to the Speech Manager.

The section “Constants” describes the available speech information selectors.

The section “Data Structures” beginning on page 4-45 shows all of the Speech Manager’s Pascal data structures, including those for the voice specification and description records, the speech status information record, and the phoneme information and descriptor records.

The section “Speech Manager Routines” beginning on page 4-54 describes the Speech Manager functions that allow you to generate speech, use voices, manage and control speech channels, convert text to phonemes, and use pronunciation dictionaries.

The section “Application-Defined Routines” beginning on page 4-82 describes the kinds of callback procedures you can implement.

The section “Resources” beginning on page 4-89 describes the format of pronunciation dictionary resources.

Constants

This section describes the available speech information selectors.

Speech Information Selectors

This section describes the **speech information selectors** that you can pass in the `selector` parameter of the `GetSpeechInfo` and `SetSpeechInfo` functions.

CONST

```
soCharacterMode      = 'char';    {get or set character-processing mode}
soCommandDelimiter  = 'dlim';    {set embedded command delimiters}
soCurrentA5         = 'myA5';    {set A5 on callbacks}
```

Speech Manager

<code>soCurrentVoice</code>	<code>= 'cvox';</code>	<code>{set speaking voice}</code>
<code>soErrorCallBack</code>	<code>= 'ercb';</code>	<code>{set error callback}</code>
<code>soErrors</code>	<code>= 'erro';</code>	<code>{get error information}</code>
<code>soInputMode</code>	<code>= 'inpt';</code>	<code>{get or set text-processing mode}</code>
<code>soNumberMode</code>	<code>= 'nmbr';</code>	<code>{get or set number-processing mode}</code>
<code>soPhonemeCallBack</code>	<code>= 'phcb';</code>	<code>{set phoneme callback}</code>
<code>soPhonemeSymbols</code>	<code>= 'phsy';</code>	<code>{get phoneme symbols and example } { words}</code>
<code>soPitchBase</code>	<code>= 'pbas';</code>	<code>{get or set baseline pitch}</code>
<code>soPitchMod</code>	<code>= 'pmod';</code>	<code>{get or set pitch modulation}</code>
<code>soRate</code>	<code>= 'rate';</code>	<code>{get or set speech rate}</code>
<code>soRecentSync</code>	<code>= 'sync';</code>	<code>{get most recent synchronization } { message information}</code>
<code>soRefCon</code>	<code>= 'refc';</code>	<code>{set reference constant value}</code>
<code>soReset</code>	<code>= 'rset';</code>	<code>{set channel back to default state}</code>
<code>soSpeechDoneCallBack</code>	<code>= 'sdcB';</code>	<code>{set speech-done callback}</code>
<code>soStatus</code>	<code>= 'stat';</code>	<code>{get status of channel}</code>
<code>soSyncCallBack</code>	<code>= 'sycb';</code>	<code>{set synchronization callback}</code>
<code>soSynthExtension</code>	<code>= 'xtnd';</code>	<code>{get or set synthesizer-specific } { information}</code>
<code>soSynthType</code>	<code>= 'vers';</code>	<code>{get synthesizer information}</code>
<code>soTextDoneCallBack</code>	<code>= 'tdcb';</code>	<code>{set text-done callback}</code>
<code>soVolume</code>	<code>= 'volm';</code>	<code>{get or set speech volume}</code>
<code>soWordCallBack</code>	<code>= 'wdcb';</code>	<code>{set word callback}</code>

Constant descriptions`soCharacterMode`

Get or set the speech channel's character-processing mode. Two constants are currently defined for the processing mode, `modeNormal` and `modeLiteral`. When the character-processing mode is `modeNormal`, input characters are spoken as you would expect to hear them. When the mode is `modeLiteral`, each character is spoken literally, so that the word "cat" would be spoken "C-A-T". The `speechInfo` parameter points to a variable of type `OSType`, which is the character-processing mode.

This selector works with `GetSpeechInfo` and `SetSpeechInfo` and does not move memory.

`soCommandDelimiter`

Set the embedded speech command delimiter characters to be used for the speech channel. By default the opening delimiter is "[[" and the closing delimiter is "]]". Your application might need to change these delimiters temporarily if those character sequences occur naturally in a text buffer that is to be spoken. Your application can also disable embedded command processing by passing empty delimiters (2 NIL bytes). The `speechInfo` parameter is a pointer to a delimiter information record, described on page 4-54.

Speech Manager

- This selector works with the `SetSpeechInfo` function and does not move memory.
- `soCurrentA5` Set the value that the Speech Manager assigns to the A5 register before invoking any application-defined callback procedures for the speech channel. The A5 register must be set correctly if the callback procedures are to be able to access application global variables. For more information on the A5 register, see *Inside Macintosh: Memory*. The `speechInfo` parameter should be set to the pointer contained in the A5 register at a time when the application is not executing interrupt code or to `NIL` if your application wishes to clear a value previously set with the `soCurrentA5` selector.
- This selector works with the `SetSpeechInfo` function and does not move memory. See Listing 4-6 on page 4-21 for an illustration of the use of this selector.
- `soCurrentVoice` Set the current voice on the current speech channel to the specified voice. The `speechInfo` parameter is a pointer to a voice specification record. Your application should create the record by calling the `MakeVoiceSpec` function, described on page 4-64. `SetSpeechInfo` will return an `incompatibleVoice` error if the specified voice is incompatible with the speech synthesizer associated with the speech channel. If you have a speech channel open using a voice from a particular synthesizer and you try to switch to a voice that works with a different synthesizer, you receive an `incompatibleVoice` error. You need to create a new channel to use with the new voice.
- This selector works with only `SetSpeechInfo` and might move memory. Your application should not invoke it at interrupt time.
- `soErrorCallback` Set the callback procedure to be called when an error is encountered during the processing of an embedded command. The callback procedure might also be called if other conditions (such as insufficient memory) arise during the speech conversion process. When a Speech Manager function returns an error directly, the error callback procedure is not called. The callback procedure is passed information about the most recent error; it can determine information about the oldest pending error by using the `speechInfo` selector `soErrors`. The `speechInfo` parameter is a pointer to an application-defined error callback procedure, whose syntax is described on page 4-86. Passing `NIL` in `speechInfo` disables the error callback procedure.
- This selector works with the `SetSpeechInfo` function and does not move memory.
- `soErrors` Get saved error information for the speech channel and clear its error registers. This selector lets you poll for various run-time errors that occur during speaking, such as the detection of badly formed embedded commands. Errors returned directly by Speech Manager functions are not reported here. If your application defines an error callback procedure, the callback should use the `soErrors` selector

Speech Manager

to obtain error information. The `speechInfo` parameter is a pointer to a speech error information record, described on page 4-49. This selector works with the `GetSpeechInfo` function and does not move memory.

`soInputMode` Get or set the speech channel's current text-processing mode. The returned value specifies whether the channel is currently in text input mode or phoneme input mode. The `speechInfo` parameter is a pointer to a variable of type `OSType`, which specifies a text-processing mode. The following constants specify the available text-processing modes:

```
CONST
    modeText           = 'TEXT' ;
    modePhonemes      = 'PHON' ;
```

The `modeText` constant indicates that the speech channel is in text-processing mode. The `modePhonemes` constant indicates that the speech channel is in phoneme-processing mode. When in phoneme-processing mode, a text buffer is interpreted to be a series of characters representing various phonemes and prosodic controls, as discussed in “Phonemic Representation of Speech” on page 4-32 and “Prosodic Control Symbols” on page 4-34. Some synthesizers might support additional input-processing modes and define constants for these modes.

This selector works with both the `GetSpeechInfo` and `SetSpeechInfo` functions. It might move memory only when used in conjunction with the `SetSpeechInfo` function.

`soNumberMode` Get or set the speech channel's current number-processing mode. Two `OSType` constants are currently defined, `modeNormal` and `modeLiteral`. When the number-processing mode is `modeNormal`, the synthesizer assembles digits into numbers (so that 12 is spoken as “twelve”). When the mode is `modeLiteral`, each digit is spoken literally (so that 12 is spoken as “one, two”). The `speechInfo` parameter is a pointer to a variable of type `OSType`, which specifies the number-processing mode.

This selector works with both the `GetSpeechInfo` and `SetSpeechInfo` functions and does not move memory.

`soPhonemeCallback` Set the callback procedure to be called every time the Speech Manager is about to generate a phoneme on the speech channel. The `speechInfo` parameter is a pointer to an application-defined phoneme callback procedure, whose syntax is described on page 4-87. Passing `NIL` in `speechInfo` disables the phoneme callback procedure.

This selector works with the `SetSpeechInfo` function and does not move memory.

`soPhonemeSymbols` Get a list of phoneme symbols and example words defined for the

	<p>speech channel's synthesizer. Your application might use this information to show the user what symbols to use when entering phonemic text directly. The <code>speechInfo</code> parameter is a pointer to a variable of type <code>Handle</code> that, on exit from the <code>GetSpeechInfo</code> function, is a handle to a phoneme descriptor record, described on page 4-53.</p> <p>This selector works with the <code>GetSpeechInfo</code> function and might move memory. Your application should not invoke it at interrupt time.</p>
<code>soPitchBase</code>	<p>Get or set the speech channel's baseline speech pitch. This selector is intended for use by the Speech Manager; ordinarily, an application uses the <code>GetSpeechPitch</code> and <code>SetSpeechPitch</code> functions, described on page 4-75 and page 4-76, respectively. The <code>speechInfo</code> parameter is a pointer to a variable of type <code>Fixed</code>.</p> <p>This selector works with both the <code>GetSpeechInfo</code> and <code>SetSpeechInfo</code> functions and does not move memory.</p>
<code>soPitchMod</code>	<p>Get or set a speech channel's pitch modulation. The <code>speechInfo</code> parameter is a pointer to a variable of type <code>Fixed</code>. Pitch modulation is also expressed as a fixed-point value in the range of 0.000 to 127.000. These values correspond to MIDI note values, where 60.000 is equal to middle C on a piano scale. The most useful speech pitches fall in the range of 40.000 to 55.000. A pitch modulation value of 0.000 corresponds to a monotone in which all speech is generated at the frequency corresponding to the speech pitch. Given a speech pitch value of 46.000, a pitch modulation of 2.000 would mean that the widest possible range of pitches corresponding to the actual frequency of generated text would be 44.000 to 48.000.</p> <p>This selector works with both the <code>GetSpeechInfo</code> and <code>SetSpeechInfo</code> functions and does not move memory.</p>
<code>soRate</code>	<p>Get or set a speech channel's speech rate. The <code>speechInfo</code> parameter is a pointer to a variable of type <code>Fixed</code>. The possible range of speech rates is from 0.000 to 65535.65535. The range of supported rates is not predefined by the Speech Manager; each speech synthesizer provides its own range of speech rates. Average human speech occurs at a rate of 180 to 220 words per minute.</p> <p>This selector works with both the <code>GetSpeechInfo</code> and <code>SetSpeechInfo</code> functions and does not move memory.</p>
<code>soRecentSync</code>	<p>Get the message code for the most recently encountered synchronization command. If no synchronization command has been encountered, 0 is returned. The <code>speechInfo</code> parameter is a pointer to a variable of type <code>OSType</code>.</p> <p>This selector works with the <code>GetSpeechInfo</code> function and does not move memory.</p>
<code>soRefCon</code>	<p>Set a speech channel's reference constant value. The reference constant value is passed to application-defined callback procedures and might contain any value convenient for the application. The <code>speechInfo</code> parameter is a long integer containing the reference</p>

Speech Manager

constant value. In contrast with other selectors, this selector does not require that the `speechInfo` parameter's value be a pointer value. Typically, however, an application does use this selector to pass a pointer or handle value to callback procedures.

This selector works with the `SetSpeechInfo` function and does not move memory. See Listing 4-6 on page 4-21 for an illustration of the use of this selector.

`soReset` Set a speech channel back to its default state. For example, speech pitch and speech rate are set to default values. The `speechInfo` parameter should be set to `NIL`.

This selector works with the `SetSpeechInfo` function and does not move memory.

`soSpeechDoneCallback`

Set the callback procedure to be called when the Speech Manager has finished generating speech on the speech channel. The `speechInfo` parameter is a pointer to an application-defined speech-done callback procedure, whose syntax is described on page 4-84. Passing `NIL` in `speechInfo` disables the speech-done callback procedure.

This selector works with the `SetSpeechInfo` function and does not move memory.

`soStatus`

Get a speech status information record for the speech channel. The `speechInfo` parameter is a pointer to a speech status information record, described on page 4-48.

This selector works with the `GetSpeechInfo` function and does not move memory.

`soSyncCallback`

Set the callback procedure to be called when the Speech Manager encounters a synchronization command within an embedded speech command in text being processed on the speech channel. The `speechInfo` parameter is a pointer to an application-defined synchronization callback procedure, whose syntax is described on page 4-85. Passing `NIL` in `speechInfo` disables the synchronization callback procedure.

This selector works with the `SetSpeechInfo` function and does not move memory.

`soSynthExtension`

Get or set synthesizer-specific information or settings. The `speechInfo` parameter is a pointer to a speech extension data record, described on page 4-53. Your application should set the `synthCreator` field of this record before calling `GetSpeechInfo` or `SetSpeechInfo`. Ordinarily, your application must pass additional information to the synthesizer in the `synthData` field.

This selector works with both the `GetSpeechInfo` and `SetSpeechInfo` functions. Whether it moves memory depends on the synthesizer being used and the information passed to the synthesizer.

Speech Manager

<code>soSynthType</code>	<p>Get a speech version information record for the speech synthesizer being used on the specified speech channel. The <code>speechInfo</code> parameter is a pointer to a speech version information record, described on page 4-50.</p> <p>This selector works with the <code>GetSpeechInfo</code> function and does not move memory.</p>
<code>soTextDoneCallback</code>	<p>Set the callback procedure to be called when the Speech Manager has finished processing speech being generated on the speech channel. The <code>speechInfo</code> parameter is a pointer to an application-defined text-done callback procedure, whose syntax is described on page 4-84. Passing <code>NIL</code> in <code>speechInfo</code> disables the text-done callback procedure.</p> <p>This selector works with the <code>GetSpeechInfo</code> function and does not move memory.</p>
<code>soVolume</code>	<p>Get or set the speech volume for a speech channel. The <code>speechInfo</code> parameter is a pointer to a variable of type <code>Fixed</code>. Volumes are expressed in fixed-point units ranging from 0.0 through 1.0. A value of 0.0 corresponds to silence, and a value of 1.0 corresponds to the maximum possible volume. Volume units lie on a scale that is linear with amplitude or voltage. A doubling of perceived loudness corresponds to a doubling of the volume.</p> <p>This selector works with both the <code>GetSpeechInfo</code> and <code>SetSpeechInfo</code> functions and does not move memory.</p>
<code>soWordCallback</code>	<p>Set the callback procedure to be called every time the Speech Manager is about to generate a word on the speech channel. The <code>speechInfo</code> parameter is a pointer to an application-defined word callback procedure, whose syntax is described on page 4-87. Passing <code>NIL</code> in <code>speechInfo</code> disables the word callback procedure.</p> <p>This selector works with the <code>SetSpeechInfo</code> function and does not move memory. See Listing 4-7 on page 4-21 for an illustration of the use of this selector.</p>

Data Structures

This section describes the data structures defined by the Speech Manager.

The speech channel record contains information internal to the Speech Manager. Speech channels, which process Speech Manager text and commands, are defined as pointers to Speech Manager records.

A voice specification record provides a unique specification of a voice. You can create such a record with the `MakeVoiceSpec` function and then pass it to the `GetVoiceDescription` function to obtain information about the voice. This information is contained in a voice description record. Or, you can use the `GetVoiceInfo` function to obtain information about the file that stores a voice. This information is contained in a voice file information record.

Speech Manager

By using the `GetSpeechInfo` function, you can obtain information about a speech channel, as well as information about its synthesizer. Such information is returned in speech status information records, speech error information records, and speech version information records.

The `GetSpeechInfo` function also allows you to obtain information about the phonemes defined for a synthesizer. Information about a single phoneme is contained in a phoneme information record. A phoneme descriptor record contains phoneme information records for all of the phonemes that a synthesizer supports.

Synthesizers that use the `GetSpeechInfo` or `SetSpeechInfo` function to allow exploitation of synthesizer-specific features often require that data passed to it be formatted in a particular way. The speech extension data record allows your application to exchange data in any format with a synthesizer.

The `SpeakString`, `SpeakText`, and `SpeakBuffer` functions can process both text and commands embedded in that text. So that commands can be distinguished from text, the commands must be enclosed by command delimiters. The delimiter information record allows your application to change the command delimiters.

Voice Specification Records

A voice specification record provides a unique specification that you must use to obtain information about a voice. You also must use a voice specification record if you wish to create a speech channel that generates speech in a voice other than the current system default voice. The `VoiceSpec` data type defines a voice specification record. In Pascal, the `VoiceSpecPtr` data type defines a pointer to a voice specification record. The `VoiceSpecPtr` data type is not defined in the interface files for C programmers. If you are programming in C and you need to pass a variable of type `VoiceSpecPtr` to a Speech Manager routine, simply pass a pointer to a voice specification record instead.

```

TYPE VoiceSpec =
RECORD
    creator:    OSType;           {ID of required synthesizer}
    id:        OSType;           {ID of voice on the synthesizer}
END;
```

Field descriptions

<code>creator</code>	The synthesizer that is required to use the voice. This is equivalent to the value contained in the <code>synthManufacturer</code> field of a speech version information record and that contained in the <code>synthCreator</code> field of a speech extension data record. The set of <code>OSType</code> values specified entirely by space characters and lowercase letters is reserved.
<code>id</code>	The voice ID of the voice for the synthesizer. Every voice on a synthesizer has a unique ID.

IMPORTANT

To ensure compatibility with future versions of the Speech Manager, you should never fill in the fields of a voice specification record yourself. Instead, you should create a voice specification record by using the `MakeVoiceSpec` function. ▲

Voice Description Records

By calling the `GetVoiceDescription` function, you can obtain information about a voice in a voice description record. The `VoiceDescription` data type defines a voice description record.

```

TYPE VoiceDescription =
RECORD
    length:      LongInt;      {size of record}
    voice:       VoiceSpec;    {voice synthesizer and ID info}
    version:     LongInt;      {version number of voice}
    name:        Str63;        {name of voice}
    comment:     Str255;       {text information about voice}
    gender:      Integer;      {neuter, male, or female}
    age:         Integer;      {approximate age in years}
    script:      Integer;      {script code of text voice can process}
    language:    Integer;      {language code of voice output}
    region:      Integer;      {region code of voice output}
    reserved1:   LongInt;      {always 0--reserved for future use}
    reserved2:   LongInt;      {always 0--reserved for future use}
    reserved3:   LongInt;      {always 0--reserved for future use}
    reserved4:   LongInt;      {always 0--reserved for future use}
END;
```

Field descriptions

<code>length</code>	The size of the voice description record, in bytes.
<code>voice</code>	A voice specification record that uniquely identifies the voice.
<code>version</code>	The version number of the voice.
<code>name</code>	The name of the voice, preceded by a length byte. Names must be 63 characters or less.
<code>comment</code>	Additional text information about the voice. The information might indicate how much memory the voice requires. Some synthesizers use this field to store a phrase that can be spoken.
<code>gender</code>	The gender of the individual represented by the voice. The value in this field must be one of the following constants:

Speech Manager

```

CONST
    kNeuter      = 0;      {neuter voice}
    kMale        = 1;      {male voice}
    kFemale      = 2;      {female voice}

```

	A neuter voice is a voice that is not distinctively male or female.
age	The approximate age in years of the individual represented by the voice.
script	The script code of text that the voice can process.
language	A code that indicates the language of voice output.
region	A code that indicates the region represented by the voice.
reserved1	Reserved.
reserved2	Reserved.
reserved3	Reserved.
reserved4	The four reserved fields are reserved for use by Apple.

Voice File Information Records

A **voice file information record** specifies the file in which a voice is stored and the resource ID of the voice within that file. You can use the `GetVoiceInfo` function to obtain a voice file information record for a voice. The `VoiceFileInfo` data type defines a voice file information record. In Pascal, the `VoiceFileInfoPtr` data type defines a pointer to a voice file information record.

```

TYPE VoiceFileInfo =
RECORD
    fileSpec:  FSSpec;      {volume, dir, and name of file}
    resID:     Integer;     {resource ID of voice in the file}
END;

```

Field descriptions

fileSpec	A file system specification record that contains the volume, directory, and name of the file containing the voice. Generally, files containing a single voice are of type <code>kTextToSpeechVoiceFileType</code> , and files containing multiple voices are of type <code>kTextToSpeechVoiceBundleType</code> .
resID	The resource ID of the voice in the file. Voices are stored in resources of type <code>kTextToSpeechVoiceType</code> .

Speech Status Information Records

By calling the `GetSpeechInfo` function with the `soStatus` selector, you can find out information about the status of a speech channel. This information is stored in a **speech status information record**, which the `SpeechStatusInfo` data type defines.

Speech Manager

```

TYPE SpeechStatusInfo =
RECORD
    outputBusy:      Boolean;      {TRUE if audio is playing }
                                { or text is being processed}
    outputPaused:    Boolean;      {TRUE if channel is paused}
    inputBytesLeft:  LongInt;      {bytes of text left to process}
    phonemeCode:     Integer;      {opcode for current phoneme}
END;

```

Field descriptions

<code>outputBusy</code>	Whether the speech channel is currently producing speech. A speech channel is considered to be producing speech even at some times when no audio data is being produced through the Macintosh speaker. This occurs, for example, when the Speech Manager is processing an input buffer but has not yet initiated speech or when speech output is paused.
<code>outputPaused</code>	Whether speech output in the speech channel has been paused by a call to the <code>PauseSpeechAt</code> function.
<code>inputBytesLeft</code>	The number of input bytes of the text that the speech channel must still process. When <code>inputBytesLeft</code> is 0, the buffer of input text passed to one of the <code>SpeakText</code> or <code>SpeakBuffer</code> functions may be disposed of. (Note that when you call the <code>SpeakString</code> function, the Speech Manager stores a duplicate of the string to be spoken in an internal buffer; thus, you may delete the original string immediately after calling <code>SpeakString</code> .)
<code>phonemeCode</code>	The opcode for the phoneme that the speech channel is currently processing.

Speech Error Information Records

By calling the `GetSpeechInfo` function with the `soErrors` selector, you can obtain a **speech error information record**, which shows what Speech Manager errors occurred while processing a text buffer on a given speech channel. The `SpeechErrorInfo` data type defines a speech error information record.

```

TYPE SpeechErrorInfo =
RECORD
    count:      Integer;      {number of errors since last check}
    oldest:     OSErr;        {oldest unread error}
    oldPos:     LongInt;      {character position of oldest error}
    newest:     OSErr;        {most recent error}
    newPos:    LongInt;      {character position of newest error}
END;

```

Speech Manager

Field descriptions

count	The number of errors that have occurred in processing the current text buffer since the last call to the <code>GetSpeechInfo</code> function with the <code>soErrors</code> selector. Of these errors, you can find information about only the first and last error that occurred.
oldest	The error code of the first error that occurred after the previous call to the <code>GetSpeechInfo</code> function with the <code>soErrors</code> selector.
oldPos	The character position within the text buffer being processed of the first error that occurred after the previous call to the <code>GetSpeechInfo</code> function with the <code>soErrors</code> selector.
newest	The error code of the most recent error.
newPos	The character position within the text buffer being processed of the most recent error.

Speech error information records never include errors that are returned by Speech Manager routines. Instead, they reflect only errors encountered directly in the processing of text, and, in particular, in the processing of commands embedded within text.

The speech error information record keeps track of only the most recent error and the first error that occurred after the previous call to the `GetSpeechInfo` function with the `soErrors` selector. If your application needs to keep track of all errors, then you should install an error callback procedure, as described in “Error Callback Procedure” beginning on page 4-86.

Speech Version Information Records

By calling the `GetSpeechInfo` function with the `soSynthType` selector, you can obtain a **speech version information record**, which provides information about the speech synthesizer currently being used. The `SpeechVersionInfo` data type defines a speech version information record.

```

TYPE SpeechVersionInfo =
RECORD
    synthType:           OSType;           {general synthesizer type}
    synthSubType:       OSType;           {specific synthesizer type}
    synthManufacturer:  OSType;           {synthesizer creator ID}
    synthFlags:         LongInt;         {synthesizer feature flags}
    synthVersion:       NumVersion;      {synthesizer version number}
END;
```

Field descriptions

synthType	The general type of the synthesizer. For the current version of the Speech Manager, this field always contains the value <code>kTextToSpeechSynthType</code> , indicating that the synthesizer converts text into speech.
synthSubType	The specific type of the synthesizer. Currently, no specific types of synthesizer are defined. If you define a new type of synthesizer, you

should register the four-character code for your type with Developer Technical Support.

`synthManufacturer`

A unique identification of a synthesizer engine. If you develop synthesizers, then you should register a different four-character code for each synthesizer you develop with Developer Technical Support. The `creatorID` field of the voice specification record and the `synthCreator` field of a speech extension data record should each be set to the value stored in this field for the desired synthesizer.

`synthFlags`

A set of flags indicating which synthesizer features are activated. The following constants define the bits in this field whose meanings are defined for all synthesizers:

CONST

```
kNoEndingProsody      = 1;
kNoSpeechInterrupt    = 2;
kPreflightThenPause  = 4;
```

The `kNoEndingProsody` flag bit is used to control whether or not the speech synthesizer automatically applies ending prosody, the speech tone and cadence that normally occur at the end of a statement. Under normal circumstances (for example, when the flag bit is not set), ending prosody is applied to the speech when the end of the `textBuf` data is reached. This default behavior can be disabled by setting the `kNoEndingProsody` flag bit.

Some synthesizers do not speak until the `kNoEndingProsody` flag bit is reset, or they encounter a period in the text, or `textBuf` is full.

The `kNoSpeechInterrupt` flag bit is used to control the behavior of `SpeakBuffer` when called on a speech channel that is still busy. When the flag bit is not set, `SpeakBuffer` behaves similarly to `SpeakString` and `SpeakText`. Any speech currently being produced on the specified speech channel is immediately interrupted, and then the new text buffer is spoken. When the `kNoSpeechInterrupt` flag bit is set, however, a request to speak on a channel that is still busy processing a prior text buffer will result in an error. The new buffer is ignored and the error `synthNotReady` is returned. If the prior text buffer has been fully processed, the new buffer is spoken normally. One way of achieving continuous speech without using callback procedures is to continually call `SpeakBuffer` with the `kNoSpeechInterrupt` flag bit set until the function returns `noErr`. The function will then execute as soon as the first text buffer has been processed.

The `kPreflightThenPause` flag bit is used to minimize the latency experienced when the speech synthesizer is attempting to speak. Ordinarily, whenever a call to `SpeakString`, `SpeakText`, or `SpeakBuffer` is made, the speech synthesizer must perform a certain amount of initial processing before speech output is heard. This startup latency can vary from a few milliseconds to several

seconds depending upon which speech synthesizer is being used. Recognizing that larger startup delays might be detrimental to certain applications, a mechanism is provided to allow the synthesizer to perform any necessary computations at noncritical times. Once the computations have been completed, the speech is able to start instantly. When the `kPreflightThenPause` flag bit is set, the speech synthesizer will process the input text as necessary to the point where it is ready to begin producing speech output. At this point, the synthesizer will enter a paused state and return to the caller. When the application is ready to produce speech, it should call the `ContinueSpeech` function to begin speaking.

`synthVersion` The version number of the synthesizer.

Phoneme Information Records

Information about a phoneme is stored in a **phoneme information record**. Ordinarily, you use a phoneme information record to show the user how to enter text to represent a particular phoneme when the 'PHON' input mode is activated. The `PhonemeInfo` data type defines a phoneme information record.

```

TYPE PhonemeInfo =
RECORD
    opCode:      Integer;      {opcode for the phoneme}
    phStr:       Str15;        {corresponding character string}
    exampleStr:  Str31;        {word that shows use of phoneme}
    hiliteStart: Integer;      {offset from beginning of word }
                                { to beginning of phoneme sound}
    hiliteEnd:   Integer;      {offset from beginning of word }
                                { to end of phoneme sound}
END;
```

Field descriptions

<code>opCode</code>	The opcode for the phoneme. For a list of English-language opcodes, see Table 4-3 on page 4-33.
<code>phStr</code>	The string used to represent the phoneme. The string does not necessarily have a phonetic connection to the phoneme, but might simply be an abstract textual representation of it.
<code>exampleStr</code>	An example word that illustrates use of the phoneme.
<code>hiliteStart</code>	The number of characters in the example word that precede the portion of that word representing the phoneme.
<code>hiliteEnd</code>	The number of characters between the beginning of the example word and the end of the portion of that word representing the phoneme.

You might use the information contained in the `hiliteStart` and `hiliteEnd` fields to highlight the characters in the example word that represent the phoneme.

Note that in order to obtain a phoneme information record for an individual phoneme, you must obtain a list of phonemes through a phoneme descriptor record, described next.

Phoneme Descriptor Records

By calling the `GetSpeechInfo` function with the `soPhonemeSymbols` selector, you can obtain a **phoneme descriptor record**, which describes all phonemes defined for the current synthesizer. The `PhonemeDescriptor` data type defines a phoneme descriptor record.

```
TYPE PhonemeDescriptor =
RECORD
    phonemeCount:    Integer;    {number of phonemes defined by current }
                                { synthesizer}
    thePhonemes:    ARRAY[0..0] OF PhonemeInfo;
                                {list of phoneme information records}
END;
```

Field descriptions

<code>phonemeCount</code>	The number of phonemes that the current synthesizer defines. Typically, this will correspond to the number of phonemes in the language supported by the synthesizer.
<code>thePhonemes</code>	An array of phoneme information records.

A common use for a phoneme descriptor record is to provide a graphical display to the user of all available phonemes. Note that such a list would be useful only for a user entering phonemic data directly rather than just entering text.

Speech Extension Data Records

The **speech extension data record** allows you to use the `GetSpeechInfo` and `SetSpeechInfo` functions with selectors defined by particular synthesizers. By requiring that you pass to one of these functions a pointer to a speech extension data record, synthesizers can permit the exchange of data in any format. The `SpeechXtndData` data type defines a speech extension data record.

```
TYPE SpeechXtndData =
RECORD
    synthCreator:    OSType;    {synthesizer creator ID}
                                {data used by synthesizer}
    synthData:       PACKED ARRAY[0..1] OF Char;
END;
```

Field descriptions

<code>synthCreator</code>	The synthesizer's creator ID, identical to the value stored in the <code>synthManufacturer</code> field of a speech version information record.
---------------------------	---

Speech Manager

	You should set this field to the appropriate value before calling <code>GetSpeechInfo</code> or <code>SetSpeechInfo</code> .
<code>synthData</code>	Synthesizer-specific data. The size and format of the data in this field may vary.

Delimiter Information Records

A **delimiter information record** defines the characters used to indicate the beginning and end of a command embedded in text. A delimiter can be one or two characters. The `DelimiterInfo` data type defines a delimiter information record.

```
TYPE DelimiterInfo =
RECORD
    startDelimiter:    PACKED ARRAY[0..1] OF Char;
    endDelimiter:      PACKED ARRAY[0..1] OF Char;
END;
```

Field descriptions

<code>startDelimiter</code>	The start delimiter for an embedded command. By default, the start delimiter is “[”.
<code>endDelimiter</code>	The end delimiter for an embedded command. By default, the end delimiter is “] ”.

Ordinarily, applications that support embedded speech commands should not change the start or end delimiters. However, if for some reason you must change the delimiters, you can use the `SetSpeechInfo` function with the `soCommandDelimiter` selector. For example, you might do this if a text buffer naturally includes the delimiter strings. Before passing such a buffer to the Speech Manager, you can change the delimiter strings to some two-character sequences not used in the buffer and then change the delimiter strings back once processing of the buffer is complete.

If a single-byte delimiter is desired, it should be followed by a `NIL` (0) byte. If the delimiter strings both consist of two `NIL` bytes, embedded command processing is disabled.

Speech Manager Routines

This section describes the routines provided by the Speech Manager. You can use these routines to

- generate speech and then pause or stop it
- obtain information about an individual voice or all voices
- create and dispose of speech channels
- obtain the Speech Manager’s version and status
- change the rate or pitch of speech

Speech Manager

- convert textual into phonetic data
- install a pronunciation dictionary into a speech channel

With the exception of the `SpeechManagerVersion`, `SpeechBusy`, and `SpeechBusySystemWide` functions, all Speech Manager routines return a result code to indicate whether an error has occurred.

The section “Application-Defined Routines” beginning on page 4-82 describes the syntax and operation of application-defined callback procedures.

Starting, Stopping, and Pausing Speech

You can use the `SpeakString` function to generate speech from strings of fewer than 256 characters. The `SpeakText` function also generates speech, but through a speech channel through which you can exert control over the generated speech. The `SpeakBuffer` function includes all the capabilities of `SpeakText` and allows you to set certain flags that control speech behavior.

To stop speech, use the `StopSpeech` function or the `StopSpeechAt` function. The latter provides control over when speech is stopped. To pause and later resume speech, use the `PauseSpeechAt` and `ContinueSpeech` functions.

SpeakString

You can use the `SpeakString` function to have the Speech Manager speak a text string.

```
FUNCTION SpeakString (s: Str255): OSErr;
```

`s` The string to be spoken.

DESCRIPTION

The `SpeakString` function attempts to speak the Pascal-style text string contained in the string `s`. Speech is produced asynchronously using the default system voice. When an application calls this function, the Speech Manager makes a copy of the passed string and creates any structures required to speak it. As soon as speaking has begun, control is returned to the application. The synthesized speech is generated asynchronously to the application so that normal processing can continue while the text is being spoken. No further interaction with the Speech Manager is required at this point, and the application is free to release the memory that the original string occupied.

If `SpeakString` is called while a prior string is still being spoken, the sound currently being synthesized is interrupted immediately. Conversion of the new text into speech is then begun. If you pass a zero-length string (or, in C, a null pointer) to `SpeakString`, the Speech Manager stops any speech previously being synthesized by `SpeakString` without generating additional speech. If your application uses `SpeakString`, it is often a good idea to stop any speech in progress whenever your application receives a

Speech Manager

suspend event. (Note, however, that calling `SpeakString` with a zero-length string has no effect on speech channels other than the one managed internally by the Speech Manager for the `SpeakString` function.)

The text passed to the `SpeakString` function may contain embedded speech commands.

SPECIAL CONSIDERATIONS

Because the `SpeakString` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeakString` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0220000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>memFullErr</code>	-108	Not enough memory to speak
<code>synthOpenFailed</code>	-241	Could not open another speech synthesizer channel

SpeakText

You can use the `SpeakText` function to have the Speech Manager speak a buffer of text.

```
FUNCTION SpeakText (chan: SpeechChannel; textBuf: Ptr;
                   textBytes: LongInt): OSErr;
```

<code>chan</code>	The speech channel through which speech is to be spoken.
<code>textBuf</code>	A pointer to the first byte of text to spoken.
<code>textBytes</code>	The number of bytes of text to spoken.

DESCRIPTION

The `SpeakText` function converts the text stream specified by the `textBuf` and `textBytes` parameters into speech using the voice and control settings for the speech channel `chan`, which should be created with the `NewSpeechChannel` function. The speech is generated asynchronously. This means that control is returned to your application before the speech has finished (and probably even before it has begun). The maximum length of the text buffer that can be spoken is limited only by the available RAM.

Speech Manager

If `SpeakText` is called while the channel is currently busy speaking the contents of a prior text buffer, it immediately stops speaking from the prior buffer and begins speaking from the new text buffer as soon as possible. If you pass a zero-length string (or, in C, a null pointer) to `SpeakText`, the Speech Manager stops all speech currently being synthesized by the speech channel specified in the `chan` parameter without generating additional speech.

▲ **WARNING**

The text buffer must be locked in memory and must not move while the Speech Manager processes it. This buffer is read at interrupt time, and moving it could cause a system crash. If your application defines a text-done callback procedure, then it can move the text buffer or dispose of it once the callback procedure is executed. ▲

SPECIAL CONSIDERATIONS

Because the `SpeakText` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeakText` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0624000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

SpeakBuffer

You can use the `SpeakBuffer` function to have the Speech Manager speak a buffer of text, using certain flags to control speech behavior.

```
FUNCTION SpeakBuffer (chan: SpeechChannel; textBuf: Ptr;
                    textBytes: LongInt;
                    controlFlags: LongInt): OSErr;
```

<code>chan</code>	The speech channel through which speech is to be spoken.
<code>textBuf</code>	A pointer to the first byte of text to spoken.
<code>textBytes</code>	The number of bytes of text to spoken.
<code>controlFlags</code>	Control flags to customize speech behavior.

DESCRIPTION

The `SpeakBuffer` function behaves identically to the `SpeakText` function, but allows control of several speech parameters by setting values of the `controlFlags` parameter. The `controlFlags` parameter relies on the following constants, which may be applied additively:

CONST

```
kNoEndingProsody      = 1;  {disable prosody at end of sentences}
kNoSpeechInterrupt    = 2;  {do not interrupt current speech}
kPreflightThenPause   = 4;  {compute speech without generating}
```

Each constant specifies a flag bit of the `controlFlags` parameter, so by passing the constants additively you can enable multiple capabilities of `SpeakBuffer`. If you pass 0 in the `controlFlags` parameter, `SpeakBuffer` works just like `SpeakText`. By passing `kNoEndingProsody + kNoSpeechInterrupt` in the `controlFlags` parameter, `SpeakBuffer` works like `SpeakText` except that the `kNoEndingProsody` and `kNoSpeechInterrupt` features have been selected. Future versions of the Speech Manager may define additional constants.

The `kNoEndingProsody` flag bit is used to control whether or not the speech synthesizer automatically applies ending prosody, the speech tone and cadence that normally occur at the end of a statement. Under normal circumstances (for example, when the flag bit is not set), ending prosody is applied to the speech when the end of the `textBuf` data is reached. This default behavior can be disabled by setting the `kNoEndingProsody` flag bit.

Some synthesizers do not speak until the `kNoEndingProsody` flag bit is reset, or they encounter a period in the text, or `textBuf` is full.

The `kNoSpeechInterrupt` flag bit is used to control the behavior of `SpeakBuffer` when called on a speech channel that is still busy. When the flag bit is not set, `SpeakBuffer` behaves similarly to `SpeakString` and `SpeakText`. Any speech currently being produced on the specified speech channel is immediately interrupted, and then the new text buffer is spoken. When the `kNoSpeechInterrupt` flag bit is set, however, a request to speak on a channel that is still busy processing a prior text buffer will result in an error. The new buffer is ignored and the error `synthNotReady` is returned. If the prior text buffer has been fully processed, the new buffer is spoken normally. One way of achieving continuous speech without using callback procedures is to continually call `SpeakBuffer` with the `kNoSpeechInterrupt` flag bit set until the function returns `noErr`. The function will then execute as soon as the first text buffer has been processed.

The `kPreflightThenPause` flag bit is used to minimize the latency experienced when the speech synthesizer is attempting to speak. Ordinarily, whenever a call to `SpeakString`, `SpeakText`, or `SpeakBuffer` is made, the speech synthesizer must perform a certain amount of initial processing before speech output is heard. This startup latency can vary from a few milliseconds to several seconds depending upon which speech synthesizer is being used. Recognizing that larger startup delays might be detrimental to certain applications, a mechanism exists to allow the synthesizer to

Speech Manager

perform any necessary computations at noncritical times. Once the computations have been completed, the speech is able to start instantly. When the `kPreflightThenPause` flag bit is set, the speech synthesizer will process the input text as necessary to the point where it is ready to begin producing speech output. At this point, the synthesizer will enter a paused state and return to the caller. When the application is ready to produce speech, it should call the `ContinueSpeech` function to begin speaking.

When the `controlFlags` parameter is set to 0, `SpeakBuffer` behaves identically to `SpeakText`.

SPECIAL CONSIDERATIONS

Because the `SpeakBuffer` function might move memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeakBuffer` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$082800C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>synthNotReady</code>	-242	Speech channel is still busy speaking
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

StopSpeech

You can use the `StopSpeech` function to terminate speech immediately on a specified channel.

```
FUNCTION StopSpeech (chan: SpeechChannel): OSErr;
```

`chan` The speech channel on which speech is to be stopped.

DESCRIPTION

The `StopSpeech` function immediately terminates speech on the channel specified by the `chan` parameter. After returning from `StopSpeech`, your application can safely release any text buffer that the speech synthesizer has been using. You can call `StopSpeech` for an already idle channel without ill effect.

You can also stop speech by passing a zero-length string (or, in C, a null pointer) to one of the `SpeakString`, `SpeakText`, or `SpeakBuffer` functions. Doing this stops speech

Speech Manager

only in the specified speech channel (or, in the case of `SpeakString`, in the speech channel managed internally by the Speech Manager).

SPECIAL CONSIDERATIONS

Because the `StopSpeech` function might move or purge memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `StopSpeech` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$022C000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

SEE ALSO

Before calling the `StopSpeech` function, you can use the `SpeechBusy` function, which is described on page 4-72, to determine if a synthesizer is still speaking. If you are working with multiple speech channels, you can use the status selector with the routine `GetSpeechInfo` which is described on page 4-77, to determine if a specific channel is still speaking.

StopSpeechAt

You can use the `StopSpeechAt` function to terminate speech delivery on a specified channel either immediately or at the end of the current word or sentence.

```
FUNCTION StopSpeechAt (chan: SpeechChannel; whereToStop: LongInt)
                    : OSErr;
```

`chan` The speech channel on which speech is to be stopped.

`whereToStop` A constant indicating when speech processing should stop. Pass the constant `kImmediate` to stop immediately, even in the middle of a word. Pass `kEndOfWord` or `kEndOfSentence` to stop speech at the end of the current word or sentence, respectively.

DESCRIPTION

The `StopSpeechAt` function halts the production of speech on the channel specified by `chan` at a specified point in the text. This routine returns immediately, although speech output continues until the specified point has been reached.

▲ WARNING

If you call the `StopSpeechAt` function before the Speech Manager finishes processing input text, then the function might return before some input text has yet to be spoken. Thus, before disposing of the text buffer, your application should wait until its text-done callback procedure has been called (if one has been defined), or until it can determine (by, for example obtaining a speech status information record) that the Speech Manager is no longer processing input text. ▲

If the end of the input text buffer is reached before the specified stopping point, the speech synthesizer stops at the end of the buffer without generating an error.

SPECIAL CONSIDERATIONS

Because the `StopSpeechAt` function might move or purge memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `StopSpeechAt` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0430000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

PauseSpeechAt

You can use the `PauseSpeechAt` function to pause speech on a speech channel.

```
FUNCTION PauseSpeechAt (chan: SpeechChannel; whereToStop: LongInt)
                        : OSErr;
```

`chan` The speech channel on which speech is to be paused.

`whereToStop`

A constant indicating when speech processing should be paused. Pass the constant `kImmediate` to pause immediately, even in the middle of a word. Pass `kEndOfWord` or `kEndOfSentence` to pause speech at the end of the current word or sentence, respectively.

DESCRIPTION

The `PauseSpeechAt` function makes speech production pause at a specified point in the text. `PauseSpeechAt` returns immediately, although speech output will continue until the specified point.

You can determine whether your application has paused speech output on a speech channel by obtaining a speech status information record through the `GetSpeechInfo` function. While a speech channel is paused, the speech status information record indicates that `outputBusy` and `outputPaused` are both `TRUE`.

If the end of the input text buffer is reached before the specified pause point, speech output pauses at the end of the buffer.

The `PauseSpeechAt` function differs from the `StopSpeech` and `StopSpeechAt` functions in that a subsequent call to `ContinueSpeech`, described next, causes the contents of the current text buffer to continue being spoken.

▲ WARNING

If you plan to continue speech synthesis from a paused speech channel, the text buffer being processed must remain available at all times and must not move while the channel is in a paused state. ▲

SPECIAL CONSIDERATIONS

Because the `PauseSpeechAt` function might move or purge memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `PauseSpeechAt` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0434000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

ContinueSpeech

You can use the `ContinueSpeech` function to resume speech paused by the `PauseSpeechAt` function.

```
FUNCTION ContinueSpeech (chan: SpeechChannel): OSErr;
```

`chan` The paused speech channel on which speech is to be resumed.

DESCRIPTION

At any time after the `PauseSpeechAt` function is called, the `ContinueSpeech` function can be called to continue speaking from the beginning of the word in which speech paused. Calling `ContinueSpeech` on a channel that is not currently in a paused state has no effect on the speech channel or on future calls to the `PauseSpeechAt` function. If you call `ContinueSpeech` on a channel before a pause is effective, `ContinueSpeech` cancels the pause.

If the `PauseSpeechAt` function stopped speech in the middle of a word, the Speech Manager will start speaking that word from the beginning when you call `ContinueSpeech`.

SPECIAL CONSIDERATIONS

Because the `ContinueSpeech` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `ContinueSpeech` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0238000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

Obtaining Information About Voices

Specification of a voice requires a voice specification record. When you already know the creator and ID for a voice, you should use the `MakeVoiceSpec` function to create such a record rather than filling in the fields of one directly. To obtain information about all available voices, use the `CountVoices` function to determine how many voices are available, and the `GetIndVoice` function to obtain a voice specification record corresponding to each voice.

Having created a voice specification record, you can obtain information about the voice to which it corresponds. The `GetVoiceDescription` function provides information about a voice in the form of a voice description record. In addition to duplicating the capabilities of the `GetVoiceDescription` function, the `GetVoiceInfo` function allows you to obtain information about where on disk a voice is stored.

MakeVoiceSpec

To set the fields of a voice specification record, you should use the `MakeVoiceSpec` function. You should never set the fields of such a record directly.

```
FUNCTION MakeVoiceSpec (creator: OSType; id: OSType;
                       voice: VoiceSpecPtr): OSErr;
```

<code>creator</code>	The ID of the synthesizer that your application requires.
<code>id</code>	The ID of the voice on the synthesizer specified by the <code>creator</code> parameter.
<code>voice</code>	A pointer to the voice specification record whose fields are to be filled in.

DESCRIPTION

A voice specification record is a unique voice ID used by the Speech Manager. Most voice management routines expect to be passed a pointer to a voice specification record. When you already know the creator and ID for a voice, you should use the `MakeVoiceSpec` function to create such a record rather than filling in the fields of one directly. On exit, the voice specification record pointed to by the `voice` parameter contains the appropriate values.

SPECIAL CONSIDERATIONS

You can call the `MakeVoiceSpec` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `MakeVoiceSpec` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0604000C</code>

RESULT CODES

<code>noErr</code>	0	No error
--------------------	---	----------

CountVoices

You can determine how many voices are available by calling the `CountVoices` function.

```
FUNCTION CountVoices (VAR numVoices: Integer): OSErr;
```

<code>numVoices</code>	On exit, the number of voices that the application can use.
------------------------	---

DESCRIPTION

The `CountVoices` function returns, in the `numVoices` parameter, the number of voices available. The application can then use this information to call the `GetIndVoice` function, described next, to obtain voice specification records for one or more of the voices.

Each time `CountVoices` is called, the Speech Manager searches for new voices.

SPECIAL CONSIDERATIONS

Because the `CountVoices` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `CountVoices` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0108000C</code>

RESULT CODES

<code>noErr</code>	<code>0</code>	No error
--------------------	----------------	----------

GetIndVoice

You can obtain a voice specification record for a voice by passing an index to the `GetIndVoice` function.

```
FUNCTION GetIndVoice (index: Integer; voice: VoiceSpecPtr): OSErr;
```

<code>index</code>	The index of the voice for which to obtain a voice specification record. This number must range from 1 to the total number of voices, as returned by the <code>CountVoices</code> function.
<code>voice</code>	A pointer to the voice specification record whose fields are to be filled in.

DESCRIPTION

The `GetIndVoice` function returns, in the voice specification record pointed to by the `voice` parameter, a specification of the voice whose index is provided in the `index` parameter. Your application should make no assumptions about the order in which voices are indexed.

Speech Manager

▲ **WARNING**

Your application should not add, remove, or modify a voice and then call the `GetIndVoice` function with an index value other than 1. To allow the Speech Manager to update its information about voices, your application should always either call the `CountVoices` function or call the `GetIndVoice` function with an index value of 1 after adding, removing, or modifying a voice or after a time at which the user might have done so. ▲

If you specify an index value beyond the number of available voices, the `GetIndVoice` function returns a `voiceNotFound` error.

SPECIAL CONSIDERATIONS

Because the `GetIndVoice` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetIndVoice` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$030C000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>voiceNotFound</code>	-244	Voice resource not found

GetVoiceDescription

You can obtain a description of a voice by using the `GetVoiceDescription` function.

```
FUNCTION GetVoiceDescription (voice: VoiceSpecPtr;
                             info: VoiceDescriptionPtr;
                             infoLength: LongInt): OSErr;
```

<code>voice</code>	A pointer to the voice specification record identifying the voice to be described, or <code>NULL</code> to obtain a description of the system default voice.
<code>info</code>	A pointer to a voice description record. If this parameter is <code>NULL</code> , the function does not fill in the fields of the voice description record; instead, it simply determines whether the <code>voice</code> parameter specifies an available voice and, if not, returns a <code>voiceNotFound</code> error.

Speech Manager

`infoLength`

The length, in bytes, of the voice description record. In the current version of the Speech Manager, the voice description record contains 362 bytes. However, you should always use the `sizeof` function to determine the length of this record.

DESCRIPTION

The `GetVoiceDescription` function fills out the voice description record pointed to by the `info` parameter with the correct information for the voice specified by the `voice` parameter. It fills in the `length` field of the voice description record with the number of bytes actually copied. This value will always be less than or equal to the value that your application passes in `infoLength` before calling `GetVoiceDescription`. This scheme allows applications targeted for the current version of the Speech Manager to work on future versions that might have longer voice description records; it also allows you to write code for future versions of the Speech Manager that will also run on computers that support only the current version.

If the voice specification record does not identify an available voice, `GetVoiceDescription` returns a `voiceNotFound` error.

SPECIAL CONSIDERATIONS

Because the `GetVoiceDescription` function moves memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetVoiceDescription` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0610000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>paramErr</code>	-50	Parameter error
<code>memFullErr</code>	-108	Not enough memory to load voice into memory
<code>voiceNotFound</code>	-244	Voice resource not found

GetVoiceInfo

You can use the `GetVoiceInfo` function to obtain the same information about a voice that the `GetVoiceDescription` function provides or to determine in which file and

Speech Manager

resource a voice is stored. This function is intended primarily for use by synthesizers, but an application can call it too.

```
FUNCTION GetVoiceInfo (voice: VoiceSpecPtr; selector: OSType;
                      voiceInfo: Ptr): OSErr;
```

voice A pointer to the voice specification record identifying the voice about which your application requires information, or `NIL` to obtain information on the system default voice.

selector A specification of the type of data being requested. For current versions of the Speech Manager, you should set this field either to `soVoiceDescription`, if you would like to use the `GetVoiceInfo` function to mimic the `GetVoiceDescription` function, or to `soVoiceFile`, if you would like to obtain information about the location of a voice on disk.

voiceInfo A pointer to the appropriate data structure. If the selector is `soVoiceDescription`, then `voiceInfo` should be a pointer to a voice description record, and the `length` field of the record should be set to the length of the voice description record. If the selector is `soVoiceFile`, then `voiceInfo` should be a pointer to a voice file information record.

DESCRIPTION

The `GetVoiceInfo` function accepts a selector in the `selector` parameter that determines the type of information you wish to obtain about the voice specified in the `voice` parameter. The function then fills the fields of the data structure appropriate to the selector you specify in the `voiceInfo` parameter.

If the voice specification is invalid, `GetVoiceInfo` returns a `voiceNotFound` error. If there is not enough memory to load the voice into memory to obtain information about it, `GetVoiceInfo` returns the result code `memFullErr`.

SPECIAL CONSIDERATIONS

Because the `GetVoiceInfo` function might move memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetVoiceInfo` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0614000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>memFullErr</code>	-108	Not enough memory to load voice into memory
<code>voiceNotFound</code>	-244	Voice resource not found

Managing Speech Channels

To take advantage of any but the most rudimentary of the Speech Manager's capabilities, you need to use speech channels. However, you cannot create a speech channel simply by declaring a variable of type `SpeechChannel`. Before your application calls any routine that requires a speech channel as a parameter, you must call the `NewSpeechChannel` function to allow the Speech Manager to allocate memory associated with the speech channel. Later, you can release the memory occupied by a speech channel by calling the `DisposeSpeechChannel` function. In general, it is a good idea to create a speech channel just before you need it and then dispose of it as soon as you have finished processing speech through it.

NewSpeechChannel

You can use the `NewSpeechChannel` function to create a new speech channel.

```
FUNCTION NewSpeechChannel (voice: VoiceSpecPtr;
                           VAR chan: SpeechChannel): OSErr;
```

<code>voice</code>	A pointer to the voice specification record corresponding to the voice to be used for the new speech channel. Pass <code>NIL</code> to create a speech channel using the system default voice.
<code>chan</code>	On exit, a valid speech channel.

DESCRIPTION

The `NewSpeechChannel` function allocates memory for a speech channel record and sets the speech channel variable pointed to by the `chan` parameter to point to this speech channel record. The Speech Manager automatically locates and opens a connection to the proper synthesizer for the voice specified by the `voice` parameter.

There is no predefined limit to the number of speech channels an application can create. However, system constraints on available RAM, processor loading, and number of available sound channels limit the number of speech channels actually possible.

▲ WARNING

Your application should not attempt to manipulate the data pointed to by a variable of type `SpeechChannel`. The internal format that the Speech Manager uses for speech channel data is not documented and may change in future versions of system software. ▲

SPECIAL CONSIDERATIONS

Because the `NewSpeechChannel` function allocates memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `NewSpeechChannel` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0418000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>memFullErr</code>	-108	Not enough memory to open speech channel
<code>synthOpenFailed</code>	-241	Could not open another speech synthesizer channel
<code>voiceNotFound</code>	-244	Voice resource not found

DisposeSpeechChannel

You can use the `DisposeSpeechChannel` function to dispose of an existing speech channel.

```
FUNCTION DisposeSpeechChannel (chan: SpeechChannel): OSErr;
```

`chan` The speech channel to dispose of.

DESCRIPTION

The `DisposeSpeechChannel` function disposes of the speech channel specified in the `chan` parameter and releases all memory the channel occupies. If the speech channel specified is producing speech, then the `DisposeSpeechChannel` function immediately stops speech before disposing of the channel. If you have defined a text-done callback procedure or a speech-done callback procedure, the procedure will not be called before the channel is disposed of.

The Speech Manager releases any speech channels that have not been explicitly disposed of by an application when the application quits. In general, however, your application should dispose of any speech channels it has created whenever it receives a suspend event. This ensures that other applications can take full advantage of Speech Manager and Sound Manager capabilities.

SPECIAL CONSIDERATIONS

Because the `DisposeSpeechChannel` function might purge memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `DisposeSpeechChannel` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$021C000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

Obtaining Information About Speech

Once you have determined with the Gestalt Manager that the Speech Manager is present, you can use the `SpeechManagerVersion` function to determine what version is available.

To determine how many speech channels are currently processing speech in your application, you can use the `SpeechBusy` function. To determine how many are processing speech in your application and other processes, you can use the `SpeechBusySystemWide` function.

SpeechManagerVersion

You can use the `SpeechManagerVersion` function to determine the current version of the Speech Manager installed in the system.

```
FUNCTION SpeechManagerVersion: NumVersion;
```

DESCRIPTION

The `SpeechManagerVersion` function returns the version of the Speech Manager installed in the system, in the format of the first 4 bytes of a 'vers' resource. You can use this call to determine whether your program can access features of the Speech Manager that are included in some Speech Manager releases but not in earlier ones. Note, however, that because this chapter documents the initial release of the Speech Manager, all features and techniques described in this chapter should be available in all versions of the Speech Manager.

SPECIAL CONSIDERATIONS

You can call the `SpeechManagerVersion` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeechManagerVersion` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0000000C</code>

SpeechBusy

You can use the `SpeechBusy` function to determine whether any channels of speech are currently synthesizing speech.

```
FUNCTION SpeechBusy: Integer;
```

DESCRIPTION

The `SpeechBusy` function returns the number of speech channels that are currently synthesizing speech in the application. This is useful when you want to ensure that an earlier speech request has been completed before having the system speak again. Note that paused speech channels are counted among those that are synthesizing speech.

The speech channel that the Speech Manager allocates internally in response to calls to the `SpeakString` function is counted in the number returned by `SpeechBusy`. Thus, if you use just `SpeakString` to initiate speech, `SpeechBusy` always returns 1 as long as speech is being produced. When `SpeechBusy` returns 0, all speech has finished.

SPECIAL CONSIDERATIONS

You can call the `SpeechBusy` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeechBusy` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$003C000C</code>

SpeechBusySystemWide

You can use the `SpeechBusySystemWide` function to determine if any speech is currently being synthesized in your application or elsewhere on the computer.

```
FUNCTION SpeechBusySystemWide: Integer;
```

DESCRIPTION

The `SpeechBusySystemWide` function returns the total number of speech channels currently synthesizing speech on the computer, whether they were initiated by your application or process's code or by some other process executing concurrently. Note that paused speech channels are counted among those channels that are synthesizing speech.

This function is useful when you want to ensure that no speech is currently being produced anywhere on the Macintosh computer before initiating speech. Although the Speech Manager allows different applications to produce speech simultaneously, this can be confusing to the user. As a result, it is often a good idea for your application to check that no other process is producing speech before producing speech itself. If the difference between the values returned by `SpeechBusySystemWide` and the `SpeechBusy` function is 0, no other process is producing speech.

SPECIAL CONSIDERATIONS

You can call the `SpeechBusySystemWide` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SpeechBusySystemWide` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0040000C</code>

Changing Speech Attributes

To determine the rate and pitch at which a speech channel is processing text, you can use the `GetSpeechRate` and `GetSpeechPitch` functions. The `SetSpeechRate` and `SetSpeechPitch` functions allow you to change rate and pitch.

The most robust of the Speech Manager's routines are the `GetSpeechInfo` and `SetSpeechInfo` functions. These allow you to obtain many types of information about a speech channel and to change many settings of a speech channel. To specify the operation that you wish to perform, you must pass `GetSpeechInfo` or `SetSpeechInfo` a selector. A full list of selectors is provided in "Speech Information Selectors" beginning on page 4-39.

GetSpeechRate

You use the `GetSpeechRate` function to obtain a speech channel's current speech rate.

```
FUNCTION GetSpeechRate (chan: SpeechChannel; VAR rate: Fixed)
                    : OSErr;
```

`chan` The speech channel whose rate you wish to determine.

Speech Manager

`rate` On exit, the speech channel's speech rate, expressed as a fixed-point, words-per-minute value.

DESCRIPTION

The `GetSpeechRate` function returns, in the `rate` parameter, the speech rate of the speech channel specified by the `chan` parameter.

SPECIAL CONSIDERATIONS

You can call the `GetSpeechRate` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetSpeechRate` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0448000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

SetSpeechRate

You can set the speech rate of a designated speech channel with the `SetSpeechRate` function.

```
FUNCTION SetSpeechRate (chan: SpeechChannel; rate: Fixed): OSErr;
```

`chan` The speech channel whose rate you wish to set.

`rate` The new speech rate for the speech channel, expressed as a fixed-point, words-per-minute value.

DESCRIPTION

The `SetSpeechRate` function adjusts the speech rate on the speech channel specified by the `chan` parameter to the rate specified by the `rate` parameter. As a general rule, typical speaking rates range from around 150 words per minute to around 180 words per minute. It is important to keep in mind, however, that users will differ greatly in their ability to understand synthesized speech at a particular rate based upon their level of experience listening to the voice and their ability to anticipate the types of utterances they will encounter.

SPECIAL CONSIDERATIONS

You can call the `SetSpeechRate` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SetSpeechRate` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0444000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

GetSpeechPitch

You can determine a speech channel's current speech pitch by using the `GetSpeechPitch` function.

```
FUNCTION GetSpeechPitch (chan: SpeechChannel; VAR pitch: Fixed)
                        : OSErr;
```

<code>chan</code>	The speech channel whose pitch you wish to determine.
<code>pitch</code>	On exit, the current pitch of the voice in the speech channel, expressed as a fixed-point frequency value.

DESCRIPTION

The `GetSpeechPitch` function returns, in the `pitch` parameter, the pitch of the speech channel specified by the `chan` parameter. Typical voice frequencies range from around 90 hertz for a low-pitched male voice to perhaps 300 hertz for a high-pitched child's voice. These frequencies correspond to approximate pitch values in the ranges of 30.000 to 40.000 and 55.000 to 65.000, respectively. For information about the mathematical relationship between pitches and frequencies expressed in hertz, see "Speech Attributes" beginning on page 4-6.

SPECIAL CONSIDERATIONS

You can call the `GetSpeechPitch` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetSpeechPitch` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0450000C</code>

RESULT CODES

noErr	0	No error
invalidComponentID	-3000	Speech channel is uninitialized or bad

SetSpeechPitch

You can use the `SetSpeechPitch` function to set the speech pitch on a designated speech channel.

```
FUNCTION SetSpeechPitch (chan: SpeechChannel; pitch: Fixed)
                        : OSErr;
```

`chan` The speech channel whose pitch you wish to set.
`pitch` The new pitch for the speech channel, expressed as a fixed-point frequency value.

DESCRIPTION

The `SetSpeechPitch` function changes the current speech pitch on the speech channel specified by the `chan` parameter to the pitch specified by the `pitch` parameter. Typical voice frequencies range from around 90 hertz for a low-pitched male voice to perhaps 300 hertz for a high-pitched child's voice. These frequencies correspond to approximate pitch values in the ranges of 30.000 to 40.000 and 55.000 to 65.000, respectively. For information about the mathematical relationship between pitches and frequencies expressed in hertz, see "Speech Attributes" beginning on page 4-6. Although fixed-point values allow you to specify a wide range of pitches, not all synthesizers will support the full range of pitches. If your application specifies a pitch that a synthesizer cannot handle, it may adjust the pitch to fit within an acceptable range.

SPECIAL CONSIDERATIONS

You can call the `SetSpeechPitch` function at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SetSpeechPitch` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$044C000C</code>

RESULT CODES

noErr	0	No error
invalidComponentID	-3000	Speech channel is uninitialized or bad

GetSpeechInfo

You can use the `GetSpeechInfo` function to obtain information about a designated speech channel.

```
FUNCTION GetSpeechInfo (chan: SpeechChannel; selector: OSType;
                       speechInfo: Ptr): OSErr;
```

`chan` The speech channel about which information is being requested.

`selector` A speech information selector that indicates the type of information being requested.

`speechInfo` A pointer whose meaning depends on the speech information selector specified in the `selector` parameter.

DESCRIPTION

The `GetSpeechInfo` function returns, in the data structure pointed to by the `speechInfo` parameter, the type of information requested by the `selector` parameter as it applies to the speech channel specified in the `chan` parameter.

The format of the data structure specified by the `speechInfo` parameter depends on the selector you choose. For example, a selector might require that your application allocate a block of memory of a certain size and pass a pointer to that block. Another selector might require that `speechInfo` be set to the address of a handle variable. In this case, the `GetSpeechInfo` function would allocate a relocatable block of memory and change the handle variable specified to reference the block.

SPECIAL CONSIDERATIONS

You can call the `GetSpeechInfo` function at interrupt time only if the speech information selector specified in the `selector` parameter does not move or purge memory.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `GetSpeechInfo` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0658000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>siUnknownInfoType</code>	-231	Feature is not implemented on synthesizer
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

SEE ALSO

For a complete list of speech information selectors, see “Speech Information Selectors” beginning on page 4-39. This list indicates how your application should set the `speechInfo` parameter for each selector and indicates which selectors might cause memory to be moved or purged.

SetSpeechInfo

You can use the `SetSpeechInfo` function to change a setting of a particular speech channel.

```
FUNCTION SetSpeechInfo (chan: SpeechChannel; selector: OSType;
                       speechInfo: Ptr): OSErr;
```

`chan` The speech channel for which your application wishes to change a setting.

`selector` A speech information selector that indicates the type of information being changed.

`speechInfo` A pointer whose meaning depends on the speech information selector specified in the `selector` parameter.

DESCRIPTION

The `SetSpeechInfo` function changes the type of setting indicated by the `selector` parameter in the speech channel specified by the `chan` parameter, based on the data your application provides via the `speechInfo` parameter.

The format of the data structure specified by the `speechInfo` parameter depends on the selector you choose. Ordinarily, a selector requires that `speechInfo` be a pointer to a data structure that specifies a new setting for the speech channel.

SPECIAL CONSIDERATIONS

You can call the `SetSpeechInfo` function at interrupt time only if the speech information selector specified in the `selector` parameter does not move or purge memory.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `SetSpeechInfo` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0654000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>paramErr</code>	-50	Parameter value is invalid
<code>siUnknownInfoType</code>	-231	Feature is not implemented on synthesizer
<code>incompatibleVoice</code>	-245	Specified voice cannot be used with synthesizer
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

SEE ALSO

For a complete list of speech information selectors, see “Speech Information Selectors” beginning on page 4-39. This list indicates how your application should set the `speechInfo` parameter for each selector and indicates which selectors might cause memory to be moved or purged.

Converting Text To Phonemes

The Speech Manager provides a utility routine, the `TextToPhonemes` function, to convert textual data into phonetic data. This is particularly useful during application development, when you might wish to adjust phrases that your application generates to produce smoother speech. By first converting the target phrase into phonemes, you can see what the synthesizer will try to speak. Then you need correct only the parts that would not have been spoken the way you want.

TextToPhonemes

You can use the `TextToPhonemes` function to convert textual data into phonemic data.

```
FUNCTION TextToPhonemes (chan: SpeechChannel; textBuf: Ptr;
                        textBytes: LongInt; phonemeBuf: Handle;
                        VAR phonemeBytes: LongInt): OSErr;
```

<code>chan</code>	A speech channel whose associated synthesizer and voice are to be used for the conversion process.
<code>textBuf</code>	A pointer to a buffer of text to be converted.
<code>textBytes</code>	The number of bytes of text to be converted.
<code>phonemeBuf</code>	A handle to a buffer to be used to store the phonemic data. The <code>TextToPhonemes</code> function may resize the relocatable block referenced by this handle.
<code>phonemeBytes</code>	On exit, the number of bytes of phonemic data written to the handle.

DESCRIPTION

The `TextToPhonemes` function converts the `textBytes` bytes of textual data pointed to by the `textBuf` parameter to phonemic data, which it writes into the relocatable block specified by the `phonemeBuf` parameter. If necessary, `TextToPhonemes` resizes this relocatable block. The `TextToPhonemes` function sets the `phonemeBytes` parameter to the number of bytes of phonetic data actually written.

▲ WARNING

If the textual data is contained in a relocatable block, a handle to that block must be locked before the `TextToPhonemes` function is called. ▲

The data returned by `TextToPhonemes` corresponds precisely to the phonemes that would be spoken had the input text been sent to `SpeakText` instead. All current mode settings for the speech channel specified by `chan` are applied to the converted speech. No callbacks are generated while the `TextToPhonemes` routine is generating its output.

SPECIAL CONSIDERATIONS

Because the `TextToPhonemes` function might move memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `TextToPhonemes` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0A5C000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>paramErr</code>	-50	Parameter value is invalid
<code>nilHandleErr</code>	-109	Handle argument is NIL
<code>siUnknownInfoType</code>	-231	Feature not implemented on synthesizer
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

Installing a Pronunciation Dictionary

Pronunciation dictionaries allow your application to override the default Speech Manager pronunciations of individual words, such as names with quirky spellings. The `UseDictionary` function allows your application to load a pronunciation dictionary into a speech channel.

UseDictionary

You can use the `UseDictionary` function to install a designated dictionary into a speech channel.

```
FUNCTION UseDictionary (chan: SpeechChannel; dictionary: Handle)
                        : OSErr;
```

`chan` The speech channel into which a dictionary is to be installed.

`dictionary` A handle to the dictionary data. This is often a handle to a resource of type 'dict'.

DESCRIPTION

The `UseDictionary` function attempts to install the dictionary data referenced by the `dictionary` parameter into the speech channel referenced by the `chan` parameter. The synthesizer will use whatever elements of the dictionary resource it considers useful to the speech conversion process. Some speech synthesizers might ignore certain types of dictionary entries.

After the `UseDictionary` function returns, your application is free to release any storage allocated for the dictionary handle. The search order for application-provided dictionaries is last-in, first-searched.

All details of how an application-provided dictionary is represented within the speech synthesizer are dependent on the specific synthesizer implementation and are private to the synthesizer.

SPECIAL CONSIDERATIONS

Because the `UseDictionary` function might move memory, you should not call it at interrupt time.

ASSEMBLY-LANGUAGE INFORMATION

The trap macro and routine selector for the `UseDictionary` function are

Trap macro	Selector
<code>_SoundDispatch</code>	<code>\$0460000C</code>

RESULT CODES

<code>noErr</code>	0	No error
<code>memFullErr</code>	-108	Not enough memory to use new dictionary
<code>badDictFormat</code>	-246	Pronunciation dictionary format error
<code>invalidComponentID</code>	-3000	Speech channel is uninitialized or bad

SEE ALSO

For a description of the format of a pronunciation dictionary, see “The Pronunciation Dictionary Resource” on page 4-89. For a discussion of how you might manipulate a dictionary in memory, see “Including Pronunciation Dictionaries” beginning on page 4-36.

Application-Defined Routines

The Speech Manager allows you to define callback procedures that execute

- when text input processing is complete (but not necessarily after speech has stopped)
- when text has been completely processed and spoken
- whenever the Speech Manager encounters an embedded synchronization command
- whenever the Speech Manager encounters an error in processing embedded speech commands
- whenever a phoneme is about to be spoken
- whenever a word is about to be spoken

▲ **WARNING**

When the Speech Manager executes a callback procedure, the Speech Manager sets the A5 register to the value specified by the most recent call to the `SetSpeechInfo` function with the `soCurrentA5` selector. However, if the most recent value specified with the `soCurrentA5` selector is `NIL` or if your application has not yet specified a value, then the Speech Manager leaves the A5 register unchanged. In this case, the callback procedure cannot access application global variables because it executes at interrupt time. For code showing how to use the `soCurrentA5` selector to ensure that the A5 register is set to your application’s A5, see Listing 4-6 on page 4-21. ▲

Text-Done Callback Procedure

You can specify a text-done callback procedure by passing the `soTextDoneCallback` selector to the `SetSpeechInfo` function.

MyTextDoneCallback

A text-done callback procedure has the following syntax:

```
PROCEDURE MyTextDoneCallback
    (chan: SpeechChannel; refCon: LongInt;
    VAR nextBuf: Ptr; VAR byteLen: LongInt;
    VAR controlFlags: LongInt);
```


Speech Manager

<code>chan</code>	The speech channel that has finished processing input text.
<code>refCon</code>	The reference constant associated with the speech channel.
<code>nextBuf</code>	On exit, a pointer to the next buffer of text to process or <code>NIL</code> if your application has no additional text to be spoken. This parameter is mostly for internal use by the Speech Manager.
<code>byteLen</code>	On exit, the number of bytes of the text buffer pointed to by the <code>nextBuf</code> parameter.
<code>controlFlags</code>	On exit, the control flags to be used in generating the next buffer of text.

DESCRIPTION

If a text-done callback procedure is installed in a speech channel, then the Speech Manager calls this procedure when it finishes processing a buffer of text. The Speech Manager might not yet have completed finishing speaking the text and indeed might not have started speaking it.

A common use of a text-done callback procedure is to alert your application once the text passed to the `SpeakText` or `SpeakBuffer` function can be disposed of (or, when the text is contained within a locked relocatable block, when the relocatable block can be unlocked). The Speech Manager copies the text you pass to the `SpeakText` or `SpeakBuffer` function into an internal buffer. Once it has finished processing the text, you may dispose of the original text buffer, even if speech is not yet complete. However, if you wish to write a callback procedure that executes when speech is completed, see the definition of a speech-done callback procedure below.

Although most applications won't need to, your callback procedure can indicate to the Speech Manager whether there is another buffer of text to speak. If there is another buffer, your callback procedure should reference it by setting the `nextBuf` and `byteLen` parameters to appropriate values. (Your callback procedure might also change the control flags to be used to process the speech by altering the value in the `controlFlags` parameter.) Setting these parameters allows the Speech Manager to generate uninterrupted speech. If there is no more text to speak, your callback procedure should set `nextBuf` to `NIL`. In this case, the Speech Manager ignores the `byteLen` and `controlFlags` parameters.

If your text-done callback procedure does not change the values of the `nextBuf` and `byteLen` parameters, the text buffer just spoken will be spoken again.

SPECIAL CONSIDERATIONS

Because your callback procedure executes at interrupt time, you must not call any routines that might move or purge memory. If you are writing a callback procedure so that your application will know when it can dispose of a text buffer, then use the callback procedure to set a global flag variable. Your application's main event loop can check this flag and dispose of the text buffer if it is set.

Your callback procedure is able to access application global variables only if the A5 register is properly set. The Speech Manager sets A5 to the proper value if you provide

Speech Manager

your application's A5 value by calling the `SetSpeechInfo` function with the `soCurrentA5` selector.

ASSEMBLY-LANGUAGE INFORMATION

Because a callback procedure is called at interrupt time, it must preserve all registers other than A0–A2 and D0–D2.

Speech-Done Callback Procedure

You can specify a speech-done callback procedure by passing the `soSpeechDoneCallback` selector to the `SetSpeechInfo` function.

MySpeechDoneCallback

A speech-done callback procedure has the following syntax:

```
PROCEDURE MySpeechDoneCallback (chan: SpeechChannel;
                                refCon: LongInt);
```

`chan` The speech channel that has finished processing input text.
`refCon` The reference constant associated with the speech channel.

DESCRIPTION

If a speech-done callback procedure is installed in a speech channel, then the Speech Manager calls this procedure when it finishes speaking a buffer of text.

You might use a speech-done callback procedure if you need to update some visual indicator that shows what text is currently being spoken. For example, suppose your application passes text buffers to the Speech Manager one paragraph at a time. Your speech-done callback procedure might set a global flag variable to indicate to the application that the Speech Manager has finished speaking a paragraph. When a routine called by your application's main event loop checks the global flag variable and determines that it has been set, the routine might ensure that the next paragraph of text is visible.

You might use a speech-done callback procedure to set a flag variable that alerts the application that it should pass a new buffer of text to the Speech Manager. If you do so, however, there might be a noticeable pause as the Speech Manager switches from processing one text buffer to another. Ordinarily, it is easier to achieve this goal by using a text-done callback procedure, as described earlier.

SPECIAL CONSIDERATIONS

Because your callback procedure executes at interrupt time, you must not call any routines that might move or purge memory.

Your callback procedure is able to access application global variables only if the A5 register is properly set. The Speech Manager sets A5 to the proper value if you provide your application's A5 value by calling the `SetSpeechInfo` function with the `soCurrentA5` selector.

ASSEMBLY-LANGUAGE INFORMATION

Because a callback procedure is called at interrupt time, it must preserve all registers other than A0–A2 and D0–D2.

Synchronization Callback Procedure

You can specify a synchronization callback procedure by passing the `soSyncCallBack` selector to the `SetSpeechInfo` function and embedding a synchronization command within a text buffer passed to the `SpeakText` or `SpeakBuffer` function.

MySynchronizationCallback

A synchronization callback procedure has the following syntax:

```
PROCEDURE MySynchronizationCallback (chan: SpeechChannel;
                                     refCon: LongInt;
                                     syncMessage: OSType);
```

`chan` The speech channel that has finished processing input text.

`refCon` The reference constant associated with the speech channel.

`syncMessage` The synchronization message passed in the embedded command. Usually, you use this message to distinguish between several different types of synchronization commands, but you can use it any way you wish.

DESCRIPTION

The Speech Manager calls a speech channel's synchronization callback procedure whenever it encounters a synchronization command embedded in a text buffer. You might use the synchronization callback procedure to provide a callback not ordinarily provided. For example, you might inset synchronization commands at the end of every sentence in a text buffer, or you might enter synchronization commands after every numeric value in the text. However, to synchronize your application with phonemes or words, it makes more sense to use the built-in phoneme and word callback procedures,

defined in “Phoneme Callback Procedure” on page 4-87 and “Word Callback Procedure” on page 4-88.

SPECIAL CONSIDERATIONS

Because your callback procedure executes at interrupt time, you must not call any routines that might move or purge memory. If you need to make a visual change in response to a synchronization command, then use the callback procedure to set a global flag variable. Your application’s main event loop can check this flag and update the screen display if it is set.

Your callback procedure is able to access application global variables only if the A5 register is properly set. The Speech Manager sets A5 to the proper value if you provide your application’s A5 value by calling the `SetSpeechInfo` function with the `soCurrentA5` selector.

ASSEMBLY-LANGUAGE INFORMATION

Because a callback procedure is called at interrupt time, it must preserve all registers other than A0–A2 and D0–D2.

Error Callback Procedure

You can specify an error callback procedure by passing the `soErrorCallBack` selector to the `SetSpeechInfo` function.

MyErrorCallback

An error callback procedure has the following syntax:

```
PROCEDURE MyErrorCallback (chan: SpeechChannel; refCon: LongInt;
                           error: OSErr; bytePos: LongInt);
```

<code>chan</code>	The speech channel that has finished processing input text.
<code>refCon</code>	The reference constant associated with the speech channel.
<code>error</code>	The error that occurred in processing an embedded command.
<code>bytePos</code>	The number of bytes from the beginning of the text buffer being spoken to the error encountered.

DESCRIPTION

The Speech Manager calls a speech channel’s error callback procedure whenever it encounters a syntax error within a command embedded in a text buffer it is processing. This can be useful during application debugging, to detect problems with commands that you have embedded in text buffers that your application speaks. It can also be

useful if your application allows users to embed commands within text buffers. Your application might display an alert indicating that the Speech Manager encountered a problem in processing an embedded command.

Ordinarily, the error information that the Speech Manager provides the error callback procedure should be sufficient. However, if your application needs information about errors that occurred before the error callback procedure was enabled, the application (including the error callback procedure) can call the `GetSpeechInfo` function with the `soErrors` selector.

SPECIAL CONSIDERATIONS

Because your callback procedure executes at interrupt time, you must not call any routines that might move or purge memory. If you need to display an alert box to the user, then use the callback procedure to set a global flag variable. Your application's main event loop can check this flag and display the alert box if it is set.

Your callback procedure is able to access application global variables only if the A5 register is properly set. The Speech Manager sets A5 to the proper value if you provide your application's A5 value by calling the `SetSpeechInfo` function with the `soCurrentA5` selector.

ASSEMBLY-LANGUAGE INFORMATION

Because a callback procedure is called at interrupt time, it must preserve all registers other than A0–A2 and D0–D2.

Phoneme Callback Procedure

You can specify a phoneme callback procedure by passing the `soPhonemeCallback` selector to the `SetSpeechInfo` function.

MyPhonemeCallback

A phoneme callback procedure has the following syntax:

```
PROCEDURE MyPhonemeCallback (chan: SpeechChannel; refCon: LongInt;
                             phonemeOpcode: Integer);
```

`chan` The speech channel that has finished processing input text.

`refCon` The reference constant associated with the speech channel.

`phonemeOpcode`
 The phoneme about to be pronounced.

DESCRIPTION

The Speech Manager calls a speech channel's phoneme callback procedure just before it pronounces a phoneme. For example, your application might use such a callback procedure to enable mouth synchronization. In this case, the callback procedure would set a global flag variable to indicate that the phoneme being pronounced is changing and another global variable to `phonemeOpcode`. A routine called by your application's main event loop could detect that the phoneme being pronounced is changing and update a picture of a mouth to reflect the current phoneme. In practice, providing a visual indication of the pronunciation of a phoneme requires several consecutive pictures of mouth movement to be rapidly displayed. Consult the linguistics literature for information on mouth movements associated with different phonemes.

SPECIAL CONSIDERATIONS

Because your callback procedure executes at interrupt time, you must not call any routines that might move or purge memory.

Your callback procedure is able to access application global variables only if the A5 register is properly set. The Speech Manager sets A5 to the proper value if you provide your application's A5 value by calling the `SetSpeechInfo` function with the `soCurrentA5` selector.

ASSEMBLY-LANGUAGE INFORMATION

Because a callback procedure is called at interrupt time, it must preserve all registers other than A0–A2 and D0–D2.

Word Callback Procedure

You can specify a word callback procedure by passing the `soWordCallback` selector to the `SetSpeechInfo` function.

MyWordCallback

A word callback procedure has the following syntax:

```
PROCEDURE MyWordCallback (chan: SpeechChannel; refCon: LongInt;
                          wordPos: LongInt; wordLen: Integer);
```

<code>chan</code>	The speech channel that has finished processing input text.
<code>refCon</code>	The reference constant associated with the speech channel.
<code>wordPos</code>	The number of bytes between the beginning of the text buffer and the beginning of the word about to be pronounced.
<code>wordLen</code>	The length in bytes of the word about to be pronounced.

DESCRIPTION

The Speech Manager calls a speech channel's word callback procedure just before it pronounces a word. You might use such a callback procedure, for example, to draw the word about to be spoken in a window. In this case, the callback procedure would set a global flag variable to indicate that the word being spoken is changing and another two global variables to `wordPos` and `wordLen`. A routine called by your application's main event loop could detect that the word being spoken is changing and draw the word in a window.

SPECIAL CONSIDERATIONS

Because your callback procedure executes at interrupt time, you must not call any routines that might move or purge memory.

Your callback procedure is able to access application global variables only if the A5 register is properly set. The Speech Manager sets A5 to the proper value if you provide your application's A5 value by calling the `SetSpeechInfo` function with the `soCurrentA5` selector.

ASSEMBLY-LANGUAGE INFORMATION

Because a callback procedure is called at interrupt time, it must preserve all registers other than A0–A2 and D0–D2.

Resources

This section describes the format of a pronunciation dictionary resource, which the Speech Manager uses to override its default pronunciation of words. The Speech Manager uses pronunciation rules as well as an internal dictionary (not stored in the same format as pronunciation dictionary resources) to determine how to pronounce words not included in a speech channel's installed pronunciation dictionaries. For an introduction to the use of and examples showing how your application can install and manipulate pronunciation dictionaries, see “Including Pronunciation Dictionaries” beginning on page 4-36.

This section does not describe the format of voice resources or speech synthesizer resources, because you should not need to access them directly.

The Pronunciation Dictionary Resource

You can store a list of words and their associated pronunciations in a resource of resource type `'dict'`. You can associate any number of dictionary resources with a speech channel. Before using its internal rules to pronounce a word, the Speech Manager searches the dictionary resources that your application has associated with the speech channel in a last-in, first-searched order.


Speech Manager

Note

Because your application is responsible for loading data from a pronunciation dictionary into memory, you can, if desired, store pronunciation information in the data fork of a file rather than in the resource fork. Also, you can devise your own format in which to store pronunciation data, as long as you convert that data into the format described in this section before calling the `UseDictionary` function. ♦

Figure 4-5 shows the format of a pronunciation dictionary resource.

Figure 4-5 Format of a pronunciation dictionary resource



Note

Some synthesizers might use resources (such as resources of type 'ttsd') to store their internal pronunciation dictionaries. These internal dictionaries are not necessarily in the same format as the pronunciation dictionaries described here. ♦


To define a dictionary resource, you ordinarily use a resource of type 'dict'. Such a resource contains a pronunciation dictionary resource header, which is at the start of the resource and defines characteristics of the dictionary as a whole, and any number of pronunciation dictionary entries. Each pronunciation dictionary entry corresponds to one word and contains one or more pronunciation dictionary entry fields. Each pronunciation dictionary entry field contains one piece of information about the word being described in the entry; for example, a dictionary entry would include a field with a textual representation of the word.

The pronunciation dictionary resource header includes the following:

- Total byte length. The total number of bytes of the dictionary, including the entire pronunciation dictionary resource header in addition to the dictionary's entries.
- Atom type. The currently defined atom type is 'dict'. Future versions of the Speech Manager might define additional atom types for other types of dictionaries.
- Format version. The currently defined format version is 1. Future versions of the Speech Manager might support additional format versions for the 'dict' atom type.
- Script code. The script code of words defined in the pronunciation dictionary (for example, `smRoman`). All words in a dictionary must be in the same script.
- Language code. The language code of words defined in the pronunciation dictionary (for example, `langEnglish`). All words in a dictionary must be in the same language.
- Region code. The region code of pronunciations in the dictionary (for example, `verUS`). All words in a dictionary must target the same region.
- Date last modified. The number of seconds between midnight, January 1, 1904, and the modification time. You can use the `GetDateTime` procedure to determine the number of seconds between midnight, January 1, 1904, and the current time. For more information, see *Inside Macintosh: Operating System Utilities*.
- Reserved. These 16 bytes are reserved for future use. You should set them to 0.
- Entry count. The number of dictionary entries.

Immediately following the pronunciation dictionary resource header is a list of the pronunciation dictionary entries.

Figure 4-6 shows the format of a pronunciation dictionary entry.


Figure 4-6 Format of a dictionary entry in a dictionary resource

Each pronunciation dictionary entry consists of the following:

- **Entry byte length.** The total number of bytes in the entry, including this word.
- **Entry type.** A code for the type of pronunciation dictionary entry. The code \$0000 represents a null entry, and codes \$0001 through \$0020 are reserved for future use by Apple Computer, Inc. You should thus ordinarily fill in this field with \$0021, which is the code for a pronunciation entry, or \$0022, which is the code for an abbreviation entry. In the current version of the Speech Manager, abbreviation entries work just like pronunciation entries.
- **Field count.** The number of pronunciation dictionary entry fields contained within this entry.

Immediately following the field count indicator are the fields themselves. Typically, a pronunciation entry always includes a field containing the word in textual format and a field containing the phonetic pronunciation of the word.

Each field within a dictionary entry has the format illustrated in Figure 4-7.

Figure 4-7 Format of a dictionary entry field

The three parts of a dictionary entry field are as follows:

- **Field byte length.** The total number of bytes in the pronunciation entry field, not including the pad byte of the field data when applicable.
- **Field type.** A code for the format of the pronunciation dictionary entry field's data. The code \$0000 represents a null entry field, and Apple reserves codes \$0001 through \$0020 as well as code \$0023 for future use. Code \$0021 represents a textual representation of the word being described in the entry. Code \$0022 represents a phonetic pronunciation of the word, including a complete set of syllable, lexical stress, word prominence, and prosodic marks, all represented in textual format.
- **Field data.** If the field type is \$0021 or \$0022, then this field contains characters representing the word textually or phonetically, respectively. The characters are not preceded by a length byte and are not followed by a null character. However, if there are an odd number of characters, then a byte must be added as padding to ensure that fields align on word boundaries. The pad byte need not be set to a particular value.

Summary of the Speech Manager

Pascal Summary

Constants

CONST

```

{Gestalt selector and response bits for speech attributes}
gestaltSpeechAttr      = 'ttsc';    {speech attributes selector}
gestaltSpeechMgrPresent = 0;        {Speech Manager is present}
gestaltSpeechHasPPCGLue = 1;        {native glue for PowerPC present}

{Operating System types}
kTextToSpeechSynthType = 'ttsc';    {synthesizer component type}
kTextToSpeechVoiceType = 'ttvd';    {voice resource type}
kTextToSpeechVoiceFileType = 'ttvf'; {voice file type}
kTextToSpeechVoiceBundleType
                        = 'ttvb';    {voice bundle file type}

{masks for SpeakBuffer and text-done callback control flags}
kNoEndingProsody      = 1;          {disable prosody at end of sentences}
kNoSpeechInterrupt    = 2;          {do not interrupt current speech}
kPreflightThenPause   = 4;          {compute speech without generating}

{constants for StopSpeechAt and PauseSpeechAt}
kImmediate             = 0;          {stop immediately}
kEndOfWord             = 1;          {stop at end of word}
kEndOfSentence        = 2;          {stop at end of sentence}

{GetSpeechInfo and SetSpeechInfo selectors}
soCharacterMode        = 'char';    {get or set character-processing mode}
soCommandDelimiter    = 'dlim';    {set embedded command delimiters}
soCurrentA5           = 'myA5';    {set A5 on callbacks}
soCurrentVoice        = 'cvox';    {set speaking voice}
soErrorCallBack       = 'ercb';    {set error callback}
soErrors              = 'erro';    {get error information}
soInputMode           = 'inpt';    {get or set text-processing mode}
soNumberMode          = 'nmbr';    {get or set number-processing mode}
soPhonemeCallBack     = 'phcb';    {set phoneme callback}

```

Speech Manager

```

soPhonemeSymbols      = 'phsy';    {get phoneme symbols and sample words}
soPitchBase           = 'pbas';    {get or set baseline pitch}
soPitchMod            = 'pmod';    {get or set pitch modulation}
soRate                = 'rate';    {get or set speech rate}
soRecentSync         = 'sync';    {get most recent synchronization }
                               { message information}

soRefCon              = 'refc';    {set reference constant value}
soReset               = 'rset';    {set channel back to default state}
soSpeechDoneCallBack = 'sdcb';    {set speech-done callback}
soStatus              = 'stat';    {get status of channel}
soSyncCallBack        = 'sycb';    {set synchronization callback}
soSynthExtension      = 'xtnd';    {get or set synthesizer-specific }
                               { information}

soSynthType           = 'vers';    {get synthesizer information}
soTextDoneCallBack    = 'tdcb';    {set text-done callback}
soVolume              = 'volm';    {get or set speech volume}
soWordCallBack        = 'wdcb';    {set word callback}

{input mode constants}
modeText              = 'TEXT';
modePhonemes          = 'PHON';

{character and number mode constants}
modeNormal            = 'NORM';
modeLiteral           = 'LTRL';

{GetVoiceInfo selectors}
soVoiceDescription    = 'info';    {get basic voice information}
soVoiceFile           = 'fref';    {get voice file reference information}

{genders}
kNeuter               = 0;
kMale                 = 1;
kFemale               = 2;

```

Data Structures

Speech Channel Record

TYPE

```

SpeechChannelRecord  = LongInt;    {speech channel record}
SpeechChannel        = ^SpeechChannelRecord; {speech channel}
SpeechChannelPtr     = ^SpeechChannel; {speech channel pointer}

```

Voice Specification Record

```

VoiceSpec =
RECORD
    creator:          OSType;          {ID of required synthesizer}
    id:               OSType;          {ID of voice on the synthesizer}
END;
VoiceSpecPtr = ^VoiceSpec;

```

Voice Description Record

```

VoiceDescription =
RECORD
    length:          LongInt;          {size of record--set by application}
    voice:           VoiceSpec;        {voice synthesizer and ID info}
    version:         LongInt;          {version number of voice}
    name:            Str63;            {name of voice}
    comment:         Str255;           {text information about voice}
    gender:          Integer;          {neuter, male, or female}
    age:             Integer;          {approximate age in years}
    script:          Integer;          {script code of text voice can }
                                     { process}
    language:        Integer;          {language code of voice output}
    region:          Integer;          {region code of voice output}
    reserved1:       LongInt;          {always 0--reserved for future use}
    reserved2:       LongInt;          {always 0--reserved for future use}
    reserved3:       LongInt;          {always 0--reserved for future use}
    reserved4:       LongInt;          {always 0--reserved for future use}
END;
VoiceDescriptionPtr = ^VoiceDescription;

```

Voice File Information Record

```

VoiceFileInfo =
RECORD
    fileSpec:        FSSpec;          {volume, dir, and name of file}
    resID:           Integer;         {resource ID of voice in the file}
END;
VoiceFileInfoPtr = ^VoiceFileInfo;

```

Speech-Status Information Record

```

SpeechStatusInfo =
RECORD
    outputBusy:      Boolean;      {TRUE if audio is playing}
    outputPaused:    Boolean;      {TRUE if channel is paused}
    inputBytesLeft:  LongInt;      {bytes of text left to process}
    phonemeCode:     Integer;      {opcode for current phoneme}
END;
SpeechStatusInfoPtr = ^SpeechStatusInfo;

```

Speech Error Information Record

```

SpeechErrorInfo =
RECORD
    count:           Integer;      {number of errors since last check}
    oldest:          OSErr;        {oldest unread error}
    oldPos:          LongInt;      {character position of oldest error}
    newest:          OSErr;        {most recent error}
    newPos:         LongInt;      {character position of newest error}
END;

```

Speech Version Information Record

```

SpeechVersionInfo =
RECORD
    synthType:       OSType;       {general synthesizer type}
    synthSubType:    OSType;       {specific synthesizer type}
    synthManufacturer:
                                OSType;       {synthesizer creator ID}
    synthFlags:      LongInt;      {synthesizer feature flags}
    synthVersion:    NumVersion;   {synthesizer version number}
END;
SpeechVersionInfoPtr = ^SpeechVersionInfo;

```

Phoneme Information Record

```

PhonemeInfo =
RECORD
    opCode:          Integer;      {opcode for the phoneme}
    phStr:           Str15;        {corresponding character string}
    exampleStr:      Str31;        {word that shows use of phoneme}
    hiliteStart:     Integer;      {offset from beginning of word }
                                { to beginning of phoneme sound}

```

Speech Manager

```

hiliteEnd:      Integer;      {offset from beginning of word }
                                   { to end of phoneme sound}
END;

```

Phoneme Descriptor Record

```

PhonemeDescriptor =
RECORD
    phonemeCount:      Integer;      {number of phonemes defined by }
                                   { current synthesizer}
                                   {list of phoneme information records}
    thePhonemes:      ARRAY[0..0] OF PhonemeInfo;
END;

```

Speech Extension Data Record

```

SpeechXtndData =
RECORD
    synthCreator:      OSType;      {synthesizer creator ID}
                                   {data used by synthesizer}
    synthData:      PACKED ARRAY[0..1] OF Char;
END;

```

Delimiter Information Record

```

DelimiterInfo =
RECORD
    startDelimiter:      PACKED ARRAY[0..1] OF Char;      {start delimiter}
    endDelimiter:      PACKED ARRAY[0..1] OF Char;      {end delimiter}
END;

```

Speech Manager Routines

Starting, Stopping, and Pausing Speech

```

FUNCTION SpeakString      (s: Str255): OSErr;
FUNCTION SpeakText      (chan: SpeechChannel; textBuf: Ptr;
    byteLen: LongInt): OSErr;
FUNCTION SpeakBuffer      (chan: SpeechChannel; textBuf: Ptr;
    byteLen: LongInt; controlFlags: LongInt):
    OSErr;
FUNCTION StopSpeech      (chan: SpeechChannel): OSErr;

```


Speech Manager

```

FUNCTION StopSpeechAt      (chan: SpeechChannel; whereToStop: LongInt):
                           OSerr;
FUNCTION PauseSpeechAt    (chan: SpeechChannel; whereToStop: LongInt):
                           OSerr;
FUNCTION ContinueSpeech   (chan: SpeechChannel): OSerr;

```

Obtaining Information About Voices

```

FUNCTION MakeVoiceSpec    (creator: OSType; id: OSType;
                           voice: VoiceSpecPtr): OSerr;
FUNCTION CountVoices      (VAR numVoices: Integer): OSerr;
FUNCTION GetIndVoice      (index: Integer; voice: VoiceSpecPtr): OSerr;
FUNCTION GetVoiceDescription
                           (voice: VoiceSpecPtr;
                            info: VoiceDescriptionPtr; infoLength: LongInt)
                           : OSerr;
FUNCTION GetVoiceInfo     (voice: VoiceSpecPtr; selector: OSType;
                           voiceInfo: Ptr): OSerr;

```

Managing Speech Channels

```

FUNCTION NewSpeechChannel (voice: VoiceSpecPtr; VAR chan: SpeechChannel):
                           OSerr;
FUNCTION DisposeSpeechChannel
                           (chan: SpeechChannel): OSerr;

```

Obtaining Information About Speech

```

FUNCTION SpeechManagerVersion
                           : NumVersion;
FUNCTION SpeechBusy        : Integer;
FUNCTION SpeechBusySystemWide
                           : Integer;

```

Changing Speech Attributes

```

FUNCTION GetSpeechRate    (chan: SpeechChannel; VAR rate: Fixed): OSerr;
FUNCTION SetSpeechRate    (chan: SpeechChannel; rate: Fixed): OSerr;
FUNCTION GetSpeechPitch   (chan: SpeechChannel; VAR pitch: Fixed): OSerr;
FUNCTION SetSpeechPitch   (chan: SpeechChannel; pitch: Fixed): OSerr;
FUNCTION GetSpeechInfo    (chan: SpeechChannel; selector: OSType;
                           speechInfo: Ptr): OSerr;
FUNCTION SetSpeechInfo    (chan: SpeechChannel; selector: OSType;
                           speechInfo: Ptr): OSerr;

```

Converting Text to Phonemes

```
FUNCTION TextToPhonemes      (chan: SpeechChannel; textBuf: Ptr;
                             textBytes: LongInt; phonemeBuf: Handle;
                             VAR phonemeBytes: LongInt): OSErr;
```

Installing a Pronunciation Dictionary

```
FUNCTION UseDictionary      (chan: SpeechChannel; dictionary: Handle)
                             : OSErr;
```

Application-Defined Routines

```
PROCEDURE MyTextDoneCallback
                             (chan: SpeechChannel; refCon: LongInt;
                              VAR nextBuf: Ptr; VAR byteLen: LongInt;
                              VAR controlFlags: LongInt);

PROCEDURE MySpeechDoneCallback
                             (chan: SpeechChannel; refCon: LongInt);

PROCEDURE MySynchronizationCallback
                             (chan: SpeechChannel; refCon: LongInt;
                              syncMessage: OSType);

PROCEDURE MyErrorCallback   (chan: SpeechChannel; refCon: LongInt;
                              error: OSErr; bytePos: LongInt);

PROCEDURE MyPhonemeCallback
                             (chan: SpeechChannel; refCon: LongInt;
                              phonemeOpcode: Integer);

PROCEDURE MyWordCallback    (chan: SpeechChannel; refCon: LongInt;
                              wordPos: LongInt; wordLen: Integer);
```

C Summary

Constants

```
/*Gestalt selector and response bits for speech attributes*/
#define gestaltSpeechAttr  'ttsc'  /*speech attributes selector*/
enum {
    gestaltSpeechMgrPresent    = 0  /*Speech Manager is present*/
    gestaltSpeechHasPPCglue    = 1  /*native glue for PowerPC present*/
};
```

Speech Manager

```

/*Operating System types*/
#define kTextToSpeechSynthType      'ttsc'   /*synthesizer component */
                                        /* type*/

#define kTextToSpeechVoiceType      'ttvd'   /*voice resource type*/
#define kTextToSpeechVoiceFileType  'ttvf'   /*voice file type*/
#define kTextToSpeechVoiceBundleType 'ttvb'   /*voice bundle file type*/

/*masks for SpeakBuffer and text-done callback control flags*/
enum {
    kNoEndingProsody      = 1,   /*disable prosody at end of sentences*/
    kNoSpeechInterrupt    = 2,   /*do not interrupt current speech*/
    kPreflightThenPause   = 4    /*compute speech without generating*/
};

/*constants for StopSpeechAt and PauseSpeechAt*/
enum {
    kImmediate            = 0,   /*stop immediately*/
    kEndOfWord            = 1,   /*stop at end of word*/
    kEndOfSentence        = 2    /*stop at end of sentence*/
};

/*GetSpeechInfo and SetSpeechInfo selectors*/
#define soCharacterMode      'char'   /*get or set character-processing */
                                        /* mode*/

#define soCommandDelimiter  'dlim'   /*set embedded command delimiters*/
#define soCurrentA5         'myA5'   /*set A5 on callbacks*/
#define soCurrentVoice      'cvox'   /*set speaking voice*/
#define soErrorCallBack     'ercb'   /*set error callback*/
#define soErrors            'erro'   /*get error information*/
#define soInputMode         'inpt'   /*get or set text-processing mode*/
#define soNumberMode        'nmbr'   /*get or set number-processing mode*/
#define soPhonemeCallBack   'phcb'   /*set phoneme callback*/
#define soPhonemeSymbols    'phsy'   /*get phoneme symbols and sample*/
                                        /* words*/

#define soPitchBase         'pbas'   /*get or set baseline pitch*/
#define soPitchMod          'pmod'   /*get or set pitch modulation*/
#define soRate              'rate'   /*get or set speech rate*/
#define soRecentSync        'sync'   /*get most recent synchronization */
                                        /* message information*/

#define soRefCon            'refc'   /*set reference constant value*/
#define soReset             'rset'   /*set channel back to default state*/
#define soSpeechDoneCallBack 'sdc'b' /*set speech-done callback*/
#define soStatus            'stat'   /*get status of channel*/
#define soSyncCallBack      'syncb'  /*set synchronization callback*/

```

Speech Manager

```

#define soSynthExtension      'xtnd'   /*get or set synthesizer-specific */
                                /* information*/
#define soSynthType          'vers'   /*get synthesizer information*/
#define soTextDoneCallBack   'tdcb'   /*set text-done callback*/
#define soVolume             'volm'   /*get or set speech volume*/
#define soWordCallBack       'wdcb'   /*set word callback*/

/*input mode constants*/
#define modeText              'TEXT'
#define modePhonemes         'PHON'

/*character and number mode constants*/
#define modeNormal           'NORM'
#define modeLiteral          'LTRL'

/*GetVoiceInfo selectors*/
enum {
    soVoiceDescription      = 'info',   /*get basic voice information*/
    soVoiceFile              = 'fref'    /*get voice file reference information*/
};

/*genders*/
enum {
    kNeuter = 0,
    kMale,
    kFemale
};

```

Data Types

Speech Channel Record

```

typedef struct SpeechChannelRecord {
    long data[1];                /*used internally*/
} SpeechChannelRecord;

```

```

typedef SpeechChannelRecord *SpeechChannel;

```

Voice Specification Record

```

typedef struct VoiceSpec {
    OSType      creator;         /*ID of required synthesizer*/
    OSType      id;             /*ID of voice on the synthesizer*/
} VoiceSpec;

```

Voice Description Record

```
typedef struct VoiceDescription {
    long        length;           /*size of structure--set by application*/
    VoiceSpec   voice;           /*voice synthesizer and ID info*/
    long        version;         /*version number of voice*/
    Str63       name;            /*name of voice*/
    Str255      comment;         /*text information about voice*/
    short       gender;          /*neuter, male, or female*/
    short       age;             /*approximate age in years*/
    short       script;          /*script code of text voice can process*/
    short       language;        /*language code of voice output*/
    short       region;          /*region code of voice output*/
    long        reserved[4];     /*always 0--reserved for future use*/
} VoiceDescription;
```

Voice File Information Record

```
typedef struct VoiceFileInfo {
    FSSpec      fileSpec;        /*volume, dir, and name of file*/
    short       resID;           /*resource ID of voice in the file*/
} VoiceFileInfo;
```

Speech Status Information Record

```
typedef struct SpeechStatusInfo {
    Boolean     outputBusy;      /*TRUE if audio is playing*/
    Boolean     outputPaused;    /*TRUE if channel is paused*/
    long        inputBytesLeft;  /*bytes of text left to process*/
    short       phonemeCode;     /*opcode for current phoneme*/
} SpeechStatusInfo;
```

Speech Error Information Record

```
typedef struct SpeechErrorInfo {
    short       count;           /*number of errors since last check*/
    OSErr       oldest;          /*oldest unread error*/
    long        oldPos;          /*character position of oldest error*/
    OSErr       newest;          /*most recent error*/
    long        newPos;          /*character position of newest error*/
} SpeechErrorInfo;
```

Speech Version Information Record

```
typedef struct SpeechVersionInfo {
    OSType      synthType;           /*general synthesizer type*/
    OSType      synthSubType;       /*specific synthesizer type*/
    OSType      synthManufacturer;  /*synthesizer creator ID*/
    long        synthFlags;         /*synthesizer feature flags*/
    NumVersion  synthVersion;       /*synthesizer version number*/
} SpeechVersionInfo;
```

Phoneme Information Record

```
typedef struct PhonemeInfo {
    short       opcode;             /*opcode for the phoneme*/
    Str15       phStr;              /*corresponding character string*/
    Str31       exampleStr;        /*word that shows use of phoneme*/
    short       hiliteStart;       /*offset from beginning of word */
                                        /* to beginning of phoneme sound*/
    short       hiliteEnd;         /*offset from beginning of word */
                                        /* to end of phoneme sound*/
} PhonemeInfo;
```

Phoneme Descriptor Record

```
typedef struct PhonemeDescriptor {
    short       phonemeCount;      /*number of phonemes defined by */
                                        /* current synthesizer*/
    PhonemeInfo thePhonemes[1];   /*list of phoneme information records*/
} PhonemeDescriptor;
```

Speech Extension Data Record

```
typedef struct SpeechXtndData {
    OSType      synthCreator;      /*synthesizer creator ID*/
    Byte        synthData[2];      /*data used by synthesizer*/
} SpeechXtndData;
```

Delimiter Information Record

```
typedef struct DelimiterInfo {
    Byte        startDelimiter[2]; /*start delimiter*/
    Byte        endDelimiter[2];   /*end delimiter*/
} DelimiterInfo;
```

Speech Manager Routines

Starting, Stopping, and Pausing Speech

```

pascal OSErr SpeakString      (StringPtr s);
pascal OSErr SpeakText       (SpeechChannel chan, Ptr textBuf,
                              long textBytes);
pascal OSErr SpeakBuffer     (SpeechChannel chan, Ptr textBuf,
                              long textBytes, long controlFlags);
pascal OSErr StopSpeech      (SpeechChannel chan);
pascal OSErr StopSpeechAt    (SpeechChannel chan, long whereToStop);
pascal OSErr PauseSpeechAt   (SpeechChannel chan, long whereToPause);
pascal OSErr ContinueSpeech  (SpeechChannel chan);

```

Obtaining Information About Voices

```

pascal OSErr MakeVoiceSpec   (OSType creator, OSType id, VoiceSpec *voice);
pascal OSErr CountVoices     (short *numVoices);
pascal OSErr GetIndVoice     (short index, VoiceSpec *voice);
pascal OSErr GetVoiceDescription
                              (VoiceSpec *voice, VoiceDescription *info,
                              long infoLength);
pascal OSErr GetVoiceInfo    (VoiceSpec *voice, OSType selector,
                              void *voiceInfo);

```

Managing Speech Channels

```

pascal OSErr NewSpeechChannel
                              (VoiceSpec *voice, SpeechChannel *chan);
pascal OSErr DisposeSpeechChannel
                              (SpeechChannel chan);

```

Obtaining Information About Speech

```

pascal NumVersion SpeechManagerVersion
                              (void);
pascal short SpeechBusy      (void);
pascal short SpeechBusySystemWide
                              (void);

```

Changing Speech Attributes

```

pascal OSErr GetSpeechRate   (SpeechChannel chan, Fixed *rate);

```

Speech Manager

```

pascal OSErr SetSpeechRate (SpeechChannel chan, Fixed rate);
pascal OSErr GetSpeechPitch
    (SpeechChannel chan, Fixed *pitch);
pascal OSErr SetSpeechPitch
    (SpeechChannel chan, Fixed pitch);
pascal OSErr GetSpeechInfo (SpeechChannel chan, OSType selector,
    void *speechInfo);
pascal OSErr SetSpeechInfo (SpeechChannel chan, OSType selector,
    void *speechInfo);

```

Converting Text to Phonemes

```

pascal OSErr TextToPhonemes
    (SpeechChannel chan, Ptr textBuf,
    long textBytes, Handle phonemeBuf,
    long *phonemeBytes);

```

Installing a Pronunciation Dictionary

```

pascal OSErr UseDictionary (SpeechChannel chan, Handle dictionary);

```

Application-Defined Routines

```

#pragma procname SpeechTextDone
typedef pascal void (*SpeechTextDoneCBPtr)
    (SpeechChannel, long, Ptr *, long *, long *);
typedef SpeechTextDoneProcPtr SpeechTextDoneCBPtr;
#pragma procname SpeechDone
typedef pascal void (*SpeechDoneCBPtr)
    (SpeechChannel, long);
typedef SpeechDoneProcPtr SpeechDoneCBPtr;
#pragma procname SpeechSync
typedef pascal void (*SpeechSyncCBPtr)
    (SpeechChannel, long, OSType);
typedef SpeechSyncProcPtr SpeechSyncCBPtr;
#pragma procname SpeechError
typedef pascal void (*SpeechErrorCBPtr)
    (SpeechChannel, long, OSErr, long);
typedef SpeechErrorProcPtr SpeechErrorCBPtr;
#pragma procname SpeechPhoneme
typedef pascal void (*SpeechPhonemeCBPtr)
    (SpeechChannel, long, short);
typedef SpeechPhonemeProcPtr SpeechPhonemeCBPtr;

```


Speech Manager

```
#pragma procname SpeechWord
typedef pascal void (*SpeechWordCBPtr)
                    (SpeechChannel, long, long, short);
typedef SpeechWordProcPtr SpeechWordCBPtr;
```

Assembly-Language Information

Data Structures

Voice Specification Data Structure

0	creator	4 bytes	ID of required synthesizer
4	id	4 bytes	ID of voice on the synthesizer

Voice Description Data Structure

0	length	long	size of structure—set by application
4	voice	8 bytes	voice specification record
12	version	long	version number of voice
16	name	64 bytes	name of voice; preceded by length byte
80	comment	256 bytes	text information about voice; preceded by length byte
336	gender	short	neuter (0), male (1), or female (2)
338	age	short	approximate age in years
340	script	short	script code of text voice can process
342	language	short	language code of text voice can process
344	region	short	region code of voice output
346	reserved	16 bytes	always set to 0—reserved for future use

Voice File Information Data Structure

0	fileSpec	70 bytes	volume, directory, and name of file
70	resID	word	resource ID of voice in the file

Speech Status Information Data Structure

0	outputBusy	byte	1 if audio is playing
1	outputPaused	byte	1 if channel is paused
2	inputBytesLeft	long	bytes of text left to process
6	phonemeCode	short	opcode for current phoneme

Speech Error Information Data Structure

0	count	word	number of errors since last check
2	oldest	long	oldest unread Operating System error
6	oldPos	long	character position of oldest error
10	newest	long	newest Operating System error
14	newPos	long	character position of newest error

Speech Version Information Data Structure

0	synthType	4 bytes	always 'TTSC'
4	synthSubType	4 bytes	synthesizer type
8	synthManufacturer	4 bytes	synthesizer creator ID
12	synthFlags	long	synthesizer feature flags
16	synthVersion	long	synthesizer version number

Phoneme Information Data Structure

0	opcode	word	opcode for the phoneme
2	phStr	16 bytes	corresponding character string; preceded by length byte
18	exampleStr	32 bytes	word that shows use of phoneme
50	hiliteStart	word	offset from beginning of word to beginning of phoneme sound
52	hiliteEnd	word	offset from beginning of word to end of phoneme sound

Phoneme Descriptor Data Structure

0	phonemeCount	word	number of phonemes defined by current synthesizer
2	thePhonemes	variable	list of phoneme information records

Speech Extension Data Structure

0	synthCreator	4 bytes	synthesizer creator ID
4	synthData	variable	data used by synthesizer

Delimiter Information Data Structure

0	startDelimiter	2 bytes	start embedded command characters; defaults to "[["
2	endDelimiter	2 bytes	end embedded command characters; defaults to "]]"

Trap Macros

Trap Macro Requiring Routine Selectors`_SoundDispatch`

Selector	Routine
\$000000C	SpeechManagerVersion
\$003C000C	SpeechBusy
\$0040000C	SpeechBusySystemWide
\$0108000C	CountVoices
\$021C000C	DisposeSpeechChannel
\$0220000C	SpeakString
\$022C000C	StopSpeech
\$0238000C	ContinueSpeech
\$030C000C	GetIndVoice
\$0418000C	NewSpeechChannel
\$0430000C	StopSpeechAt
\$0434000C	PauseSpeechAt
\$0444000C	SetSpeechRate
\$0448000C	GetSpeechRate
\$044C000C	SetSpeechPitch
\$0450000C	GetSpeechPitch
\$0460000C	UseDictionary
\$0604000C	MakeVoiceSpec
\$0610000C	GetVoiceDescription
\$0614000C	GetVoiceInfo
\$0624000C	SpeakText
\$0654000C	SetSpeechInfo
\$0658000C	GetSpeechInfo
\$0828000C	SpeakBuffer
\$0A5C000C	TextToPhonemes

Result Codes

noErr	0	No error
paramErr	-50	Parameter error
memFullErr	-108	Not enough memory to speak
nilHandleErr	-109	Handle argument is NIL
siUnknownInfoType	-231	Feature not implemented on synthesizer
noSynthFound	-240	Could not find the specified speech synthesizer
synthOpenFailed	-241	Could not open another speech synthesizer channel
synthNotReady	-242	Speech synthesizer is still busy speaking
bufTooSmall	-243	Output buffer is too small to hold result
voiceNotFound	-244	Voice resource not found
incompatibleVoice	-245	Specified voice cannot be used with synthesizer
badDictFormat	-246	Pronunciation dictionary format error
badPhonemeText	-247	Raw phoneme text contains invalid characters
unimplMsg	-248	Unimplemented message
badVoiceID	-250	Specified voice has not been preloaded
badParmCount	-252	Incorrect number of embedded command arguments
invalidComponentID	-3000	Speech channel is uninitialized or bad

Sound Components

Contents

About Sound Components	5-4
Sound Component Chains	5-4
The Apple Mixer	5-6
The Data Stream	5-7
Writing a Sound Component	5-8
Creating a Sound Component	5-8
Specifying Sound Component Capabilities	5-11
Dispatching to Sound Component-Defined Routines	5-12
Registering and Opening a Sound Component	5-16
Finding and Changing Component Capabilities	5-18
Sound Components Reference	5-22
Constants	5-22
Sound Component Information Selectors	5-22
Audio Data Types	5-26
Sound Component Features Flags	5-26
Action Flags	5-27
Data Format Flags	5-28
Data Structures	5-29
Sound Component Data Records	5-29
Sound Parameter Blocks	5-30
Sound Information Lists	5-31
Compression Information Records	5-32
Sound Manager Utilities	5-33
Opening and Closing the Apple Mixer Component	5-33
Saving and Restoring Sound Component Preferences	5-35
Sound Component-Defined Routines	5-36
Managing Sound Components	5-37
Creating and Removing Audio Sources	5-42
Getting and Setting Sound Component Information	5-44
Managing Source Data	5-46

Summary of Sound Components	5-50	
C Summary	5-50	
Constants	5-50	
Data Types	5-53	
Sound Manager Utilities	5-54	
Sound Component-Defined Routines	5-55	
Assembly-Language Summary	5-56	
Data Structures	5-56	

Sound Components

This chapter describes sound components, which are code modules used by the Sound Manager to manipulate audio data or to communicate with sound output devices. Current versions of the Sound Manager allow you to write two kinds of sound components:

- compression and decompression components (codecs), which allow you to implement audio data compression and decompression algorithms different from those provided by the Sound Manager's MACE (Macintosh Audio Compression and Expansion) capabilities
- sound output device components, which send audio data directly to sound output devices

You need to read this chapter only if you are developing a sound output device or if you want to implement a custom compression and decompression scheme for audio data. For example, you might write a codec to handle 16-bit audio data compression and decompression. (The MACE algorithms currently compress and expand only 8-bit data at ratios of 3:1 and 6:1.)

IMPORTANT

Sound components are loaded and managed by the Sound Manager and operate transparently to applications. Applications that want to create sounds must use Sound Manager routines to do so. The routines described in this chapter are intended for use exclusively by sound components. ▲

To use this chapter, you should already be familiar with the general operation of the Sound Manager, as described in the chapter "Introduction to Sound on the Macintosh" in this book. Because sound components are components, you also need to be familiar with the Component Manager, described in *Inside Macintosh: More Macintosh Toolbox*. If you are developing a sound output device component, you need to be familiar with the process of installing a driver and handling interrupts created by your hardware device. See *Inside Macintosh: Devices* for complete information on devices and device drivers.

If you're developing a sound output device, you might also need to write a control panel extension that installs a custom subpanel into the Sound control panel. For example, your subpanel could allow the user to set various characteristics of the sound your output device is creating. For complete information on writing control panel subpanels, see the chapter "Control Panel Extensions" in *Inside Macintosh: Operating System Utilities*.

This chapter begins with a general description of sound components and how they are managed by the Sound Manager. Then it provides instructions on how to write a sound component. The section "Sound Components Reference" beginning on page 5-22 describes the sound component selectors your component might need to handle and the component-defined routines that your sound component should call in response to those the sound component selectors. It also describes a small number of Sound Manager utility routines that your sound component can use.

Note

Pascal interfaces for sound components are not currently available. As a result, this chapter provides all source code examples and reference materials in C. ♦

About Sound Components

A **sound component** is a component that works with the Sound Manager to manipulate audio data or to communicate with a sound output device. Sound components provide the foundation for the modular, device-independent sound architecture introduced with Sound Manager version 3.0. This section provides a description of sound components and shows how they are managed by the Sound Manager. For specific information on creating a sound component, see “Writing a Sound Component” beginning on page 5-8.

Sound Component Chains


Prior to version 3.0, the Sound Manager performed all audio data processing internally, using its own filters to decompress audio data, convert sample rates, mix separate sound channels, and so forth. This effectively rendered it difficult, if not impossible, to add other data modification filters to process the audio data. (The now-obsolete method of installing a sound modifier with the `SndAddModifier` routine did not work reliably.) More importantly, the Sound Manager was responsible for managing the entire stream of audio data, from the application to the available sound-producing audio hardware. This made it very difficult to support new sound output devices.

In versions 3.0 and later, the Sound Manager provides a new audio data processing architecture based on components, illustrated in Figure 5-1. The fundamental idea is that the process of playing a sound can be divided into a number of specific steps, each of which has well-defined inputs and outputs. Figure 5-1 shows the steps involved in playing an 11 kHz compressed sampled sound resource on a Macintosh II computer.


An application sends the compressed sound data to the Sound Manager, which constructs an appropriate **sound component chain** that links the unprocessed audio data to the sound components required to modify the data into a form that can be sent to the current sound output device. As you can see in Figure 5-1, the Sound Manager links together sound components that, in sequence, expand the compressed sound data into audio samples, convert the sample rate from 11 kHz to 22 kHz, mix those samples with samples from any other sound channels that might be playing, and then write the samples to the available audio hardware (in this case, the FIFO buffer in the Apple Sound Chip).

IMPORTANT

The Sound Manager itself converts both wave-table data and square-wave data into sampled-sound data before sending the data into a chain of sound components. As a result, sound components need to be concerned only with sampled-sound data. ▲

Figure 5-1 The component-based sound architecture

The components in a component chain may vary, depending both on the format of the audio data sent to the Sound Manager by an application and on the capabilities of the current sound output device. The chain shown in Figure 5-1 is necessary to handle the compressed 11 kHz sound because the Apple Sound Chip can handle only 22 kHz noncompressed sampled-sound data. Other sound output devices may be able to do more processing internally, thereby reducing the amount of processing required by the sound component chain. For instance, a DSP-based sound card might be capable of converting sample rates itself. In that case, the Sound Manager would not install the rate conversion component into the sound component chain. The resulting sound component chain is shown in Figure 5-2.

Figure 5-2 A component chain for audio hardware that can convert sample rates

The principal function of a sound component is to transfer data from the source down the chain of sound components while performing some specific modification on the data. It does this by getting a block of data from its **source component** (the component that immediately precedes it in the chain). The sound component then processes that data and stores it in the component's own private buffers. The next component can then get that processed data, perform its own modifications, and pass the data to the next component in the chain. Eventually, the audio data flows through the Apple Mixer (described in the next section) to the **sound output device component**, which sends the data to the current sound output device.

Sound Components

Notice that only the sound output device component communicates directly with the sound output hardware. This insulates all other sound components from having to know anything about the current sound output device. Rather, those components (sometimes called **utility components**) can simply operate on a stream of bytes.

The Sound Manager provides sound output device components for all sound output devices built into Macintosh computers. It also provides utility components for many typical kinds of audio data manipulation, including


- sample rate conversion
- audio data expansion
- sample size conversion
- format conversion (for example, converting offset binary data to two's complement)

Currently, you can write sound output device components to handle communication with your own sound output devices. You can also write utility components to handle custom compression and expansion schemes. You cannot currently write any other kind of utility component.

The Apple Mixer

As you've seen, most sound components take a single source of audio data and modify it in some way, thereby producing a single output stream of audio data. There is one special sound component, known as the **Apple Mixer component** (or, more briefly, the **Apple Mixer**), that is able to handle more than one input data stream. Its function is precisely to mix together all open channels of sound data into a single output stream, as shown in Figure 5-3.


Figure 5-3 Mixing multiple channels of sound



The Apple Mixer has a more general function also, namely to construct the sound component chain required to process audio data from a given sound source into a format that can be handled by a particular sound output device. The Apple Mixer always feeds its output directly to the sound output device component, which sends the data to its associated audio hardware. After creating the component chain, the Apple Mixer assigns it a **source ID**, a 4-byte token that provides a unique reference to the component chain. The Apple Mixer is actually created by the sound output device component, when that component calls the Sound Manager's `OpenMixerSoundComponent` function.

In addition to creating sound component chains and mixing their data, the Apple Mixer can control the volume and stereo panning of a particular sound channel. Some sound output devices might be able to provide these capabilities as well. Indeed, some sound output devices might even be able to mix the data in multiple sound channels. In those cases, the sound output device component can call the `OpenMixerSoundComponent` function once for each sound source it wants to manage. The result is a separate instance of the Apple Mixer for each sound source, as shown in Figure 5-4.

Figure 5-4 A sound output device component that can mix sound channels



The sound output device component can instruct each instance of the Apple Mixer to pass all the sound data through unprocessed, thereby allowing the output device to perform the necessary processing and mixing. In this case, the Apple Mixer consumes virtually no processing time. The Apple Mixer must, however, still be present to set up the sound component chain and to assign a source ID to each sound source.

The Data Stream

A sound component is a standalone code resource that performs some signal processing function or communicates with a sound output device. All sound components have a standard programming interface and local storage that allows them to be connected

Sound Components

together in series to perform a wide range of audio data processing tasks. As previously indicated, all sound components (except for mixer components and some sound output device components) accept a single stream of input data and produce a single stream of output data.

The Sound Manager sends your sound component information about its input stream by passing it the address of a **sound component data record**, defined by the `SoundComponentData` data type.

```
typedef struct {
    long          flags;           /*sound component flags*/
    OSType        format;         /*data format*/
    short         numChannels;    /*number of channels in data*/
    short         sampleSize;     /*size of a sample*/
    UnsignedFixed sampleRate;     /*sample rate*/
    long          sampleCount;    /*number of samples in buffer*/
    Byte          *buffer;        /*location of data*/
    long          reserved;       /*reserved*/
} SoundComponentData, *SoundComponentDataPtr;
```

The `buffer` field points to the buffer of input data. The other fields define the format of that data. For example, the sample size and rate are passed in the `sampleSize` and `sampleRate` fields, respectively. A utility component should modify the data in that buffer and then write the processed data into an internal buffer. Then it should fill out a sound component data record and pass its address back to the Sound Manager, which will then pass it on to the next sound component in the chain. Eventually, the audio data passes through all utility components in the chain, through the Apple Mixer and the sound output device component, down to the audio hardware.

Writing a Sound Component

A sound component is a component that works with the Sound Manager to manipulate audio data or to communicate with a sound output device. Because a sound component is a component, it must be able to respond to standard selectors sent by the Component Manager. In addition, a sound component must handle other selectors specific to sound components. This section describes how to write a sound component.

Creating a Sound Component

A sound component is a component. It contains a number of resources, including icons, strings, and the standard component resource (a resource of type 'thng') required of any Component Manager component. In addition, a sound component must contain code to handle required selectors passed to it by the Component Manager as well as selectors specific to the sound component.

Note

For complete details on components and their structure, see the chapter “Component Manager” in *Inside Macintosh: More Macintosh Toolbox*. This section provides specific information about sound components. ♦

The component resource binds together all the relevant resources contained in a component; its structure is defined by the `ComponentResource` data type.

```
struct ComponentResource {
    ComponentDescription    cd;
    ResourceSpec            component;
    ResourceSpec            componentName;
    ResourceSpec            componentInfo;
    ResourceSpec            componentIcon;
};
```

The `component` field specifies the resource type and resource ID of the component’s executable code. By convention, this field should be set to the value `kSoundComponentCodeType`:

```
#define kSoundComponentCodeType    'sift'    /*sound component code type*/
```

(You can, however, specify some other resource type if you wish.) The resource ID can be any integer greater than or equal to 128. See the following section for further information about this code resource. The `ResourceSpec` data type has this structure:

```
typedef struct {
    OSType            resType;
    short            resID;
} ResourceSpec;
```

The `componentName` field specifies the resource type and resource ID of the resource that contains the component’s name. Usually the name is contained in a resource of type `'STR'`. This string should be as short as possible.

The `componentInfo` field specifies the resource type and resource ID of the resource that contains a description of the component. Usually the description is contained in a resource of type `'STR'`.

The `componentIcon` field specifies the resource type and resource ID of the resource that contains an icon for the component. Usually the icon is contained in a resource of type `'ICON'`.

The `cd` field of the `ComponentResource` structure is a **component description record**, which contains additional information about the component. A component description record is defined by the `ComponentDescription` data type.

```
typedef struct {
    OSType            componentType;
    OSType            componentSubType;
```

Sound Components

```

    OSType                componentManufacturer;
    unsigned long         componentFlags;
    unsigned long         componentFlagsMask;
} ComponentDescription;

```

For sound components, the `componentType` field must be set to a value recognized by the Sound Manager. Currently, there are five available component types for sound components:

```

#define kSoundComponentType    'sift'    /*utility component*/
#define kMixerType             'mixr'    /*mixer component*/
#define kSoundHardwareType     'sdev'    /*sound output device component*/
#define kSoundCompressor       'scom'    /*compression component*/
#define kSoundDecompressor     'sdec'    /*decompression component*/

```

In addition, the `componentSubType` field must be set to a value that indicates the type of audio services your component provides. For example, the Apple-supplied sound output device components have these subtypes:

```

#define kClassicSubType        'clas'    /*Classic hardware*/
#define kASCSubType            'asc '    /*ASC device*/
#define kDSPSubType            'dsp '    /*DSP device*/

```

If you add your own sound output device component, you should define some other subtype.

Note

Apple Computer, Inc., reserves for its own use all types and subtypes composed solely of lowercase letters. ♦

You can assign any value you like to the `componentManufacturer` field; typically you put the signature of your sound component in this field.

The `componentFlags` field of the component description for a sound component contains bit flags that encode information about the component. You can use this field to specify that the Component Manager should send your component the `kComponentRegisterSelect` selector.

```

enum {
    cmpWantsRegisterMessage    = 1L<<31 /*send register request*/
};

```

This bit is most useful for sound output device components, which might need to test for the presence of the appropriate hardware to determine whether to register with the Component Manager. When your component gets the `kComponentRegisterSelect` selector at system startup time, it should make sure that all the necessary hardware is available. If it isn't available, your component shouldn't register. See "Registering and Opening a Sound Component" beginning on page 5-16 for more information on opening and registering your sound component.

Sound Components

You also use the `componentFlags` field of the component description to define the characteristics of your component. For example, you can set a bit in that field to indicate that your sound component can accept stereo sound data. See “Specifying Sound Component Capabilities” on page 5-11 for more details on specifying the features of your sound component.

You should set the `componentFlagsMask` field to 0.

Listing 5-1 shows, in Rez format, a component resource for a sample sound output device component named `SurfBoard`.

Listing 5-1 Rez input for a component resource

```
#define kSurfBoardID 128
#define kSurfBoardSubType 'SURF'
resource 'thng' (kSurfBoardID, purgeable) {
    'sdev', /*component type*/
    kSurfBoardSubType, /*component subtype*/
    'appl', /*component manufacturer*/
    cmpWantsRegisterMessage, /*component flags*/
    0, /*component flags mask*/
    'sift', /*component code resource type*/
    kSurfBoardID, /*component code resource ID*/
    'STR ', /*component name resource type*/
    kSurfBoardID, /*component name resource ID*/
    'STR ', /*component info resource type*/
    kSurfBoardID+1, /*component info resource ID*/
    'ICON', /*component icon resource type*/
    kSurfBoardID /*component icon resource ID*/
};
```

Your sound component is contained in a resource file. You can assign any type you wish to be the file creator, but the type of the file must be `'thng'`. If the sound component contains a `'BNDL'` resource, then the file's bundle bit must be set.

Specifying Sound Component Capabilities

As mentioned in the previous section, the `componentFlags` field of a component description for a sound component contains bit flags that encode information about the component. The high-order 8 bits of that field are reserved for use by the Component Manager. In those 8 bits, you can set the `cmpWantsRegisterMessage` bit to indicate that the Component Manager should call your component during registration.

The low-order 24 bits of the `componentFlags` field of a component description are used by the Sound Manager. You'll set some of these bits to define the capabilities of

Sound Components

your sound component. You can use the following constants to set specific bits in the `componentFlags` field.

```
#define k8BitRawIn           (1 << 0)    /*data flags*/
#define k8BitTwosIn        (1 << 1)
#define k16BitIn           (1 << 2)
#define kStereoIn          (1 << 3)
#define k8BitRawOut        (1 << 8)
#define k8BitTwosOut       (1 << 9)
#define k16BitOut          (1 << 10)
#define kStereoOut         (1 << 11)
#define kReverse            (1 << 16)    /*action flags*/
#define kRateConvert        (1 << 17)
#define kCreateSoundSource  (1 << 18)
#define kHighQuality        (1 << 22)    /*performance flags*/
#define kRealTime           (1 << 23)
```

These constants define four types of information about your sound component: the kind of audio data it can accept as input, the kind of audio data it can produce as output, the actions it can perform on the audio data it's passed, and the performance of your sound component. For example, a utility component that accepts only monaural 8-bit, offset binary data as input and converts it to 16-bit two's complement data might have the value `0x0000801` (that is, `k8BitRawIn | k16BitOut`) in the `componentFlags` field.

The Sound Manager also defines a number of masks that you can use to select ranges of bits within the `componentFlags` field. See “Sound Component Features Flags” on page 5-26 for complete information on the defined bit constants and masks.

Dispatching to Sound Component-Defined Routines

As explained earlier, the code stored in the sound component should be contained in a resource of type `kSoundComponentCodeType`. The Component Manager expects the entry point in this resource to be a function with this format:

```
pascal ComponentResult MySurfDispatch (ComponentParameters *params,
                                       SoundComponentGlobalsPtr globals);
```

The Component Manager calls your sound component by passing `MySurfDispatch` a selector in the `params->what` field; `MySurfDispatch` must interpret the selector and possibly dispatch to some other routine in the resource. Your sound component must be able to handle the required selectors, defined by these constants:

```
#define kComponentOpenSelect      -1
#define kComponentCloseSelect     -2
#define kComponentCanDoSelect     -3
#define kComponentVersionSelect   -4
```


Sound Components

```
#define kComponentRegisterSelect      -5
#define kComponentTargetSelect       -6
#define kComponentUnregisterSelect    -7
```

Note

For complete details on required component selectors, see the chapter “Component Manager” in *Inside Macintosh: More Macintosh Toolbox*. ♦

In addition, your sound component must be able to respond to component-specific selectors. Some of these selectors must be handled by your component; if your component doesn’t implement one of these selectors, it should return the `badComponentSelector` result code. Other selectors should be delegated up the component chain. This allows the Sound Manager to query a particular component chain by passing a selector to the first component in the chain. If your component does not implement a delegable selector, it should call the Component Manager routine `DelegateComponentCall` to delegate the selector to its source component. If your sound component does implement a particular delegable selector, it should perform the operation associated with it. The Sound Manager defines a constant to designate the delegable selectors.

```
/*first selector that can be delegated up the chain*/
#define kDelegatedSoundComponentSelectors    0x0100
```

The Sound Manager can pass these selectors to your sound component:

```
enum {
    /*the following calls cannot be delegated*/
    kSoundComponentInitOutputDeviceSelect      = 1,
    kSoundComponentSetSourceSelect,
    kSoundComponentGetSourceSelect,
    kSoundComponentGetSourceDataSelect,
    kSoundComponentSetOutputSelect,
    /*the following calls can be delegated*/
    kSoundComponentAddSourceSelect = kDelegatedSoundComponentSelectors + 1,
    kSoundComponentRemoveSourceSelect,
    kSoundComponentGetInfoSelect,
    kSoundComponentSetInfoSelect,
    kSoundComponentStartSourceSelect,
    kSoundComponentStopSourceSelect,
    kSoundComponentPauseSourceSelect,
    kSoundComponentPlaySourceBufferSelect
};
```

You can respond to these selectors by calling the Component Manager routine `CallComponentFunctionWithStorage` or by delegating the selector to your component’s source component. Listing 5-2 illustrates how to define a sound component entry point routine.

Listing 5-2 Handling Component Manager selectors

```

pascal ComponentResult MySurfDispatch (ComponentParameters *params,
                                       SoundComponentGlobalsPtr globals)
{
    ComponentRoutine    myRoutine;
    ComponentResult     myResult;

    /*Get address of component-defined routine.*/
    myRoutine = MyGetComponentRoutine(params->what);

    if (myRoutine == nil)                /*selector not implemented*/
        myResult = badComponentSelector;
    else if (myRoutine == kDelegateCall) /*selector should be delegated*/
        myResult = DelegateComponentCall(params, globals->sourceComponent);
    else
        myResult = CallComponentFunctionWithStorage((Handle) globals, params,
                                                    (ComponentRoutine) myRoutine);
    return (myResult);
}

```

As you can see, the `MySurfDispatch` function defined in Listing 5-2 simply retrieves the address of the appropriate component-defined routine, as determined by the `params->what` field. If the routine `MyGetComponentRoutine` returns `nil`, then `MySurfDispatch` itself returns the `badComponentSelector` result code. Otherwise, if the selector should be delegated, `MySurfDispatch` calls `DelegateComponentCall` to do so. Finally, if the selector hasn't yet been handled, the appropriate component-defined routine is executed via `CallComponentFunctionWithStorage`.

Listing 5-3 defines the function `MyGetComponentRoutine`.

Listing 5-3 Finding the address of a component-defined routine

```

ComponentRoutine MyGetComponentRoutine (short selector)
{
    void          *myRoutine;

    if (selector < 0)
        switch (selector)          /*required component selectors*/
        {
            case kComponentRegisterSelect:
                myRoutine = MyRegisterSoundComponent;
                break;
            case kComponentVersionSelect:

```

Sound Components

```

        myRoutine = MySoundComponentVersion;
        break;
    case kComponentCanDoSelect:
        myRoutine = MySoundComponentCanDo;
        break;
    case kComponentCloseSelect:
        myRoutine = MyCloseSoundComponent;
        break;
    case kComponentOpenSelect:
        myRoutine = MyOpenSoundComponent;
        break;
    default:
        myRoutine = nil;    /*unknown selector, so fail*/
        break;
}
else if (selector < kDelegatedSoundComponentSelectors)
    /*selectors that can't be delegated*/
switch (selector)
{
    case kSoundComponentInitOutputDeviceSelect:
        myRoutine = MySoundComponentInitOutputDevice;
        break;

    case kSoundComponentSetSourceSelect:
    case kSoundComponentGetSourceSelect:
    case kSoundComponentGetSourceDataSelect:
    case kSoundComponentSetOutputSelect:
    default:
        myRoutine = nil;    /*unknown selector, so fail*/
        break;
}
else    /*selectors that can be delegated*/
switch (selector)
{
    case kSoundComponentStartSourceSelect:
        myRoutine = MySoundComponentStartSource;
        break;
    case kSoundComponentPlaySourceBufferSelect:
        myRoutine = MySoundComponentPlaySourceBuffer;
        break;
    case kSoundComponentGetInfoSelect:
        myRoutine = MySoundComponentGetInfo;
        break;
}

```

Sound Components

```

        case kSoundComponentSetInfoSelect:
            myRoutine = MySoundComponentSetInfo;
            break;
        case kSoundComponentAddSourceSelect:
        case kSoundComponentRemoveSourceSelect:
        case kSoundComponentStopSourceSelect:
        case kSoundComponentPauseSourceSelect:
        default:
            myRoutine = kDelegateCall;           /*delegate it*/
            break;
    }

    return (myRoutine);
}

```

In all likelihood, your component is loaded into the system heap, although it might be loaded into an application heap if memory is low in the system heap. You can call the Component Manager function `GetComponentInstanceA5` to determine the A5 value of the current application. If this function returns 0, your component is in the system heap; otherwise, your component is in an application's heap. Its location might affect how you allocate memory. For example, calling the `MoveHHI` routine on handles in the system heap has no result. Thus, you should either call the `ReserveMemSys` routine before calling `NewHandleSys` (so that the handle is allocated as low in the system heap as possible) or else just allocate a nonrelocatable block by calling the `NewPtrSys` routine.

If you need to access resources that are stored in your sound component, you can use `OpenComponentResFile` and `CloseComponentResFile`. `OpenComponentResFile` requires the `ComponentInstance` parameter supplied to your routine. You should not call Resource Manager routines such as `OpenResFile` or `CloseResFile`.

▲ **WARNING**

Do not leave any resource files open when your sound component is closed. Their maps will be left in the subheap when the subheap is freed, causing the Resource Manager to crash. ▲

The following sections illustrate how to define some of the sound component functions.

Registering and Opening a Sound Component

The Component Manager sends your component the `kComponentRegisterSelect` selector, usually at system startup time, to allow your component to determine whether it wants to register itself with the Component Manager. Utility components should always register themselves, so that the capabilities they provide will be available when needed. Sound output device components, however, should first check to see whether any necessary hardware is available before registering themselves. If the hardware they drive isn't available, there is no point in registering with the Component Manager.

The Component Manager sends your component the `kComponentOpenSelect` selector whenever the Sound Manager wants to open a connection to your component. In general, a sound output device component has only one connection made to it. A utility component, however, might have several instances, if the capabilities it provides are needed by more than one sound component chain. Your component should do as little as possible when opening up. It should allocate whatever global storage it needs to manage the connection and call `SetComponentInstanceStorage` so that the Component Manager can remember the location of that storage and pass it to all other component-defined routines.

As noted in the previous section, your component is probably loaded into the system heap. If so, you should also allocate any global storage in the system heap. If memory is tight, however, your component might be loaded into an application's heap (namely, the heap of the first application that plays sound). In that case, you should allocate any global variables you need in that heap. The Sound Manager ensures that other applications will not try to play sound while the component is in this application heap.

IMPORTANT

Your component is always sent the `kComponentOpenSelect` component selector before it is sent the `kComponentRegisterSelect` selector. As a result, you should not attempt to initialize or configure any associated hardware in response to `kComponentOpenSelect`. ▲

The Sound Manager sends the `kSoundComponentInitOutputDeviceSelect` selector specifically to allow a sound output device component to perform any hardware-related operations. Your component should initialize the hardware to some reasonable default values, create the Apple Mixer, and allocate any other memory that might be needed. Listing 5-4 shows one way to respond to the `kSoundComponentInitOutputDeviceSelect` selector.

Listing 5-4 Initializing an output device

```
static pascal ComponentResult MySoundComponentInitOutputDevice
    (SoundComponentGlobalsPtr globals, long actions)
{
#pragma unused (actions)
    ComponentResult    myResult;

    /*Make sure we got our globals.*/
    if (globals->hwGlobals == nil)
        return (notEnoughHardwareErr);

    /*Set up the hardware.*/
    myResult = MySetupHardware(globals);
    if (myResult != noErr)
        return (myResult);
}
```

Sound Components

```

    /*Create an Apple Mixer.*/
    myResult = OpenMixerSoundComponent(&globals->thisComp, 0,
                                       &globals->sourceComponent);

    return (myResult);
}

```

The `MySoundComponentInitOutputDevice` function defined in Listing 5-4 simply retrieves the location of its global variables, configures the hardware by calling the `MySetupHardware` function, and then calls `OpenMixerSoundComponent` to create an instance of the Apple Mixer.

Finding and Changing Component Capabilities

All sound components take a stream of input data and produce a (usually different) stream of output data. The Sound Manager needs to know what operations your component can perform, so that it knows what other sound components might need to be linked together to play a particular sound on the available sound output device. It calls your component's `SoundComponentGetInfo` and `SoundComponentSetInfo` functions to get and set information about the capabilities and current settings of your sound component.

To specify the kind of information it wants to get or set, the Sound Manager passes your component a **sound component information selector**. If your component does not support a particular selector, it should pass the selector to the specified sound source. If your component does support the selector, it should either return the desired information directly or alter its settings as requested.

The sound component information selectors can specify any of a large number of audio capabilities or component settings. For example, the selector `siRateMultiplier` is passed to get or set the current output sample rate multiplier value.

Note

The Sound Manager uses many of the sound input device information selectors defined by the Sound Input Manager for communicating with sound input devices. See “Sound Input Manager” in this book for a description of the sound input device information selectors. A complete list of all sound component information selectors is provided in “Sound Component Information Selectors” beginning on page 5-22. ♦

Your component's `SoundComponentGetInfo` function has the following declaration:

```

pascal ComponentResult SoundComponentGetInfo (ComponentInstance ti,
                                             SoundSource sourceID, OSType selector,
                                             void *infoPtr);

```

The sound component information selector is passed in the `selector` parameter. The sound source is identified by the source ID passed in the `sourceID` parameter.

Sound Components

The `infoPtr` parameter specifies the location in memory of the information returned by `SoundComponentGetInfo`. If the information to be returned occupies four bytes or fewer, you can simply return the information in the location pointed to by that parameter. Otherwise, you should pass back in the `infoPtr` parameter a pointer to a record of type `SoundInfoList`, which contains an integer and a handle to an array of data items. In the second case, you'll need to allocate memory to hold the information you need to pass back. Listing 5-5 defines a component's `SoundComponentGetInfo` routine. It returns information to the Sound Manager about its capabilities and current settings.

Listing 5-5 Getting sound component information

```
static pascal ComponentResult MySoundComponentGetInfo
    (SoundComponentGlobalsPtr globals, SoundSource sourceID,
     OSType selector, void *infoPtr)
{
    HandleListPtr    listPtr;
    short            *sp, i;
    UnsignedFixed    *lp;
    Handle           h;
    HardwareGlobalsPtr hwGlobals = globals->hwGlobals;
    ComponentResult  result = noErr;

    /*Make sure we got our global variables.*/
    if (hwGlobals == nil)
        return (notEnoughHardwareErr);

    switch (selector)
    {
        case siSampleSize:                /*return current sample size*/
            *((short *) infoPtr) = hwGlobals->sampleSize;
            break;

        case siSampleSizeAvailable:       /*return sample sizes available*/
            h = NewHandle(sizeof(short) * kSampleSizesCount);
            if (h == nil)
                return (MemError());

            listPtr = (HandleListPtr) infoPtr;
            listPtr->count = 0;              /*num. sample sizes in handle*/
            listPtr->handle = h;           /*handle to be returned*/

            sp = (short *) *h;             /*store sample sizes in handle*/
```

Sound Components

```

for (i = 0; i < kSampleSizesCount; ++i)
    if (hwGlobals->sampleSizesActive[i])
    {
        listPtr->count++;
        *sp++ = hwGlobals->sampleSizes[i];
    }
break;

case siSampleRate:
    /*return current sample rate*/
    *((Fixed *) infoPtr) = hwGlobals->sampleRate;
break;

case siSampleRateAvailable:
    /*return sample rates available*/
    h = NewHandle(sizeof(UndsignedFixed) * kSampleRatesCount);
    if (h == nil)
        return (MemError());

    listPtr = (HandleListPtr) infoPtr;
    listPtr->count = 0;
    listPtr->handle = h;

    lp = (UndsignedFixed *) *h;

    /*If the hardware can support a range of sample rate values,
    the list count should be set to 0 and the minimum and maximum
    sample rate values should be stored in the handle.*/
    if (hwGlobals->supportsRateRange)
    {
        *lp++ = hwGlobals->sampleRateMin;
        *lp++ = hwGlobals->sampleRateMax;
    }

    /*If the hardware supports a limited set of sample rates,
    the list count should be set to the number of sample rates
    and this list of rates should be stored in the handle.*/
    else
    {
        for (i = 0; i < kSampleRatesCount; ++i)
            if (hwGlobals->sampleRatesActive[i])
            {
                listPtr->count++;
                *lp++ = hwGlobals->sampleRates[i];
            }
    }

```


Sound Components

```

        }
    }
    break;

case siNumberChannels:                /*return current num. channels*/
    *((short *) infoPtr) = hwGlobals->numChannels;
    break;

case siChannelAvailable:              /*return channels available*/
    h = NewHandle(sizeof(short) * kChannelsCount);
    if (h == nil)
        return (MemError());

    listPtr = (HandleListPtr) infoPtr;
    listPtr->count = 0;                 /*num. channels in handle*/
    listPtr->handle = h;               /*handle to be returned*/

    sp = (short *) *h;                /*store channels in handle*/

    for (i = 0; i < kChannelsCount; ++i)
        if (hwGlobals->channelsActive[i])
        {
            listPtr->count++;
            *sp++ = hwGlobals->channels[i];
        }
    break;

case siHardwareVolume:
    *((long *)infoPtr) = hwGlobals->volume;
    break;

/*If you do not handle a selector, delegate it up the chain.*/
default:
    result = SoundComponentGetInfo(globals->sourceComponent, sourceID,
                                   selector, infoPtr);

    break;
}
return (result);
}

```

You can define your `MySoundComponentSetInfo` routine in an exactly similar fashion.

Sound Components Reference

This section describes the constants, data structures, and routines you can use to write a sound component. It also describes the routines that your sound component should call in response to a sound component selector. See “Writing a Sound Component” on page 5-8 for information on creating a component that contains these component-defined routines.

Constants

This section provides details on the constants defined by the Sound Manager for use with sound components. You’ll use these constants to

- determine the kind of information the Sound Manager wants your sound component to return to it or settings it wants your sound component to change
- define the format of the audio data your sound component is currently producing
- specify the action flags for the `SoundComponentPlaySourceBuffer` function
- specify the format of the data your sound output device component expects to receive

Sound Component Information Selectors

The Sound Manager calls your sound component’s `SoundComponentGetInfo` and `SoundComponentSetInfo` functions to determine the capabilities of your component and to change those capabilities. It passes those functions a sound component information selector in the function’s `selector` parameter to specify the type of information it wants to get or set. The available sound component information selectors are defined by constants.

Note

Most of these selectors can be passed to both `SoundComponentGetInfo` and `SoundComponentSetInfo`. Some of them, however, can be sent to only one or the other. ♦

```
#define siChannelAvailable      'chav'    /*number of channels available*/
#define siCompressionAvailable 'cmav'    /*compression types available*/
#define siCompressionFactor    'cmfa'    /*current compression factor*/
#define siCompressionType      'comp'    /*current compression type*/
#define siHardwareMute         'hmut'    /*current hardware mute state*/
#define siHardwareVolume       'hvol'    /*current hardware volume*/
#define siHardwareVolumeSteps  'hstp'    /*number of hardware volume steps*/
#define siHeadphoneMute       'pmut'    /*current headphone mute state*/
#define siHeadphoneVolume     'pvol'    /*current headphone volume*/
```

Sound Components

```

#define siHeadphoneVolumeSteps  'hdst'  /*num. of headphone volume steps*/
#define siNumberChannels         'chan'  /*current number of channels*/
#define siQuality                'qual'  /*current quality*/
#define siRateMultiplier        'rmul'  /*current rate multiplier*/
#define siSampleRate            'srat'  /*current sample rate*/
#define siSampleRateAvailable    'srav'  /*sample rates available*/
#define siSampleSize            'ssiz'  /*current sample size*/
#define siSampleSizeAvailable    'ssav'  /*sample sizes available*/
#define siSpeakerMute           'smut'  /*current speaker mute*/
#define siSpeakerVolume         'svol'  /*current speaker volume*/
#define siVolume                'volu'  /*current volume setting*/

```

Constant descriptions**siChannelAvailable**

Get the maximum number of channels this sound component can manage, as well as the channels themselves. The `infoPtr` parameter points to a record of type `SoundInfoList`, which contains an integer (the number of available channels) and a handle to an array of integers (which represent the channel numbers themselves).

siCompressionAvailable

Get the number and list of compression types this sound component can manage. The `infoPtr` parameter points to a record of type `SoundInfoList`, which contains the number of compression types, followed by a handle that references a list of compression types, each of type `OSType`.

siCompressionFactor

Get information about the current compression type. The `infoData` parameter points to a compression information record (see page 5-32).

siCompressionType

Get or set the current compression type. The `infoPtr` parameter points to a buffer of type `OSType`, which is the compression type.

siHardwareMute

Get or set the current mute state of the audio hardware. A value of 0 indicates that the hardware is not muted, and a value of 1 indicates that the hardware is muted. Not all sound components need to support this selector; it's intended for sound output device components whose associated hardware can be muted.

siHardwareVolume

Get or set the current volume level of all sounds produced on the sound output device. The `infoPtr` parameter points to a long integer, where the high-order word represents the right volume level and the low-order word represents the left volume level. A volume level is specified by an unsigned 16-bit number: 0x0000 represents silence and 0x0100 represents full volume. (You can use the constant `kFullVolume` for full volume.) You can specify values

Sound Components

larger than 0x0100 to overdrive the volume, although doing so might result in clipping. This selector applies to the volume of the output device, whereas the `siVolume` selector applies to the volume of a specific sound channel and its component chain. If a sound output device supports more than one output port (for example, both headphones and speakers), the `siHardwareVolume` selector applies to all those ports.

`siHardwareVolumeSteps`

Get the number of audible volume levels supported by the audio hardware. If the device supports a range of volume levels (for example, 0x000 to 0x1000), you should return only the number of levels that are audible. The Sound Manager uses this information to handle the volume slider in the Alert Sounds control panel.

`siHeadphoneMute`

Get or set the current mute state of the headphone. A value of 0 indicates that the headphone is not muted, and a value of 1 indicates that the headphone is muted. Not all sound components need to support this selector; it's intended for sound output device components whose associated headphone can be muted.

`siHeadphoneVolume`

Get or set the current volume level of all sounds produced on the headphone. The `infoPtr` parameter points to a long integer, where the high-order word represents the right volume level and the low-order word represents the left volume level. A volume level is specified by an unsigned 16-bit number: 0x0000 represents silence and 0x0100 represents full volume. (You can use the constant `kFullVolume` for full volume.) You can specify values larger than 0x0100 to overdrive the volume, although doing so might result in clipping. This selector applies to the volume of the headphones.

`siHeadphoneVolumeSteps`

Get the number of audible volume levels supported by the headphones. If the headphones support a range of volume levels (for example, 0x000 to 0x1000), you should return only the number of levels that are audible.

`siNumberChannels`

Get or set the current number of audio channels currently being managed by the sound component. The `infoPtr` parameter points to an integer, which is the number of channels. For example, for stereo sounds, this integer should be 2.

`siQuality`

Get or set the current quality setting for the sound component. The `infoPtr` parameter points to a 32-bit value, which typically determines how much processing should be applied to the audio data stream.

`siRateMultiplier`

Get or set the current rate multiplier for the sound component. The `infoPtr` parameter points to a buffer of type `UnsignedFixed`, which is the multiplier to be applied to the playback rate of the sound, independent of the base sample rate of the sound. For example, if the current rate multiplier is 2.0, the sound is played

Sound Components

	back at twice the speed specified in the <code>sampleRate</code> field of the sound component data record.
<code>siSampleRate</code>	Get or set the current sample rate of the data being output by the sound component. The <code>infoPtr</code> parameter points to a buffer of type <code>UnsignedFixed</code> , which is the sample rate.
<code>siSampleRateAvailable</code>	Get the range of sample rates this sound component can handle. The <code>infoPtr</code> parameter points to a record of type <code>SoundInfoList</code> , which is the number of sample rates the component supports, followed by a handle to a list of sample rates, each of type <code>UnsignedFixed</code> . The sample rates can be in the range 0 to 65535.65535. If the number of sample rates is 0, then the first two sample rates in the list define the lowest and highest values in a continuous range of sample rates.
<code>siSampleSize</code>	Get or set the current sample size of the audio data being output by the sound component. The <code>infoPtr</code> parameter points to an integer, which is the sample size in bits.
<code>siSampleSizeAvailable</code>	Get the range of sample sizes this sound component can handle. The <code>infoPtr</code> parameter points to a record of type <code>SoundInfoList</code> , which is the number of sample sizes the sound component supports, followed by a handle. The handle references a list of sample sizes, each of type <code>Integer</code> . Sample sizes are specified in bits.
<code>siSpeakerMute</code>	Get or set the current mute state of the speakers. A value of 0 indicates that the speakers are not muted, and a value of 1 indicates that the speakers are muted. Not all sound components need to support this selector; it's intended for sound output device components whose associated speakers can be muted.
<code>siSpeakerVolume</code>	Get or set the current volume level of all sounds produced on the speakers. The <code>infoPtr</code> parameter points to a long integer, where the high-order word represents the right volume level and the low-order word represents the left volume level. A volume level is specified by an unsigned 16-bit number: 0x0000 represents silence and 0x0100 represents full volume. (You can use the constant <code>kFullVolume</code> for full volume.) You can specify values larger than 0x0100 to overdrive the volume, although doing so might result in clipping. This selector applies to the volume of the speakers.
<code>siVolume</code>	Get or set the current volume level of the sound component. The <code>infoPtr</code> parameter points to a long integer, where the high-order word represents the right volume level and the low-order word represents the left volume level. A volume level is specified by an unsigned 16-bit number: 0x0000 represents silence and 0x0100 represents full volume. (You can use the constant <code>kFullVolume</code> for full volume.) You can specify values larger than 0x0100 to overdrive the volume, although doing so might result in clipping. This selector applies to the volume of a specific sound channel and its

component chain, while the `siHardwareVolume` selector applies to the volume of the output device.

Audio Data Types

You can use the following constants to define the format of the audio data your sound component is currently producing. You can also define additional data types to denote your own compression schemes. You pass these constants in the `format` field of a sound component data record.

```
#define kOffsetBinary          'raw '
#define kTwosComplement       'twos'
#define kMACE3Compression     'MAC3 '
#define kMACE6Compression     'MAC6 '
```

Constant descriptions

`kOffsetBinary` The data is noncompressed samples in offset binary format (that is, values range from 0 to 255).

`kTwosComplement` The data is noncompressed samples in two's complement format (that is, values range from -128 to 128).

`kMACE3Compression` The data is compressed using MACE 3:1 compression.

`kMACE6Compression` The data is compressed using MACE 6:1 compression.

Sound Component Features Flags

You can use the following constants to define features of your sound component. You use some combination of these constants to set bits in the `componentFlags` field of a component description record, which is contained in a 'thng' resource. These bits represent the kind of data your component can receive as input, the kind of data your component can produce as output, the operations your component can perform, and the performance of your component.

```
#define k8BitRawIn             (1 << 0)    /*data flags*/
#define k8BitTwosIn           (1 << 1)
#define k16BitIn              (1 << 2)
#define kStereoIn             (1 << 3)
#define k8BitRawOut           (1 << 8)
#define k8BitTwosOut          (1 << 9)
#define k16BitOut             (1 << 10)
#define kStereoOut            (1 << 11)
#define kReverse               (1 << 16)   /*action flags*/
#define kRateConvert          (1 << 17)
```

Sound Components

```
#define kCreateSoundSource      (1 << 18)
#define kHighQuality           (1 << 22) /*performance flags*/
#define kRealTime              (1 << 23)
```

Constant descriptions

k8BitRawIn	The component can accept 8 bit offset binary data as input.
k8BitTwosIn	The component can accept 8 bit two's complement data as input.
k16BitIn	The component can accept 16 bit data as input. 16 bit data is always in two's complement format.
kStereoIn	The component can accept stereo data as input.
k8BitRawOut	The component can produce 8 bit offset binary data as output.
k8BitTwosOut	The component can produce 8 bit two's complement data as output.
k16BitOut	The component can produce 16 bit data as output. 16 bit data is always in two's complement format.
kStereoOut	The component can produce stereo data as output.
kReverse	The component can accept reversed audio data.
kRateConvert	The component can convert sample rates.
kCreateSoundSource	The component can create sound sources.
kHighQuality	The component can produce high quality output.
kRealTime	The component can operate in real time.

Action Flags

You can use constants to specify the action flags in the `actions` parameter of the `SoundComponentPlaySourceBuffer` function. See page 5-49 for information about this function.

```
#define kSourcePaused          (1 << 0)
#define kPassThrough           (1 << 16)
#define kNoSoundComponentChain (1 << 17)
```

Constant descriptions

kSourcePaused	If this bit is set, the component chain is configured to play the specified sound but the playback is initially paused. In this case, your <code>SoundComponentStartSource</code> function must be called to begin playback. If this bit is clear, the playback begins immediately once the component chain is set up and configured.
kPassThrough	If this bit is set, the Sound Manager passes all data through to the sound output device component unmodified. A sound output device component that can handle any sample rate and sound format described in a sound parameter block should set this bit.
kNoSoundComponentChain	If this bit is set, the Sound Manager does not construct a component chain for processing the sound data.

Data Format Flags

You can use constants to set or clear flag bits in the `outputFlags` parameter passed to the `OpenMixerSoundComponent` routine. These flags specify the format of the data your sound output device component expects to receive. See page 5-33 for information about the `OpenMixerSoundComponent` function.

IMPORTANT

Most of these flags are ignored unless the `kNoMixing` flag is set, because a sound output device component cannot perform data modifications such as sample rate conversion or sample size conversion unless it is also able to mix sound sources. ▲

```
#define kNoMixing                (1 << 0)    /*don't mix sources*/
#define kNoSampleRateConversion (1 << 1)    /*don't convert sample rate*/
#define kNoSampleSizeConversion (1 << 2)    /*don't convert sample size*/
#define kNoSampleFormatConversion \
                                (1 << 3)    /*don't convert sample format*/
#define kNoChannelConversion     (1 << 4)    /*don't convert stereo/mono*/
#define kNoDecompression         (1 << 5)    /*don't decompress*/
#define kNoVolumeConversion      (1 << 6)    /*don't apply volume*/
#define kNoRealtimeProcessing    (1 << 7)    /*don't run at interrupt time*/
```

Constant descriptions

`kNoMixing` If this bit is set, the Apple Mixer does not mix audio data sources.

`kNoSampleRateConversion`
 If this bit is set, the sound component chain does not perform sample rate conversion (for example, converting 11 kHz data to 22 kHz data).

`kNoSampleSizeConversion`
 If this bit is set, the sound component chain does not perform sample size conversion (for example, converting 8-bit data to 16-bit data).

`kNoSampleFormatConversion`
 If this bit is set, the sound component chain does not convert between sample formats (for example, converting from two's complement data to offset binary data). Most sound output devices on Macintosh computers accept only 8-bit offset binary data, which is therefore the default type of data produced by the Apple Mixer. If your output device can handle either offset binary or two's complement data, you should set this flag. Note that 16-bit data is always in two's complement format.

`kNoChannelConversion`
 If this bit is set, the sound component chain does not convert channels (for example, converting monophonic channels to stereo or stereo channels to monophonic).

`kNoDecompression`
 If this bit is set, the sound component chain does not decompress

audio data. If your output device can decompress data, you should set this flag.

`kNoVolumeConversion`

If this bit is set, the sound component chain does not convert volumes.

`kNoRealtimeProcessing`

If this bit is set, the sound component chain does not do any processing at interrupt time.

Data Structures

This section describes the data structures you need to use when writing a sound component.

Sound Component Data Records

The flow of data from one sound component to another is managed using a sound component data record. This record indicates to other sound components the format of the data that a particular component is generating, together with the location and length of the buffer containing that data. This allows other sound components to access data from that component as needed. A sound component data record is defined by the `SoundComponentData` data type.

```
typedef struct {
    long          flags;                /*sound component flags*/
    OSType        format;              /*data format*/
    short         numChannels;         /*number of channels in data*/
    short         sampleSize;         /*size of a sample*/
    UnsignedFixed sampleRate;         /*sample rate*/
    long          sampleCount;        /*number of samples in buffer*/
    Byte          *buffer;            /*location of data*/
    long          reserved;           /*reserved*/
} SoundComponentData, *SoundComponentDataPtr;
```

Field descriptions

`flags` A set of bit flags whose meanings are specific to a particular sound component.

`format` The format of the data a sound component is producing. The following formats are defined by Apple:

```
#define kOffsetBinary          'raw '
#define kTwosComplement        'twos'
#define kMACE3Compression     'MAC3'
#define kMACE6Compression     'MAC6'
```

Sound Components

	See “Audio Data Types” on page 5-26 for a description of these formats. You can define additional format types, which are currently assumed to be the types of proprietary compression algorithms.
numChannels	The number of channels of sound in the output data stream. If this field contains the value 1, the data is monophonic. If this field contains 2, the data is stereophonic. Stereo data is stored as interleaved samples, in a left-to-right ordering.
sampleSize	The size, in bits, of each sample in the output data stream. Typically this field contains the values 8 or 16. For compressed sound data, this field indicates the size of the samples after the data has been expanded.
sampleRate	The sample rate for the audio data. The sample rate is expressed as an unsigned, fixed-point number in the range 0 to 65536.0 samples per second.
sampleCount	The number of samples in the buffer pointed to by the <code>buffer</code> field. For compressed sounds, this field indicates the number of compressed samples in the sound, not the size of the buffer.
buffer	The location of the buffer that contains the sound data.
reserved	Reserved for future use. You should set this field to 0.

Sound Parameter Blocks

The Sound Manager passes a component’s `SoundComponentPlaySourceBuffer` function a **sound parameter block** that describes the source data to be modified or sent to a sound output device. A sound parameter block is defined by the `SoundParamBlock` data type.

```
struct SoundParamBlock {
    long          recordSize;    /*size of this record in bytes*/
    SoundComponentData desc;    /*description of sound buffer*/
    Fixed         rateMultiplier; /*rate multiplier*/
    short         leftVolume;    /*volume on left channel*/
    short         rightVolume;  /*volume on right channel*/
    long          quality;      /*quality*/
    ComponentInstance filter;   /*filter*/
    SoundParamProcPtr moreRtn;  /*routine to call to get more data*/
    SoundParamProcPtr completionRtn; /*buffer complete routine*/
    long          refCon;      /*user refcon*/
    short         result;     /*result*/
};
typedef struct SoundParamBlock SoundParamBlock;
typedef SoundParamBlock *SoundParamBlockPtr;
```

Field descriptions

`recordSize` The length, in bytes, of the sound parameter block.

Sound Components

<code>desc</code>	A sound component data record that describes the format, size, and location of the sound data. See “Sound Component Data Records” on page 5-29 for a description of the sound component data record.
<code>rateMultiplier</code>	A multiplier to be applied to the playback rate of the sound. This field contains an unsigned fixed-point number. If, for example, this field has the value 2.0, the sound is played back at twice the rate specified in the <code>sampleRate</code> field of the sound component data record contained in the <code>desc</code> field.
<code>leftVolume</code>	The playback volume for the left channel. You specify a volume with 16-bit value, where 0 (hexadecimal 0x0000) represents no volume and 256 (hexadecimal 0x0100) represents full volume. You can overdrive a channel’s volume by passing volume levels greater than 0x0100.
<code>rightVolume</code>	The playback volume for the right channel. You specify a volume with 16-bit value, where 0 (hexadecimal 0x0000) represents no volume and 256 (hexadecimal 0x0100) represents full volume. You can overdrive a channel’s volume by passing volume levels greater than 0x0100.
<code>quality</code>	The level of quality for the sound. This value usually determines how much processing should be applied during audio data processing (such as rate conversion and decompression) to increase the output quality of the sound.
<code>filter</code>	Reserved for future use. You should set this field to <code>nil</code> .
<code>moreRtn</code>	A pointer to a callback routine that is called to retrieve another buffer of audio data. This field is used internally by the Sound Manager.
<code>completionRtn</code>	A pointer to a callback routine that is called when the sound has finished playing. This field is used internally by the Sound Manager.
<code>refCon</code>	A value that is to be passed to the callback routines specified in the <code>moreRtn</code> and <code>completionRtn</code> fields. You can use this field to pass information (for example, the address of a structure) to a callback routine.
<code>result</code>	The status of the sound that is playing. The value 1 indicates that the sound is currently playing. The value 0 indicates that the sound has finished playing. Any negative value indicates that some error has occurred.

Sound Information Lists

The `SoundComponentGetInfo` and `SoundComponentSetInfo` functions access information about a sound component using a **sound information list**, which is defined by the `SoundInfoList` data type.

Sound Components

```
typedef struct {
    short        count;
    Handle       handle;
} SoundInfoList, *SoundInfoListPtr;
```

Field descriptions

count	The number of elements in the array referenced by the handle field.
handle	A handle to an array of data elements. The type of these data elements depends on the kind of information requested, which is determined by the selector parameter passed to <code>SoundComponentGetInfo</code> or <code>SoundComponentSetInfo</code> . See “Sound Component Information Selectors” beginning on page 5-22 for information about the available information selectors.

Compression Information Records

When the Sound Manager calls your `SoundComponentGetInfo` routine with the `siCompressionFactor` selector, you need to return a pointer to a **compression information record**, which is defined by the `CompressionInfo` data type.

```
typedef struct {
    long        recordSize;
    OSType      format;
    short       compressionID;
    short       samplesPerPacket;
    short       bytesPerPacket;
    short       bytesPerFrame;
    short       bytesPerSample;
    short       futureUse1;
} CompressionInfo, *CompressionInfoPtr, **CompressionInfoHandle;
```

Field descriptions

recordSize	The size of this compression information record.
format	The compression format.
compressionID	The compression ID.
samplesPerPacket	The number of samples in each packet.
bytesPerPacket	The number of bytes in each packet.
bytesPerFrame	The number of bytes in each frame.
bytesPerSample	The number of bytes in each sample.
futureUse1	Reserved for use by Apple Computer, Inc. You should set this field to 0.

Sound Manager Utilities

This section describes several utility routines provided by the Sound Manager that are intended for use only by sound components. You can use these routines to

- open and close the Apple Mixer component
- save and restore a user's preference settings for a sound component

Note

For a description of the routines that a sound component must implement, see “Sound Component-Defined Routines” on page 5-36. ♦

Opening and Closing the Apple Mixer Component

A sound output device component needs to open and close one or more instances of the Apple Mixer component.

OpenMixerSoundComponent

A sound output device component can use the `OpenMixerSoundComponent` function to open and connect itself to the Apple Mixer component.

```
pascal OSErr OpenMixerSoundComponent
                (SoundComponentDataPtr outputDescription,
                 long outputFlags,
                 ComponentInstance *mixerComponent);
```

`outputDescription`

A description of the data format your sound output device is expecting to receive.

`outputFlags`

A set of 32 bit flags that provide additional information about the data format your output device is expecting to receive. See “Data Format Flags” beginning on page 5-28 for a description of the constants you can use to select bits in this parameter.

`mixerComponent`

The component instance of the Apple Mixer component. You need this instance to call the `SoundComponentGetSourceData` and `CloseMixerSoundComponent` functions.

DESCRIPTION

The `OpenMixerSoundComponent` function opens the standard Apple Mixer component and creates a connection between your sound output device component and the Apple Mixer. If your output device can perform specific operations on the

Sound Components

stream of audio data, such as channel mixing and rate conversion, it should call `OpenMixerSoundComponent` as many times as are necessary to create a unique component chain for each sound source. If, on the other hand, your output device does not perform channel mixing, it should call `OpenMixerSoundComponent` only once, from its `SoundComponentInitOutputDevice` function. This opens a single instance of the Apple Mixer component, which in turn manages all the available sound sources.

Your component specifies the format of the data it can handle by filling in a sound component data record and passing its address in the `outputDescription` parameter. The sound component data record specifies the data format as well as the sample rate and sample size expected by the output device component. If these specifications are sufficient to determine the kind of data your component can handle, you should pass the value 0 in the `outputFlags` parameter. Otherwise, you can set flags in the `outputFlags` parameter to select certain kinds of input data. For example, you can set the `kNoChannelConversion` flag to prevent the component chain from converting monophonic sound to stereo sound, or stereo sound to monophonic sound. See “Data Format Flags” beginning on page 5-28 for a description of the constants you can use to select bits in the `outputFlags` parameter.

SPECIAL CONSIDERATIONS

The `OpenMixerSoundComponent` function is available only in versions 3.0 and later of the Sound Manager. It should be called only by sound output device components.

CloseMixerSoundComponent

A sound output device component can use the `CloseMixerSoundComponent` function to close the Apple Mixer.

```
pascal OSErr CloseMixerSoundComponent (ComponentInstance ci);
```

`ci` The component instance of the Apple Mixer component.

DESCRIPTION

The `CloseMixerSoundComponent` function closes the Apple Mixer component instance specified by the `ci` parameter. Your output device component should call this function when it is being closed.

SPECIAL CONSIDERATIONS

The `CloseMixerSoundComponent` function is available only in versions 3.0 and later of the Sound Manager. It should be called only by sound output device components.

RESULT CODES

<code>noErr</code>	0	No error
<code>invalidComponentID</code>	-3000	Invalid component ID

Saving and Restoring Sound Component Preferences

A sound component can use the `SetSoundPreference` and `GetSoundPreference` functions to save and restore a user's preference settings.

SetSoundPreference

A sound component can use the `SetSoundPreference` function to have the Sound Manager store a block of preferences data in a resource file. You're most likely to use this function in a sound output device component, although other types of sound components can use it also.

```
pascal OSErr SetSoundPreference (OSType type, Str255 name,
                                Handle settings);
```

<code>type</code>	The resource type to be used to create the preferences resource.
<code>name</code>	The resource name to be used to create the preferences resource.
<code>settings</code>	A handle to the data to be stored in the preferences resource.

DESCRIPTION

The `SetSoundPreference` function causes the Sound Manager to attempt to create a new resource that contains preferences data for your sound component. You can use this function to maintain a structure of any format across subsequent startups of the machine. You'll retrieve the preferences data by calling the `GetSoundPreference` function. The data is stored in a resource with the specified type and name in a resource file in the Preferences folder in the System Folder. In general, the resource type and name should be the same as the sound component subtype and name.

The `settings` parameter is a handle to the preferences data you want to store. It is the responsibility of your component to allocate and initialize the block of data referenced by that handle. The Sound Manager copies the handle's data into a resource in the appropriate location. Your sound component should dispose of the handle when `SetSoundPreference` returns.

The format of the block of preferences data referenced by the `settings` parameter is defined by your sound component. It is recommended that you include a field specifying the version of the data format; this allows you to modify the format of the block of data while remaining compatible with previous formats you might have defined.

SPECIAL CONSIDERATIONS

The `SetSoundPreference` function is available only in versions 3.0 and later of the Sound Manager.

GetSoundPreference

A sound component can use the `GetSoundPreference` function to have the Sound Manager read a block of preferences data from a resource file. You'll use it to retrieve a block of preferences data you previously saved by calling `SetSoundPreference`.

```
pascal OSErr GetSoundPreference (OSType type, Str255 name,
                                Handle settings);
```

`type` The resource type of the preferences resource.
`name` The resource name of the preferences resource.
`settings` A handle to the data in the preferences resource.

DESCRIPTION

The `GetSoundPreference` function retrieves the block of preferences data you previously stored in a resource by calling the `SetSoundPreference` function. It is the responsibility of your component to allocate the block of data referenced by the `settings` handle. The Sound Manager resizes the handle (if necessary) and fills it with data from the resource with the specified type and name. Your sound component should dispose of the handle once it's finished reading the data from it. You can determine the size of the handle returned by the Sound Manager by calling the Memory Manager's `GetHandleSize` function.

SPECIAL CONSIDERATIONS

The `GetSoundPreference` function is available only in versions 3.0 and later of the Sound Manager.

Sound Component-Defined Routines

This section describes the routines you need to define in order to write a sound component. You need to write routines to

- load, configure, and unload your sound component
- add and remove audio sources
- read and set component settings
- control and process audio data

Sound Components

Some of these routines are optional for some types of sound components. All routines return result codes. If they succeed, they should return `noErr`. To simplify dispatching, the Component Manager requires these routines to return a value of type `ComponentResult`.

See “Writing a Sound Component” beginning on page 5-8 for a description of how you call these routines from within a sound component. See “Sound Manager Utilities” beginning on page 5-33 for a description of some Sound Manager utility routines you can use in a sound component.

Managing Sound Components

To write a sound component, you might need to define routines that manage the loading, configuration, and unloading of your sound component:

- `SoundComponentInitOutputDevice`
- `SoundComponentSetSource`
- `SoundComponentGetSource`
- `SoundComponentGetSourceData`
- `SoundComponentSetOutput`

After the Sound Manager opens your sound component, it attempts to add your sound component to a sound component chain. Thereafter, the Sound Manager calls your component’s `SoundComponentInitOutputDevice` function to give you an opportunity to set default values for any associated hardware and to perform any hardware-specific operations.

SoundComponentInitOutputDevice

A sound output device component must implement the `SoundComponentInitOutputDevice` function. The Sound Manager calls this function to allow a sound output device component to configure any associated hardware devices.

```
pascal ComponentResult SoundComponentInitOutputDevice
    (ComponentInstance ti, long actions);
```

`ti` A component instance that identifies your sound component.

`actions` A set of flags. This parameter is currently unused.

DESCRIPTION

Your `SoundComponentInitOutputDevice` function is called by the Sound Manager at noninterrupt time to allow your sound output device component to perform any hardware-specific initialization. You should perform any necessary initialization that

Sound Components

was not already performed in your `OpenComponent` function. Note that your `OpenComponent` function cannot assume that the appropriate hardware is available. As a result, the Sound Manager calls your `SoundComponentInitOutputDevice` function when it is safe to communicate with your audio hardware. You can call the `OpenMixerSoundComponent` function to create a single sound component chain.

SPECIAL CONSIDERATIONS

Your `SoundComponentInitOutputDevice` function is always called at noninterrupt time. All other component-defined routines might be called at interrupt time. Accordingly, your `SoundComponentInitOutputDevice` function should handle any remaining memory allocation needed by your component and it should lock down any relocatable blocks your component will access.

RESULT CODES

Your `SoundComponentInitOutputDevice` function should return `noErr` if successful or an appropriate result code otherwise.

SEE ALSO

See Listing 5-4 on page 5-17 for a sample `SoundComponentInitOutputDevice` function.

SoundComponentSetSource

A sound component can implement the `SoundComponentSetSource` function. The Sound Manager calls this function to identify your component's source component.

```
pascal ComponentResult SoundComponentSetSource
    (ComponentInstance ti,
     SoundSource sourceID,
     ComponentInstance source);
```

<code>ti</code>	A component instance that identifies your sound component.
<code>sourceID</code>	A source ID for the source component chain created by the Apple Mixer.
<code>source</code>	A component instance that identifies your source component.

DESCRIPTION

Your `SoundComponentSetSource` function is called by the Sound Manager to identify to your sound component the sound component that is its source. The source component is identified by the `source` parameter. Your component uses that information when it

Sound Components

needs to obtain more data from its source (usually, by calling its `SoundComponentGetSourceData` function).

Because a sound output device component is always connected directly to one or more instances of the Apple Mixer, the `SoundComponentSetSource` function needs to be implemented only by utility components (that is, components that perform modifications on sound data). Utility components are linked together into a chain of sound components, each link of which has only one input source. As a result, a utility component can usually ignore the `sourceID` parameter passed to it.

RESULT CODES

Your `SoundComponentSetSource` function should return `noErr` if successful or an appropriate result code otherwise.

SoundComponentGetSource

A sound component can implement the `SoundComponentGetSource` function. The Sound Manager calls this function to determine your component's source component.

```
pascal ComponentResult SoundComponentGetSource
    (ComponentInstance ti,
     SoundSource sourceID,
     ComponentInstance *source);
```

<code>ti</code>	A component instance that identifies your sound component.
<code>sourceID</code>	A source ID for the source component chain created by the Apple Mixer.
<code>source</code>	A component instance that identifies your source component.

DESCRIPTION

Your `SoundComponentGetSource` function is called by the Sound Manager to retrieve your component's source component instance. Your component should return, in the `source` parameter, the component instance of your component's source. This should be the source component instance your component was passed when the Sound Manager called your `SoundComponentSetSource` function.

In general, all sound components have sources, except for the source at the beginning of the source component chain. In the unlikely event that your component does not have a source, you should return `nil` in the `source` parameter. A sound output device component is always connected directly to an instance of the Apple Mixer. Accordingly, a sound output device component should return a component instance of the Apple Mixer in the `source` parameter and a source ID in the `sourceID` parameter. A utility component can ignore the `sourceID` parameter.

RESULT CODES

Your `SoundComponentGetSource` function should return `noErr` if successful or an appropriate result code otherwise.

SoundComponentGetSourceData

A utility component must implement the `SoundComponentGetSourceData` function. A sound output device component calls this function on its source component when it needs more data.

```
pascal ComponentResult SoundComponentGetSourceData
    (ComponentInstance ti,
     SoundComponentDataPtr *sourceData);
```

`ti` A component instance that identifies your sound component.

`sourceData` On output, a pointer to a sound component data record that specifies the type and location of the data your component has processed.

DESCRIPTION

Your `SoundComponentGetSourceData` function is called when the sound component immediately following your sound component in the sound component chain needs more data. Your function should generate a new block of audio data, fill out a sound component data record describing the format and location of that data, and then return the address of that record in the `sourceData` parameter.

Your `SoundComponentGetSourceData` function might itself need to get more data from its source component. To do this, call through to the source component's `SoundComponentGetSourceData` function. If your component cannot generate any more data, it should set the `sampleCount` field of the sound component data record to 0 and return `noErr`.

IMPORTANT

Sound output device components do not need to implement this function, but all utility components must implement it. ▲

RESULT CODES

Your `SoundComponentGetSourceData` function should return `noErr` if successful or an appropriate result code otherwise.

SoundComponentSetOutput

A sound output device component can call the `SoundComponentSetOutput` function of the Apple Mixer to indicate the type of data it expects to receive.

```
pascal ComponentResult SoundComponentSetOutput
    (ComponentInstance ti,
     SoundComponentDataPtr requested,
     SoundComponentDataPtr *actual);
```

`ti` A component instance that identifies your sound component.

`requested` A pointer to a sound component data record that specifies the type of the data your component expects to receive.

`actual` This parameter is currently unused.

DESCRIPTION

The Apple Mixer's `SoundComponentSetOutput` function can be called by a sound output device component to specify the kind of audio data the output device component wants to receive. The Apple Mixer uses that information to determine the type of sound component chain it needs to construct in order to deliver that kind of audio data to your sound output device component. For example, if your sound output device is able to accept 16-bit samples, the Sound Manager doesn't need to convert 16-bit audio data into 8-bit data.

The following lines of code illustrate how the sound output device component for the Apple Sound Chip might call Apple Mixer's `SoundComponentSetOutput` function:

```
myDataRec.flags = 0;                            /*ignored here*/
myDataRec.format = kOffsetBinary;            /*ASC needs offset binary*/
myDataRec.sampleRate = rate22khz;           /*ASC needs 22 kHz samples*/
myDataRec.sampleSize = 8;                    /*ASC needs 8-bit data*/
myDataRec.numChannels = 2;                   /*ASC can do stereo*/
myDataRec.sampleCount = 1024;               /*ASC uses a 1K FIFO*/
myErr = SoundComponentSetOutput(mySource, &myDataRec, &myActual);
```

In general, however, a sound output device component shouldn't need to call the Apple Mixer's `SoundComponentSetOutput` function. Instead, it can indicate the type of data it expects to receive when it calls the `OpenMixerSoundComponent` function. The `SoundComponentSetOutput` function is intended for sophisticated sound output device components that might want to reinitialize the Apple Mixer.

IMPORTANT

Only the Apple Mixer component needs to implement this function. ▲

RESULT CODES

The Apple Mixer's `SoundComponentSetOutput` function returns `noErr` if successful or an appropriate result code otherwise.

Creating and Removing Audio Sources

To write a sound output device component, you might need to define two routines that create and remove audio sources:

- `SoundComponentAddSource`
- `SoundComponentRemoveSource`

Your component needs to contain these functions only if, like the Apple Mixer, it can mix two or more audio channels into a single output stream. Sound components that operate on a single input stream only do not need to include these functions.

SoundComponentAddSource

A sound output device component that can mix multiple channel of audio data must implement the `SoundComponentAddSource` function to add a new sound source.

```
pascal ComponentResult SoundComponentAddSource
    (ComponentInstance ti, SoundSource *sourceID);
```

`ti` A component instance that identifies your sound component.

`sourceID` On exit, a source ID for the newly created source component chain.

DESCRIPTION

The `SoundComponentAddSource` function is called by the Sound Manager to create a new sound source. If your sound output device component can mix multiple channels of sound, it needs to define this function. Your `SoundComponentAddSource` function should call the Sound Manager function `OpenMixerSoundComponent` to create a new instance of the Apple Mixer component. The Apple Mixer component then creates a sound component chain capable of generating the type of data your sound output device component wants to receive.

The Apple Mixer also assigns a unique 4-byte source ID that identifies the new sound source and component chain. You can retrieve that source ID by calling the Apple Mixer's `SoundComponentAddSource` function. Your `SoundComponentAddSource` function should then pass that source ID back to the Sound Manager in the `sourceID` parameter.

IMPORTANT

Most sound components do not need to implement the `SoundComponentAddSource` function. Only sound components that can handle more than one source of input need to define it. ▲

SPECIAL CONSIDERATIONS

The `SoundComponentAddSource` function is called at noninterrupt time.

RESULT CODES

Your `SoundComponentAddSource` function should return `noErr` if successful or an appropriate result code otherwise.

SEE ALSO

See page 5-33 for a description of `OpenMixerSoundComponent`.

SoundComponentRemoveSource

A sound output device component that implements the `SoundComponentAddSource` function must also implement the `SoundComponentRemoveSource` function to remove sound sources.

```
pascal ComponentResult SoundComponentRemoveSource
    (ComponentInstance ti, SoundSource sourceID);
```

`ti` A component instance that identifies your sound component.

`sourceID` A source ID for the source component chain to be removed.

DESCRIPTION

Your `SoundComponentRemoveSource` function is called by the Sound Manager to remove the existing sound source specified by the `sourceID` parameter. Your `SoundComponentRemoveSource` function should do whatever is necessary to invalidate that source and then call through to the Apple Mixer's `SoundComponentRemoveSource` function.

IMPORTANT

Most sound components do not need to implement the `SoundComponentRemoveSource` function. Only sound components that can handle more than one source of input need to define it. ▲

SPECIAL CONSIDERATIONS

Your `SoundComponentRemoveSource` function is always called at noninterrupt time.

RESULT CODES

Your `SoundComponentRemoveSource` function should return `noErr` if successful or an appropriate result code otherwise.

Getting and Setting Sound Component Information

To write a sound component, you need to define two routines that determine the capabilities of your component or to change those capabilities:

- `SoundComponentGetInfo`
- `SoundComponentSetInfo`

SoundComponentGetInfo

A sound component must implement the `SoundComponentGetInfo` function. The Sound Manager calls this function to get information about the capabilities of your component.

```
pascal ComponentResult SoundComponentGetInfo
    (ComponentInstance ti,
     SoundSource sourceID,
     OSType selector, void *infoPtr);
```

<code>ti</code>	A component instance that identifies your sound component.
<code>sourceID</code>	A source ID for a source component chain.
<code>selector</code>	A sound component information selector. See “Sound Component Information Selectors” beginning on page 5-22 for a description of the available selectors.
<code>infoPtr</code>	On output, a pointer to the information requested by the caller.

DESCRIPTION

Your `SoundComponentGetInfo` function returns information about your sound component. The `sourceID` parameter specifies the sound source to return information about, and the `selector` parameter specifies the kind of information to be returned. If the information occupies 4 or fewer bytes, it should be returned in the location pointed to by the `infoPtr` parameter. If the information is larger than 4 bytes, the `infoPtr` parameter is a pointer to a component information list, a 6-byte structure of type `SoundInfoList`:

Sound Components

```
typedef struct {
    short          count;
    Handle         handle;
} SoundInfoList, *SoundInfoListPtr;
```

This structure consists of a count and a handle to a variable-sized array. The `count` field specifies the number of elements in the array to which `handle` is a handle. It is your component's responsibility to allocate the block of data referenced by that handle, but it is the caller's responsibility to dispose of that handle once it is finished with it.

The data type of the array elements depends on the kind of information being returned. For example, the selector `siSampleSizeAvailable` indicates that you should return a list of the sample sizes your component can support. You return the information by passing back, in the `infoPtr` parameter, a pointer to an integer followed by a handle to an array of integers.

If your component cannot provide the information specified by the `selector` parameter, it should pass the selector to its source component.

SPECIAL CONSIDERATIONS

Your `SoundComponentGetInfo` function is not called at interrupt time if it is passed a selector that might cause it to allocate memory for the handle in the component information list.

RESULT CODES

Your `SoundComponentGetInfo` function should return `noErr` if successful or an appropriate result code otherwise.

SEE ALSO

See "Finding and Changing Component Capabilities" on page 5-18 for a sample `SoundComponentGetInfo` function.

SoundComponentSetInfo

A sound component must implement the `SoundComponentSetInfo` function. The Sound Manager calls this function to modify settings of your component.

```
pascal ComponentResult SoundComponentSetInfo
    (ComponentInstance ti,
     SoundSource sourceID,
     OSType selector, void *infoPtr);
```

`ti` A component instance that identifies your sound component.

Sound Components

<code>sourceID</code>	A source ID for a source component chain.
<code>selector</code>	A sound component information selector. See “Sound Component Information Selectors” beginning on page 5-22 for a description of the available selectors.
<code>infoPtr</code>	A pointer to the information your component is to use to modify its settings. If the information occupies 4 or fewer bytes, however, this parameter contains the information itself, not the address of the information.

DESCRIPTION

Your `SoundComponentSetInfo` function is called by the Sound Manager to set one of the settings for your component, as specified by the `selector` parameter. If the information associated with that selector occupies 4 or fewer bytes, it is passed on the stack, in the `infoPtr` parameter itself. Otherwise, the `infoPtr` parameter is a pointer to a structure of type `SoundInfoList`. See the description of `SoundComponentGetInfo` for more information about the `SoundInfoList` structure.

If your component cannot modify the settings specified by the `selector` parameter, it should pass the selector to its source component.

RESULT CODES

Your `SoundComponentSetInfo` function should return `noErr` if successful or an appropriate result code otherwise.

Managing Source Data

To write a sound output device component, you might need to define routines that manage the flow of data in a sound channel:

- `SoundComponentStartSource`
- `SoundComponentStopSource`
- `SoundComponentPauseSource`
- `SoundComponentPlaySourceBuffer`

SoundComponentStartSource

A sound output device component must implement the `SoundComponentStartSource` function. The Sound Manager calls this function to start playing sounds in one or more sound channels.

Sound Components

```
pascal ComponentResult SoundComponentStartSource
    (ComponentInstance ti,
     short count, SoundSource *sources);
```

`ti` A component instance that identifies your sound component.

`count` The number of source IDs in the array pointed to by the `source` parameter.

`sources` An array of source IDs.

DESCRIPTION

Your `SoundComponentStartSource` function is called by the Sound Manager to begin playing the sounds originating from the sound sources specified by the `sources` parameter. Your function should start (or resume) sending data from those sources to the associated sound output device. If your component supports only one sound source, you can ignore the `sources` parameter.

SPECIAL CONSIDERATIONS

Your `SoundComponentStartSource` function can be called at interrupt time.

RESULT CODES

Your `SoundComponentStartSource` function should return `noErr` if successful or an appropriate result code otherwise. You should return `noErr` even if no sounds are playing in the specified channels.

SoundComponentStopSource

A sound output device component must implement the `SoundComponentStopSource` function. The Sound Manager calls this function to stop playing sounds in one or more sound channels.

```
pascal ComponentResult SoundComponentStopSource
    (ComponentInstance ti, short count,
     SoundSource *sources);
```

`ti` A component instance that identifies your sound component.

`count` The number of source IDs in the array pointed to by the `source` parameter.

`sources` An array of source IDs.

DESCRIPTION

Your `SoundComponentStopSource` function is called by the Sound Manager to stop the sounds originating from the sound sources specified by the `sources` parameter. Your function should stop sending data from those sources to the associated sound output device. In addition, your `SoundComponentStopSource` function should flush any data from the specified sound sources that it's caching. If your component supports only one sound source, you can ignore the `sources` parameter.

RESULT CODES

Your `SoundComponentStopSource` function should return `noErr` if successful or an appropriate result code otherwise. You should return `noErr` even if no sounds are playing in the specified channels.

SoundComponentPauseSource

A sound output device component must implement the `SoundComponentPauseSource` function. The Sound Manager calls this function to stop pause the playing of sounds in one or more sound channels.

```
pascal ComponentResult SoundComponentPauseSource
    (ComponentInstance ti,
     short count, SoundSource *sources);
```

<code>ti</code>	A component instance that identifies your sound component.
<code>count</code>	The number of source IDs in the array pointed to by the <code>source</code> parameter.
<code>sources</code>	An array of source IDs.

DESCRIPTION

Your `SoundComponentPauseSource` function is called by the Sound Manager to pause the playing of the sounds originating from the sound sources specified by the `sources` parameter. Your function should stop sending data from those sources to the associated sound output device. Because your `SoundComponentStartSource` function might be called to resume playing sounds, you should not flush any data. If your component supports only one sound source, you can ignore the `sources` parameter.

RESULT CODES

Your `SoundComponentPauseSource` function should return `noErr` if successful or an appropriate result code otherwise. You should return `noErr` even if no sounds are playing in the specified channels.

SoundComponentPlaySourceBuffer

A sound component must implement the `SoundComponentPlaySourceBuffer` function. The Sound Manager calls this function to start a new sound playing.

```
pascal ComponentResult SoundComponentPlaySourceBuffer
    (ComponentInstance ti,
     SoundSource sourceID,
     SoundParamBlockPtr pb,
     long actions);
```

<code>ti</code>	A component instance that identifies your sound component.
<code>sourceID</code>	A source ID for a source component chain.
<code>pb</code>	A pointer to a sound parameter block.
<code>actions</code>	A set of 32 bit flags that describe the actions to be taken when preparing to play the source data. See “Action Flags” on page 5-27 for a description of the constants you can use to select bits in this parameter.

DESCRIPTION

Your `SoundComponentPlaySourceBuffer` function is called by the Sound Manager to start a new sound playing. The sound parameter block pointed to by the `pb` parameter specifies the sound to be played. That parameter block should be passed successively to all sound components in the chain specified by the `sourceID` parameter. This allows the components to determine their output formats and playback settings and to prepare for a subsequent call to their `SoundComponentGetSourceData` function. It also allows a sound output device component to prepare for starting up its associated hardware.

RESULT CODES

Your `SoundComponentPlaySourceBuffer` function should return `noErr` if successful or an appropriate result code otherwise.

Summary of Sound Components

This section provides a C summary for the constants, data types, and routines you can use to write a sound component. There are currently no Pascal interfaces available for writing sound components.

C Summary

Constants

```

/*component types*/
#define kSoundComponentType      'sift'    /*utility component*/
#define kMixerType               'mixr'    /*mixer component*/
#define kSoundHardwareType       'sdev'    /*sound output device component*/
#define kSoundCompressor         'scom'    /*compression component*/
#define kSoundDecompressor       'sdec'    /*decompression component*/
#define kNoSoundComponentType    '****'    /*no type*/

/*subtypes for kSoundComponentType component type*/
#define kRate8SubType            'ratb'    /*8-bit rate converter*/
#define kRate16SubType           'ratw'    /*16-bit rate converter*/
#define kConverterSubType        'conv'    /*sample format converter*/
#define kSndSourceSubType        'sour'    /*generic source component*/

/*subtypes for kMixerType component type*/
#define kMixer8SubType           'mixb'    /*8-bit mixer*/
#define kMixer16SubType          'mixw'    /*16-bit mixer*/

/*subtypes for kSoundHardwareType component type*/
#define kClassicSubType          'clas'    /*Classic hardware*/
#define kASCSubType              'asc '    /*ASC device*/
#define kDSPSubType              'dsp '    /*DSP device*/

/*subtypes for kSoundCompressor and kSoundDecompressor component types*/
#define kMace3SubType            'MAC3'    /*MACE 3:1*/
#define kMace6SubType            'MAC6 '   /*MACE 6:1*/
#define kCDXA4SubType            'CDX4'    /*CD/XA 4:1*/
#define kCDXA2SubType            'CDX2'    /*CD/XA 2:1*/

#define kSoundComponentCodeType  'sift'    /*sound component code type*/

```

Sound Components

```

/*first selector that can be delegated up the chain*/
#define kDelegatedSoundComponentSelectors      0x0100

/*Component Manager selectors for routines*/
enum {
    /*the following calls cannot be delegated*/
    kSoundComponentInitOutputDeviceSelect      = 1,
    kSoundComponentSetSourceSelect,
    kSoundComponentGetSourceSelect,
    kSoundComponentGetSourceDataSelect,
    kSoundComponentSetOutputSelect,
    /*the following calls can be delegated*/
    kSoundComponentAddSourceSelect = kDelegatedSoundComponentSelectors + 1,
    kSoundComponentRemoveSourceSelect,
    kSoundComponentGetInfoSelect,
    kSoundComponentSetInfoSelect,
    kSoundComponentStartSourceSelect,
    kSoundComponentStopSourceSelect,
    kSoundComponentPauseSourceSelect,
    kSoundComponentPlaySourceBufferSelect
};

/*sound component information selectors*/
#define siChannelAvailable      'chav' /*number of channels available*/
#define siCompressionAvailable  'cmav' /*compression types available*/
#define siCompressionFactor     'cmfa' /*current compression factor*/
#define siCompressionType       'comp' /*current compression type*/
#define siHardwareMute          'hmut' /*current hardware mute state*/
#define siHardwareVolume        'hvol' /*current hardware volume*/
#define siHardwareVolumeSteps   'hstp' /*number of hardware volume steps*/
#define siHeadphoneMute         'pmut' /*current headphone mute state*/
#define siHeadphoneVolume       'pvol' /*current headphone volume*/
#define siHeadphoneVolumeSteps  'hdst' /*num. of headphone volume steps*/
#define siNumberChannels        'chan' /*current number of channels*/
#define siQuality                'qual' /*current quality*/
#define siRateMultiplier        'rmul' /*current rate multiplier*/
#define siSampleRate            'srat' /*current sample rate*/
#define siSampleRateAvailable   'srav' /*sample rates available*/
#define siSampleSize            'ssiz' /*current sample size*/
#define siSampleSizeAvailable   'ssav' /*sample sizes available*/
#define siSpeakerMute          'smut' /*current speaker mute*/
#define siSpeakerVolume         'svol' /*current speaker volume*/
#define siVolume                'volu' /*current volume setting*/

```

Sound Components

```

/*audio data format types*/
#define kOffsetBinary          'raw '
#define kTwosComplement       'twos'
#define kMACE3Compression     'MAC3'
#define kMACE6Compression     'MAC6'

/*sound component features flags*/
#define k8BitRawIn             (1 << 0)    /*data flags*/
#define k8BitTwosIn           (1 << 1)
#define k16BitIn              (1 << 2)
#define kStereoIn             (1 << 3)
#define k8BitRawOut           (1 << 8)
#define k8BitTwosOut          (1 << 9)
#define k16BitOut             (1 << 10)
#define kStereoOut            (1 << 11)

#define kReverse               (1 << 16)    /*action flags*/
#define kRateConvert          (1 << 17)
#define kCreateSoundSource    (1 << 18)

#define kHighQuality          (1 << 22)    /*performance flags*/
#define kRealTime             (1 << 23)

/*action flags for SoundComponentPlaySourceBuffer*/
#define kSourcePaused         (1 << 0)
#define kPassThrough          (1 << 16)
#define kNoSoundComponentChain (1 << 17)

/*flags for OpenMixerSoundComponent*/
#define kNoMixing              (1 << 0)    /*don't mix sources*/
#define kNoSampleRateConversion (1 << 1)  /*don't convert sample rate*/
#define kNoSampleSizeConversion (1 << 2)  /*don't convert sample size*/
#define kNoSampleFormatConversion \
                                (1 << 3)  /*don't convert sample format*/
#define kNoChannelConversion  (1 << 4)  /*don't convert stereo/mono*/
#define kNoDecompression      (1 << 5)  /*don't decompress*/
#define kNoVolumeConversion   (1 << 6)  /*don't apply volume*/
#define kNoRealtimeProcessing (1 << 7)  /*don't run at interrupt time*/

/*quality flags*/
#define kBestQuality          (1 << 0)    /*use interp. in rate conv.*/

```


Sound Components

```

/*volume specifications*/
#define kSilenceByte          0x80
#define kSilenceLong         0x80808080
#define kFullVolume          0x0100

```

Data Types

Unsigned Fixed-Point Numbers

```
typedef unsigned long UnsignedFixed; /*unsigned fixed-point number*/
```

Sound Component Data Record

```

typedef struct {
    long          flags;          /*sound component flags*/
    OSType        format;        /*data format*/
    short         numChannels;    /*number of channels in data*/
    short         sampleSize;    /*size of a sample*/
    UnsignedFixed sampleRate;    /*sample rate*/
    long          sampleCount;    /*number of samples in buffer*/
    Byte          *buffer;       /*location of data*/
    long          reserved;      /*reserved*/
} SoundComponentData, *SoundComponentDataPtr;

```

Sound Parameter Block

```

typedef pascal Boolean (*SoundParamProcPtr)(SoundParamBlockPtr *pb);

struct SoundParamBlock {
    long          recordSize;    /*size of this record in bytes*/
    SoundComponentData desc;    /*description of sound buffer*/
    Fixed         rateMultiplier; /*rate multiplier*/
    short         leftVolume;    /*volume on left channel*/
    short         rightVolume;   /*volume on right channel*/
    long          quality;       /*quality*/
    ComponentInstance filter;   /*filter*/
    SoundParamProcPtr moreRtn;   /*routine to call to get more data*/
    SoundParamProcPtr completionRtn; /*buffer complete routine*/
    long          refCon;        /*user refcon*/
    short         result;        /*result*/
};

typedef struct SoundParamBlock SoundParamBlock;
typedef SoundParamBlock *SoundParamBlockPtr;

```

Sound Source

```
typedef struct privateSoundSource *SoundSource;
```

Sound Information List

```
typedef struct {
    short        count;
    Handle       handle;
} SoundInfoList, *SoundInfoListPtr;
```

Compression Information Record

```
typedef struct {
    long         recordSize;
    OSType       format;
    short        compressionID;
    short        samplesPerPacket;
    short        bytesPerPacket;
    short        bytesPerFrame;
    short        bytesPerSample;
    short        futureUse1;
} CompressionInfo, *CompressionInfoPtr, **CompressionInfoHandle;
```

Sound Manager Utilities

Opening and Closing the Apple Mixer Component

```
pascal OSErr OpenMixerSoundComponent
    (SoundComponentDataPtr outputDescription,
     long outputFlags,
     ComponentInstance *mixerComponent);

pascal OSErr CloseMixerSoundComponent
    (ComponentInstance ci);
```

Saving and Restoring Sound Component Preferences

```
pascal OSErr SetSoundPreference
    (OSType type, Str255 name, Handle settings);

pascal OSErr GetSoundPreference
    (OSType type, Str255 name, Handle settings);
```

Sound Component-Defined Routines

Managing Sound Components

```

pascal ComponentResult SoundComponentInitOutputDevice
    (ComponentInstance ti, long actions);
pascal ComponentResult SoundComponentSetSource
    (ComponentInstance ti, SoundSource sourceID,
     ComponentInstance source);
pascal ComponentResult SoundComponentGetSource
    (ComponentInstance ti, SoundSource sourceID,
     ComponentInstance *source);
pascal ComponentResult SoundComponentGetSourceData
    (ComponentInstance ti,
     SoundComponentDataPtr *sourceData);
pascal ComponentResult SoundComponentSetOutput
    (ComponentInstance ti,
     SoundComponentDataPtr requested,
     SoundComponentDataPtr *actual);

```

Creating and Removing Audio Sources

```

pascal ComponentResult SoundComponentAddSource
    (ComponentInstance ti, SoundSource *sourceID);
pascal ComponentResult SoundComponentRemoveSource
    (ComponentInstance ti, SoundSource sourceID);

```

Getting and Setting Sound Component Information

```

pascal ComponentResult SoundComponentGetInfo
    (ComponentInstance ti, SoundSource sourceID,
     OSType selector, void *infoPtr);
pascal ComponentResult SoundComponentSetInfo
    (ComponentInstance ti, SoundSource sourceID,
     OSType selector, void *infoPtr);

```

Managing Source Data

```

pascal ComponentResult SoundComponentStartSource
    (ComponentInstance ti, short count,
     SoundSource *sources);
pascal ComponentResult SoundComponentStopSource
    (ComponentInstance ti, short count,
     SoundSource *sources);

```

Sound Components

```

pascal ComponentResult SoundComponentPauseSource
    (ComponentInstance ti, short count,
     SoundSource *sources);

pascal ComponentResult SoundComponentPlaySourceBuffer
    (ComponentInstance ti, SoundSource sourceID,
     SoundParamBlockPtr pb, long actions);

```

Assembly-Language Summary

Data Structures

Sound Component Data Record

0	flags	long	sound component flags
4	format	long	data format
8	numChannels	word	number of channels in data
10	sampleSize	word	size of a sample
12	sampleRate	long	sample rate (Fixed)
16	sampleCount	long	number of samples in buffer
20	buffer	long	location of data
24	reserved	long	reserved

Sound Parameter Block

0	recordSize	long	size of this record in bytes
4	desc	28 bytes	description of sound buffer
32	rateMultiplier	long	rate multiplier (Fixed)
36	leftVolume	word	volume on left channel
38	rightVolume	word	volume on right channel
40	quality	long	quality
44	filter	long	filter
48	moreRtn	long	routine to call to get more data
52	completionRtn	long	buffer complete routine
56	refCon	long	user refcon
60	result	word	result

Sound Information List

0	count	word	number of data items in the handle
2	handle	long	handle to list of data items

Compression Information Record

0	recordSize	long	the size of this record
4	format	4 bytes	compression format
8	compressionID	word	compression ID
10	samplesPerPacket	word	the number of samples per packet
12	bytesPerPacket	word	the number of bytes per packet
14	bytesPerFrame	word	the number of bytes per frame
16	bytesPerSample	word	the number of bytes per sample
18	futureUse1	word	reserved

Audio Components

Contents

About Audio Components	6-3
Writing an Audio Component	6-5
Creating an Audio Component	6-5
Dispatching to Audio Component-Defined Routines	6-7
Audio Components Reference	6-8
Data Structures	6-8
Audio Information Records	6-9
Audio Component-Defined Routines	6-9
Getting and Setting Volumes	6-10
Managing the Mute State	6-11
Resetting Audio Components	6-13
Getting Audio Component Information	6-13
Summary of Audio Components	6-15
C Summary	6-15
Constants	6-15
Data Types	6-16
Audio Component-Defined Routines	6-16
Assembly-Language Summary	6-17
Data Structures	6-17

This chapter describes audio components, which are code modules used by the Sound Manager to adjust volumes or other settings of a sound output device. In general, you need to write an audio component only if you are developing a sound output device with multiple output ports that can be independently controlled by software. If your sound output device has only one software-controllable output port, the sound output device component for that device manages the volume levels of the port.

IMPORTANT

The Sound Manager loads and manages audio components, which operate transparently to applications. The routines described in this chapter are intended for use exclusively by audio components. ▲

To use this chapter, you should already be familiar with writing sound output device components, as described in the chapter “Sound Components” in this book. Because audio components are components, you also need to be familiar with the Component Manager, described in *Inside Macintosh: More Macintosh Toolbox*.

This chapter begins by describing what audio components are and the Sound Manager uses them. Then it provides instructions on how to write an audio component. The section “Audio Components Reference” beginning on page 6-8 describes the routines that your audio component might need to define.

Note

Pascal interfaces for audio components are not currently available. As a result, this chapter provides all source code examples and reference materials in C. ♦

About Audio Components


An **audio component** is a component that works with the Sound Manager to adjust volumes or other settings of a sound output device. The Sound Manager uses audio components, however, only when a particular sound output device has more than one audio port that can be controlled through software. If a sound output device has only one audio port, the sound component that communicates with the output device controls the volume settings of that port.

IMPORTANT

Because audio components are currently used to manage only volume and mute settings, they might have been called *volume components*. The more general term anticipates future capabilities of audio components. For example, audio components might in the future be used to modify bass or treble settings of an audio port. ▲


An **audio port** is any independently controllable sound-producing hardware connected or attached to a sound output device. For example, the Apple AudioVision 14 Display (shown in Figure 6-1) contains two audio ports: a set of speakers and a jack for headphones.

Figure 6-1 The Apple AudioVision 14 Display



As the Volumes subpanel of the Sound control panel shows (Figure 6-2), the two audio ports are independently controllable by software.

Figure 6-2 The Volumes control panel for the Apple AudioVision 14 Display



The control panel shown in Figure 6-2 contains volume sliders both for the set of speakers and for the headphones. The volume of the speakers is controlled by the sound component that drives the sound output device. The volume of the headphones is controlled by an audio component.

In short, audio components are used to allow a single sound output device to have more than one audio port. The sound component that communicates with that device can control the volume setting of one audio port; audio components control the volume settings of all other audio ports.

Writing an Audio Component

Because an audio component is a component, it must be able to respond to standard selectors sent by the Component Manager. In addition, an audio component must handle other selectors specific to audio components. This section briefly describes how to write an audio component.

Creating an Audio Component

An audio component is a component. It contains a number of resources, including icons, strings, and the standard component resource (a resource of type 'tng') required of any Component Manager component. In addition, an audio component must contain code to handle required selectors passed to it by the Component Manager as well as selectors specific to the audio component.

Note

For complete details on components and their structure, see the chapter “Component Manager” in *Inside Macintosh: More Macintosh Toolbox*. This section provides specific information about audio components. ♦

The component resource binds together all the relevant resources contained in a component; its structure is defined by the `ComponentResource` data type.

```
struct ComponentResource {
    ComponentDescription    cd;
    ResourceSpec            component;
    ResourceSpec            componentName;
    ResourceSpec            componentInfo;
    ResourceSpec            componentIcon;
};
```

The `component` field specifies the resource type and resource ID of the component's executable code. By convention, this field should be set to the value `kAudioCodeType`.

```
#define kAudioCodeType    'adio'    /*audio component code type*/
```

Audio Components

(You can, however, specify some other resource type if you wish.) The resource ID can be any integer greater than or equal to 128. See the following section for further information about this code resource.

The `componentName` field specifies the resource type and resource ID of the resource that contains the component's name. Usually the name is contained in a resource of type 'STR'. This string should be as short as possible.

The `componentInfo` field specifies the resource type and resource ID of the resource that contains a description of the component. Usually the description is contained in a resource of type 'STR'.

The `componentIcon` field specifies the resource type and resource ID of the resource that contains an icon for the component. Usually the icon is contained in a resource of type 'ICON'.

The `cd` field of the `ComponentResource` structure is a **component description record**, which contains additional information about the component. A component description record is defined by the `ComponentDescription` data type.

```
typedef struct {
    OSType          componentType;
    OSType          componentSubType;
    OSType          componentManufacturer;
    unsigned long   componentFlags;
    unsigned long   componentFlagsMask;
} ComponentDescription;
```

For audio components, the `componentType` field must be set to a value recognized by the Sound Manager.

```
#define kAudioComponentType    'adio'    /*audio component*/
```

In addition, the `componentSubType` field must be set to a value that indicates the type of audio services your component provides. For example, the Apple-supplied audio components have these subtypes:

```
#define kAwacsPhoneSubType      'hphn'    /*AWACS phone*/
#define kAudioVisionSpeakerSubType 'telc'    /*AudioVision speaker*/
#define kAudioVisionHeadphoneSubType 'telh'    /*AudioVision headphones*/
```

If you write an audio component, you should define some other subtype.

Note

Apple Computer, Inc., reserves for its own use all types and subtypes composed solely of lowercase letters. ♦

You can assign any value you like to the `componentManufacturer` field; typically you put the signature of your audio component in this field.

Audio Components

The `componentFlags` field of the component description for an audio component contains bit flags that encode information about the component. You can use this field to specify that the Component Manager should send your component the `kComponentRegisterSelect` selector.

```
enum {
    cmpWantsRegisterMessage    = 1L<<31 /*send register request*/
};
```

This bit is useful for audio components, which might need to test for the presence of the appropriate hardware to determine whether to register with the Component Manager. When your component gets the `kComponentRegisterSelect` selector at system startup time, it should make sure that all the necessary hardware is available. If it isn't available, your component shouldn't register.

You should set the `componentFlagsMask` field to 0.

Your audio component is contained in a resource file. You can assign any type you wish to be the file creator, but the type of the file must be 'thng'. If the audio component contains a 'BNDL' resource, then the file's bundle bit must be set.

Dispatching to Audio Component-Defined Routines

As explained in the previous section, the code stored in the audio component should be contained in a resource of type `kAudioCodeType`. The Component Manager expects the entry point in this resource to be a function with this format:

```
pascal ComponentResult MyAudioDispatch (ComponentParameters *params,
                                       AudioGlobalsPtr globals);
```

The Component Manager calls your sound component by passing `MyAudioDispatch` a selector in the `params->what` field; `MyAudioDispatch` must interpret the selector and possibly dispatch to some other routine in the resource. Your audio component must be able to handle the required selectors, defined by these constants:

```
#define kComponentOpenSelect          -1
#define kComponentCloseSelect         -2
#define kComponentCanDoSelect         -3
#define kComponentVersionSelect       -4
#define kComponentRegisterSelect      -5
#define kComponentTargetSelect        -6
#define kComponentUnregisterSelect     -7
```

Note

For complete details on required component selectors, see the chapter "Component Manager" in *Inside Macintosh: More Macintosh Toolbox*. ♦

In addition, your audio component must be able to respond to component-specific selectors. The Sound Manager can pass these selectors to your audio component:

Audio Components

```
enum {
    kAudioGetVolumeSelect = 0,
    kAudioSetVolumeSelect,
    kAudioGetMuteSelect,
    kAudioSetMuteSelect,
    kAudioSetToDefaultsSelect,
    kAudioGetInfoSelect
};
```

You can respond to these selectors by calling the Component Manager routine `CallComponentFunctionWithStorage`. See the section “Audio Component-Defined Routines” beginning on page 6-9 for information on how to handle these selectors.

In all likelihood, your component is loaded into the system heap, although it might be loaded into an application heap if memory is low in the system heap. You can call the Component Manager function `GetComponentInstanceA5` to determine the A5 value of the current application. If this function returns 0, your component is in the system heap; otherwise, your component is in an application’s heap. Its location might affect how you allocate memory. For example, calling the `MoveHHI` routine on handles in the system heap has no result. Thus, you should either call the `ReserveMemSys` routine before calling `NewHandleSys` (so that the handle is allocated as low in the system heap as possible) or else just allocate a nonrelocatable block by calling the `NewPtrSys` routine.

If you need to access resources that are stored in your audio component, you can use `OpenComponentResFile` and `CloseComponentResFile`. `OpenComponentResFile` requires the `ComponentInstance` parameter supplied to your routine. You should not call Resource Manager routines such as `OpenResFile` or `CloseResFile`.

▲ **WARNING**

Do not leave any resource files open when your audio component is closed. Their maps will be left in the subheap when the subheap is freed, causing the Resource Manager to crash. ▲

Audio Components Reference

This section describes the data structures you can use to write an audio component. It also describes the routines that your audio component should call in response to an audio component selector. See “Writing an Audio Component” beginning on page 6-5 for information on creating a component that contains these component-defined routines.

Data Structures

This section describes the data structure you need to use when writing an audio component.

Audio Information Records

You return information about the capabilities of your audio component in the `info` parameter passed to your `AudioGetInfo` function. The `info` parameter contains a pointer to an **audio information record**. An audio information record is defined by the `AudioInfo` data type.

```
typedef struct {
    long            capabilitiesFlags;    /*device capabilities*/
    long            reserved;            /*reserved*/
    unsigned short numVolumeSteps;      /*number of volume steps*/
} AudioInfo, *AudioInfoPtr;
```

Field descriptions

`capabilitiesFlags`

A set of bit flags specifying the capabilities of the audio component. You can use constants to set some of these bits:

```
#define audioDoesMono          (1L<<0) /*supports mono output*/
#define audioDoesStereo       (1L<<1) /*supports stereo output*/
#define audioDoesIndependentChannels (1L<<2) /*supports independent
                                             software control of each channel*/
```

`reserved` Reserved for use by Apple Computer, Inc.

`numVolumeSteps`

The number of volume steps your audio component supports.

Audio Component-Defined Routines

This section describes the routines you must define in order to write an audio component. You need to write routines to

- get and set volume levels of a sound output device
- manage mute states
- reset device settings
- get information about the audio component

All routines return result codes. If they succeed, they should return `noErr`. To simplify dispatching, the Component Manager requires these routines to return a value of type `ComponentResult`.

See “Writing an Audio Component” beginning on page 6-5 for a description of how you call these routines from within an audio component.

Getting and Setting Volumes

To write an audio component, you might need to define two routines that manage the volume level of the associated audio port:

- `AudioGetVolume`
- `AudioSetVolume`

AudioGetVolume

An audio component can implement the `AudioGetVolume` function. The Sound Manager calls this function to determine the current volume of an audio port.

```
pascal ComponentResult AudioGetVolume (ComponentInstance ac,
                                        short whichChannel,
                                        ShortFixed *volume);
```

`ac` A component instance that identifies your audio component.

`whichChannel` The channel or channels whose volume you should return.

`volume` On output, the current volume level of the specified channel.

DESCRIPTION

Your `AudioGetVolume` function is called by the Sound Manager to determine the current volume levels of one or more channels of an audio port. The `volume` parameter can have any value between 0 and 1, where 0 indicates minimum volume and 1 indicates maximum volume. The `whichChannel` parameter indicates the channels or channels whose volumes you should return. The following constants are defined for the `whichChannel` parameter:

```
#define audioAllChannels            0            /*all channels*/
#define audioLeftChannel           1            /*left channel*/
#define audioRightChannel          2            /*right channel*/
```

RESULT CODES

Your `AudioGetVolume` function should return `noErr` if successful or an appropriate result code otherwise. In particular, if your audio component doesn't support software control of volume levels, `AudioGetVolume` should return `unImpErr`.

AudioSetVolume

An audio component can implement the `AudioSetVolume` function. The Sound Manager calls this function to set the current volume of an audio port.

```
pascal ComponentResult AudioSetVolume (ComponentInstance ac,
                                        short whichChannel,
                                        ShortFixed volume);
```

`ac` A component instance that identifies your audio component.

`whichChannel` The channel or channels whose volume you should set.

`volume` The desired volume level of the specified channel.

DESCRIPTION

Your `AudioSetVolume` function is called by the Sound Manager to set the volume levels of one or more channels of an audio port. See the description of the `AudioGetVolume` function for the values of the `whichChannel` and `volume` parameters.

RESULT CODES

Your `AudioSetVolume` function should return `noErr` if successful or an appropriate result code otherwise. In particular, if your audio component doesn't support software control of volume levels, `AudioSetVolume` should return `unImpErr`.

Managing the Mute State

To write an audio component, you might need to define two routines that manage the mute state of the associated audio port:

- `AudioGetMute`
- `AudioSetMute`

AudioGetMute

An audio component can implement the `AudioGetMute` function. The Sound Manager calls this function to determine the current mute state of an audio port.

```
pascal ComponentResult AudioGetMute (ComponentInstance ac,
                                        short whichChannel,
                                        short *mute);
```

Audio Components

<code>ac</code>	A component instance that identifies your audio component.
<code>whichChannel</code>	The channel or channels whose mute state you should return.
<code>mute</code>	On output, the current mute state of the specified channel.

DESCRIPTION

Your `AudioGetMute` function is called by the Sound Manager to determine the current mute state of one or more channels of an audio port. The following constants define the mute states you can return in the `mute` parameter:

```
#define audioUnmuted      0      /*device is not muted*/
#define audioMuted       1      /*device is muted*/
```

The `whichChannel` parameter indicates the channels or channels whose mute state you should return. The following constants are defined for the `whichChannel` parameter:

```
#define audioAllChannels  0      /*all channels*/
#define audioLeftChannel  1      /*left channel*/
#define audioRightChannel 2      /*right channel*/
```

RESULT CODES

Your `AudioGetMute` function should return `noErr` if successful or an appropriate result code otherwise. In particular, if your audio component doesn't support software control of mute states, `AudioGetMute` should return `unImpErr`.

AudioSetMute

An audio component can implement the `AudioSetMute` function. The Sound Manager calls this function to set the current mute state of an audio port.

```
pascal ComponentResult AudioSetMute (ComponentInstance ac,
                                     short whichChannel,
                                     short mute);
```

<code>ac</code>	A component instance that identifies your audio component.
<code>whichChannel</code>	The channel or channels whose mute state you should set.
<code>mute</code>	The desired mute state of the specified channel.

DESCRIPTION

Your `AudioSetMute` function is called by the Sound Manager to set the mute state of one or more channels of an audio port. See the description of the `AudioGetMute` function for the values of the `whichChannel` and `mute` parameters.

RESULT CODES

Your `AudioSetMute` function should return `noErr` if successful or an appropriate result code otherwise. In particular, if your audio component doesn't support software control of mute states, `AudioSetMute` should return `unImpErr`.

Resetting Audio Components

To write an audio component, you need to define the `AudioSetToDefaults` routine, which resets the associated audio port to its default settings.

AudioSetToDefaults

The Sound Manager might call your `AudioSetToDefaults` function to reset an audio port.

```
pascal ComponentResult AudioSetToDefaults (ComponentInstance ac);
```

`ac` A component instance that identifies your audio component.

DESCRIPTION

Your `AudioSetToDefaults` function should reset its volume and mute levels to some reasonable default value. It should also reset to reasonable values any other settings it might be maintaining privately.

RESULT CODES

Your `AudioSetToDefaults` function should return `noErr` if successful or an appropriate result code otherwise.

Getting Audio Component Information

To write an audio component, you need to define the `AudioGetInfo` routine, which returns information about the capabilities of your component.

AudioGetInfo

An audio component must implement the `AudioGetInfo` function. The Sound Manager calls this function to get information about the capabilities of your component.

```
pascal ComponentResult AudioGetInfo (ComponentInstance ac,  
                                     AudioInfoPtr info);
```

`ac` A component instance that identifies your sound component.

`info` A pointer to an audio information record.

DESCRIPTION

Your `AudioGetInfo` function returns information about your audio component. You should fill out the audio information record pointed to by the `info` parameter. See “Audio Information Records” beginning on page 6-9 for a description of the audio information record.

RESULT CODES

Your `AudioGetInfo` function should return `noErr` if successful or an appropriate result code otherwise.

Summary of Audio Components

This section provides a C summary for the constants, data types, and routines you can use to write an audio component. There are currently no Pascal interfaces available for writing audio components.

C Summary

Constants

```

/*component types*/
#define kAudioComponentType          'adio'  /*audio component*/

/*subtypes for kAudioComponentType component type*/
#define kAwacsPhoneSubType          'hphn'  /*AWACS phone*/
#define kAudioVisionSpeakerSubType  'telc'  /*AudioVision speaker*/
#define kAudioVisionHeadphoneSubType 'telh' /*AudioVision headphones*/

#define kAudioCodeType              'adio'  /*audio component code type*/

/*Component Manager selectors for routines*/
enum {
    kAudioGetVolumeSelect = 0,
    kAudioSetVolumeSelect,
    kAudioGetMuteSelect,
    kAudioSetMuteSelect,
    kAudioSetToDefaultsSelect,
    kAudioGetInfoSelect
};

/*values for whichChannel parameter*/
#define audioAllChannels          0          /*all channels*/
#define audioLeftChannel          1          /*left channel*/
#define audioRightChannel         2          /*right channel*/

/*values for mute parameter*/
#define audioUnmuted              0          /*device is not muted*/
#define audioMuted                1          /*device is muted*/

```

Audio Components

```

/*audio component features flags*/
#define audioDoesMono          (1L<<0) /*supports mono output*/
#define audioDoesStereo       (1L<<1) /*supports stereo output*/
#define audioDoesIndependentChannels (1L<<2) /*supports independent
                                             software control of each channel*/

```

Data Types

Short Fixed-Point Numbers

```
typedef short ShortFixed;
```

Audio Information Record

```

typedef struct {
    long          capabilitiesFlags; /*device capabilities*/
    long          reserved;         /*reserved*/
    unsigned short numVolumeSteps; /*number of volume steps*/
} AudioInfo, *AudioInfoPtr;

```

Audio Component-Defined Routines

Getting and Setting Volumes

```

pascal ComponentResult AudioGetVolume
    (ComponentInstance ac, short whichChannel,
     ShortFixed *volume);

pascal ComponentResult AudioSetVolume
    (ComponentInstance ac, short whichChannel,
     ShortFixed volume);

```

Managing the Mute State

```

pascal ComponentResult AudioGetMute
    (ComponentInstance ac, short whichChannel,
     short *mute);

pascal ComponentResult AudioSetMute
    (ComponentInstance ac, short whichChannel,
     short mute);

```

Resetting Audio Components

```

pascal ComponentResult AudioSetToDefaults
    (ComponentInstance ac);

```

Getting Audio Component Information

```
pascal ComponentResult AudioGetInfo
    (ComponentInstance ac, AudioInfoPtr info);
```

Assembly-Language Summary

Data Structures

Audio Information Record

0	capabilitiesFlags	long	device capabilities
4	reserved	long	reserved
8	numVolumeSteps	word	number of volume steps

Glossary

AGC See **automatic gain control**.

AIFF See **Audio Interchange File Format**.

AIFF-C See **Audio Interchange File Format Extension for Compression**.

alert sound See **system alert sound**.

Alert Sounds control panel A subpanel of the Sound control panel that allows the user to select a system alert sound. See also **Sound In control panel**, **Sound Out control panel**, **Volumes control panel**.

allophone A distinct variety of a phoneme in a particular language that is never used contrastingly with any other allophone of the phoneme.

amplitude A modification to the wave amplitude of a sound to make it sound louder or softer. See also **speech volume**. Compare **wave amplitude**.

Apple Mixer See **Apple Mixer component**.

Apple Mixer component A sound component that is responsible for mixing together the audio data streams from all open sound channels.

Apple Sound Chip (ASC) A custom chip that, in conjunction with other circuitry, generates a stereo sound signal that drives the internal speaker or an external sound jack. Compare **Enhanced Apple Sound Chip**.

ASC See **Apple Sound Chip**.

asynchronous sound play The playing of sound during other, non-sound related operations. Compare **synchronous sound play**.

audio compression A technique of reducing the amount of memory space required for a buffer of sampled-sound data, usually at the expense of audio fidelity. See also **audio expansion**.

audio component A component that works with the Sound Manager to adjust volumes or other settings of a sound output device. Compare **sound component**.

audio data See **sampled-sound data**, **sound**, **square-wave data**, **wave-table data**.

audio decompression See **audio expansion**.

audio expansion The decompression of compressed sound data. See also **audio compression**.

audio information record A structure you can use to specify information about an audio component. Defined by the `AudioInfo` data type.

Audio Interchange File Format (AIFF) A sound storage file format designed to allow easy exchange of audio data among applications.

Audio Interchange File Format Extension for Compression (AIFF-C) An extension of the Audio Interchange File Format that allows for the storage of compressed sound data.

audio port Any independently-controllable sound-producing hardware connected or attached to a sound output device. A sound output device can have several audio ports.

audio selection record A structure you can use to specify that only part of a sound be played. Defined by the `AudioSelection` data type.

automatic gain control (AGC) A feature of sound recording that moderates the recording to give a consistent signal level.

base frequency The pitch at which a sampled sound is recorded. The wave of a sampled sound may include frequencies other than the base frequency (and need not even include the base frequency).

baseline pitch See **speech pitch**.

buffered expansion Audio expansion of a sound that does not occur while the sound is playing. Compare **real-time expansion**.

callback procedure An application-defined procedure that is invoked at a specified time or based on specified criteria.

channel A portion of sound data that can be described by a single sound wave. Do not confuse with sound channel or speech channel. See also **monophonic sound**, **stereo sound**.

chunk Any distinct portion of a sound file.

chunk header The first segment of a chunk, which defines the characteristics of the chunk. Defined by the `ChunkHeader` data type.

codec See **compression/decompression component**.

command See **embedded speech command**, **sound command**.

command delimiter A sequence of one or two characters that indicates the start or end of an embedded speech command.

component A piece of code that provides a defined set of services to one or more clients. Applications, system extensions, and other components can use the services of a component. See also **audio component**, **sound component**.

component description record A structure that contains information about a component. Defined by the `ComponentDescription` data type.

Component Manager A collection of routines that allows your application or other clients to access components. The Component Manager manages components and also provides services to components.

compressed sound data Sampled-sound data that has been subjected to audio compression.

compressed sound header A sound header that can describe noncompressed and compressed sampled-sound data, whether monophonic or stereo. Defined by the `CmpSoundHeader` data type. See also **extended sound header**, **sampled sound header**.

compression See **audio compression**.

compression/decompression component (codec) A component that handles data compression and decompression.

compression information record A structure you use to specify information about a sound component that can decompress compressed audio data. Defined by the `CompressionInfo` data type.

computer-generated speech See **synthesized speech**.

continuous play from disk See **play from disk**.

continuous recording A feature of a sound input device driver that allows recording from the device while other processing continues.

current sound input device The sound input device that the user has chosen through the Sound In subpanel of the Sound control panel.

current sound output device The sound output device that the user has chosen through the Sound Out subpanel of the Sound control panel.

DAC See **digital-to-analog convertor**.

decompressed sound data Sampled-sound data that has been subjected to audio compression and expansion.

decompression See **audio expansion**.

delimiter See **command delimiter**.

delimiter information record A structure that defines the characters used to indicate the beginning and end of a command embedded in text. Defined by the `DelimiterInfo` data type.

dictionary See **pronunciation dictionary**.

digital signal processor (DSP) A processor that manipulates digital data.

digital-to-analog convertor (DAC) A device that converts data from digital to analog form.

double buffering A technique used by the Sound Manager to manage a play from disk. When using this technique, the Sound Manager plays one buffer of sampled-sound data while filling a second with more data. When the first buffer of sound finishes playing, the Sound Manager plays the data in the second buffer while filling the first with more data. See also **play from disk, sampled-sound data**.

drop-sample conversion A form of sample rate conversion that uses an existing sample as an interpolated sample point. Compare **linear interpolation**.

DSP See **digital signal processor**.

duration The length of time that a sound takes to play.

EASC See **Enhanced Apple Sound Chip**.

embedded speech command In a buffer of input text, a sequence of characters enclosed by command delimiters that provides instructions to a speech synthesizer.

ending prosody The rhythm, modulation, and stress patterns associated with the end of a sentence of speech.

Enhanced Apple Sound Chip (EASC) A modified Apple Sound Chip that generates stereo sound using pulse-code modulation. Compare **Apple Sound Chip**.

enhanced Sound Manager Any version of the Sound Manager greater than 2.0.

error callback procedure An application-defined procedure that is executed whenever the Speech Manager encounters an error in an embedded speech command in a buffer of input text.

expansion See **audio expansion**.

extended sound header A sound header that can describe monophonic and stereo sampled-sound data, but not compressed sound data. Defined by the `ExtSoundHeader` data type. See also **compressed sound header, sampled sound header**.

FIFO See **first-in, first-out**.

Finder sound file A file of file type `'sfil'` containing a sound resource. If a user opens a Finder sound file, the Finder plays the sound resource contained within it. See also **sound file, sound resource**.

first-in, first-out (FIFO) Characteristic of a queue in which the first item put into the queue becomes the first item to be taken out of it. Compare **last-in, first out**.

frequency The number of times per second that an action occurs. An action's frequency is measured in cycles per second, or hertz. See also **period**.

gain The ratio of the output volume to the input volume. See also **automatic gain control**.

hertz (Hz) A unit of frequency, equal to one cycle per second.

instrument A sampled sound played at varying rates to produce a number of different pitches or notes. See also **voice**.

interleaving The technique of combining two or more channels of sound data by alternating small pieces of the data in each channel into a single data stream. See also **sample frame**.

interpolation The process of generating sample points between two given sample points. See also **linear interpolation**.

kilohertz (kHz) A unit of frequency, equal to one thousand cycles per second.

last-in, first out (LIFO) Characteristic of a queue in which the last item put into the queue becomes the first item to be taken out of it. Compare **first-in, first out**.

LIFO See **last-in, first-out**.

linear interpolation A form of interpolation that uses the calculated mean of two sample points as the interpolated sample point. Compare **drop-sample conversion**.

MACE See **Macintosh Audio Compression and Expansion**.

Macintosh Audio Compression and Expansion (MACE) A set of Sound Manager routines that allow your application to compress and expand audio data.

megahertz (MHz) A unit of frequency, equal to one million cycles per second.

microsecond A unit of time equal to one millionth of a second. Abbreviated μ s.

MIDI See **Musical Instrument Digital Interface**.

MIDI Manager The part of the Macintosh system software that controls the flow of MIDI data and commands through a MIDI interface.

MIDI note value An integer that is defined to correspond to a frequency specified in hertz that is associated with a musical note.

millisecond A unit of time equal to one thousandth of a second. Abbreviated ms.

modulation of speech See **pitch modulation**.

monophonic sound. Sound consisting of a single channel. Compare **stereo sound**.

multichannel sound See **stereo sound**.

Musical Instrument Digital Interface (MIDI) A standard protocol for sending audio data and commands to digital devices.

noncompressed sound data Sampled-sound data that has not been subjected to audio compression or that has been decompressed.

note See **frequency**, **MIDI note value**.

offset-binary encoding A method of digitally encoding sound that represents the range of amplitude values as an unsigned number, with the midpoint of the range representing silence. For example, an 8-bit sound stored in offset-binary format would contain sample values ranging from 0 to 255, with a value of 128 specifying silence (no amplitude). Samples in Macintosh sound resources are stored in offset-binary form. See also **two's complement encoding**.

packet A unit of compressed sampled-sound data. One or more packets make up a sample frame of compressed sampled-sound data. See also **sample point**.

period The time elapsed during one complete cycle. See also **frequency**.

phoneme A speech sound in a language that a speaker of the language psychologically considers to be a single unit. A single phoneme may have several allophones.

phoneme callback procedure An application-defined procedure that is executed whenever the Speech Manager is about to pronounce a phoneme.

phoneme descriptor record A structure that contains information about all phonemes defined for the current synthesizer. Defined by the `PhonemeDescriptor` data type.

phoneme information record A structure that contains information about a phoneme. Defined by the `PhonemeInfo` data type.

phonemic representation of speech The representation of speech using a series of phonemes.

phonetic representation of speech The representation of speech using a series of allophones.

pitch A listener's subjective interpretation of a sound's frequency. See also **speech pitch**.

pitch modulation A fixed-point value defined on a scale from 0.000 to 100.000 that indicates the maximum amount by which the frequency of generated speech may deviate from that corresponding to the speech pitch in either direction. A value of 0.000 corresponds to a monotone.

play from disk The ability of the Sound Manager to play sampled sounds stored on disk (either in a sound file or a sound resource) continuously without audible gaps.

playthrough A feature of sound recording that allows the user to hear, through the speaker of a Macintosh computer, the sound being recorded.

polyphonic sound See **stereo sound**.

pronunciation dictionary A list of words and their pronunciations, installed in a speech channel to override default speech synthesizer pronunciations of words.

pronunciation dictionary resource A pronunciation dictionary stored in a resource of type 'dict'.

prosody The rhythm, modulation, and stress patterns of speech.

rate See **sample rate**, **speech rate**.

real-time expansion Audio expansion of a sound that occurs while the sound is playing. Compare **buffered expansion**.

recording The process of creating an analog or digital representation of a sound. See also **sampling**.

sample See **sample point**.

sampled sound Any sound defined using sampled-sound data.

sampled-sound data Any set of values that represent the sample points of a sampled sound. The values can be in either offset-binary format or two's complement format.

sampled sound header A sound header that can describe monophonic, noncompressed sampled-sound data. Defined by the `SoundHeader` data type. See also **compressed sound header**, **extended sound header**.

sample frame An interleaved set of sample points (for noncompressed sampled-sound data) or packets (for compressed sampled-sound data).

sample point A value representing the amplitude of sampled-sound data at a particular instant. One or more sample points make up a sample frame of noncompressed sampled-sound data. See also **packet**.

sample rate The rate at which samples are recorded. Sample rates are usually measured in kilohertz or megahertz.

sampling The process of representing a sound by measuring its amplitude at discrete points in time. See also **recording**.

sifter See **sound component**.

sound Anything perceived by the organs of hearing. See also **frequency**, **pitch**, **stereo sound**, **timbre**.

sound channel A path that sound data traverses from an application to the sound output device. A sound channel is associated with a queue of sound commands and with other information about the audio characteristics of the sound data. See also **sound channel record**.

sound channel record A structure that represents a sound channel. Defined by the `SndChannel` data type.

sound channel status record A structure whose address you pass to the `SndChannelStatus` function. Defined by the `SCStatus` data type.

sound command An instruction to produce sound, modify sound, or otherwise assist in the overall process of sound production. See also **sound command record**.

sound command record A structure that describes a sound command. Defined by the `SndCommand` data type.

sound component A component that works with the Sound Manager to manipulate audio data or to communicate with a sound output device. See also **audio component**, **compression/decompression component**, **sound output device component**, **utility component**.

sound component chain A chain of sound components that links a sound source to a sound output device.

sound component data record A structure that specifies information about the data stream generated by a sound component. Defined by the `SoundComponentData` data type.

sound component information selector A value of type `OSType` that indicates the kind of information a sound component should return or modify.

Sound control panel A control panel that allows the user to specify basic sound-related settings and preferences. See also **Alert Sounds control panel**, **Sound In control panel**, **Sound Out control panel**, **Volumes control panel**.

sound data See **sampled-sound data**, **sound**, **square-wave data**, **wave-table data**.

sound double buffer header record A structure that you use to manage your own double-buffering scheme. Defined by the `SndDoubleBufferHeader` and `SndDoubleBufferHeader2` data types.

sound double buffer record A structure that you use to manage your own double-buffering scheme. Defined by the `SndDoubleBuffer` data type.

Sound Driver A device driver on the original Macintosh computers that provided sound generation. The Sound Driver is now obsolete; it has been replaced by the Sound Manager.

sound file A file of file type 'AIFF' or 'AIFC' that can be used to store sampled-sound data and information about that data. See also **Audio Interchange File Format, Audio Interchange File Format Extension for Compression, chunk, Finder sound file, sound resource**.

sound header A data structure (usually stored in a sound resource) that contains information about a buffer of sampled-sound data. See also **compressed sound header, extended sound header, sampled sound header**.

Sound In control panel A subpanel of the Sound control panel that allows the user to select a sound input device. See also **Alert Sounds control panel, Sound Out control panel, Volumes control panel**.

sound information list A structure that specifies the information associated with a sound component information selector. Defined by the `SoundInfoList` data type.

sound input device Any hardware device (such as a microphone or audio digitizer) that records sound.

sound input device driver A standard Macintosh device driver used by the Sound Manager to manage communication between applications and a sound input device.

sound input device information selector A variable of type `OSType` that is used to specify the type of information that an application or the Sound Input Manager is requesting from a sound input device driver.

Sound Input Manager The part of the Macintosh system software that controls the recording of sound from sound input devices.

sound input parameter block A parameter block that contains information about sound recording. Defined by the `SPB` data type.

Sound Manager The part of the Macintosh system software that manages the production and manipulation of sounds on Macintosh computers.

Sound Manager status record A structure filled in by the `SndManagerStatus` function, which gives information on the current CPU loading caused by all open channels of sound. Defined by the `SMStatus` data type.

Sound Out control panel A subpanel of the Sound control panel that allows the user to select a sound output device. See also **Alert Sounds control panel, Sound In control panel, Volumes control panel**.

sound output device Any hardware device (such as a speaker or sound synthesizer) that produces sound.

sound output device component A sound component that communicates with a sound output device. See also **compression/decompression component and utility component**.

sound parameter block A parameter block that describes the source data to be modified or sent to a sound output device. Defined by the `SoundParamBlock` data type.

sound recording dialog box The dialog box displayed by the Sound Input Manager when you call `SndRecord` or `SndRecordToFile`.

sound resource A resource of resource type 'snd' that can be used to store sound commands and sound data. See also **sound file**.

sound resource header The portion of a sound resource that describes the format of the sound resource.

sound source The origin of a specific channel of sound.

source See **sound source**.

source component The sound component that provides input for a particular component.

source ID A unique 4-byte identifier created by the Apple Mixer to refer to a single chain of sound components linking a sound source to the current sound output device. Defined by the `SoundSource` data type.

speech The process or product of speaking. See also **sound**, **synthesized speech**.

speech amplitude See **speech volume**.

speech attribute A setting defined for a voice or a class of voices that affects the quality of speech generated by the Speech Manager. Speech attributes include **speech pitch**, **speech rate**, **pitch modulation**, **speech volume**.

speech channel The data structure used by the Speech Manager to store settings related to speech generation. All speech must be generated through a speech channel. Defined by the `SpeechChannel` data type.

speech channel control flags Constants that enable special Speech Manager features associated with speech generation.

speech command See **embedded speech command**.

speech-done callback procedure An application-defined procedure that is executed when the Speech Manager completes speaking a buffer of input text.

speech error information record A structure that contains information about which Speech Manager errors occurred while processing a text buffer on a given speech channel. Defined by the `SpeechErrorInfo` data type.

speech extension data record A structure passed to `GetSpeechInfo` or `SetSpeechInfo` to get or set synthesizer information. Defined by the `SpeechXtndData` data type.

speech information selector A variable of type `OSType` that is used to specify the type of information that an application or the Speech Manager is requesting from a speech synthesizer.

Speech Manager The part of the Macintosh system software that provides a standardized method for Macintosh applications to generate synthesized speech.

speech modulation See **pitch modulation**.

speech pitch A fixed-point value on a scale from 0.000 to 100.000 that indicates the average (or baseline) frequency a speech synthesizer should use in generating synthesized speech. A value of 60.000 corresponds to Middle C on a conventional piano keyboard. See also **pitch modulation**.

speech rate A fixed-point value specifying the approximate number of words per minute that a speech synthesizer should use in generating speech.

speech status information record A structure that contains information about the status of a speech channel. Defined by the `SpeechStatusInfo` data type.

speech synthesizer The executable code that is linked to a speech channel and manages all communication between the Speech Manager and the Sound Manager.

speech version information record A structure that contains information about the speech synthesizer currently being used. Defined by the `SpeechVersionInfo` data type.

speech volume A fixed-point value on a scale from 0.000 to 1.000 that indicates the average amplitude a speech synthesizer should use in generating synthesized speech. A value of 0.000 corresponds to the lowest possible volume, and a value of 1.000 corresponds to the highest.

square-wave data Any set of values that represent a sound by its frequency, amplitude, and duration.

stereo sound Sound that simultaneously consists of two or more channels. Also called *polyphonic sound* or *multichannel sound*. Compare **monophonic sound**.

synchronization callback procedure An application-defined procedure that is executed whenever the Speech Manager encounters an embedded synchronization speech command in a buffer of input text.

synchronous sound play A playing of sound by the Sound Manager that prevents other code from executing until the sound is done playing. Compare **asynchronous sound play**.

synthesized speech The product of converting nonaural tokens (such as written or digitally-stored words or phonemes) into speech. See also **Speech Manager**.

synthesizer See **speech synthesizer**.

system alert sound A sound resource stored in the System file that is played whenever an application or other executable code calls the SysBeep procedure.

text The written representation of language.

text-done callback procedure An application-defined procedure that is executed when the Speech Manager has finished processing (although not necessarily speaking) a buffer of input text.

text-to-speech See **synthesized speech**.

tick A unit of time equal to one sixtieth of a second.

timbre The tone of a sound, which can range from clear to buzzing.

two's complement encoding A system for digitally encoding sound that stores the amplitude values as a signed number—silence is represented by a sample with a value of 0. For example, with 8-bit sound samples, two's complement values would range from -128 to 127, with 0 meaning silence. The Audio Interchange File Format (AIFF) used by the Sound Manager stores samples in two's complement form. Compare **offset-binary encoding**.

uncompressed sound data See **decompressed sound data, noncompressed sound data**.

utility component A sound component that performs some modification on sound data and does not communicate directly with any sound output device. See also **sound component, sound output device component**.

version record A structure that contains version information. Defined by the NumVersion data type.

voice (1) The set of parameters that specify a particular quality of synthesized speech. A voice is designed to work with a particular speech synthesizer. (2) A sampled sound played at varying rates to produce a number of different pitches or notes. See also **instrument**.

voice description record A structure that contains information about a voice. Defined by the VoiceDescription data type.

voice file information record A structure that contains information about the file in which a voice is stored and the resource ID of the voice within that file. Defined by the VoiceFileInfo data type.

voice specification record A structure that provides a unique specification that you must use to obtain information about a voice. Defined by the VoiceSpec data type.

volume See **amplitude, speech volume**.

Volumes control panel A subpanel of the Sound control panel that allows the user to select volumes. See also **Alert Sounds control panel, Sound In control panel, Sound Out control panel**.

VOX recording A feature that allows sound recording only when the sound to be recorded exceeds a certain amplitude.

VOX stopping A feature that stops sound recording when the sound falls below a certain amplitude.

wave amplitude The height of a sound wave at an instant of time. Compare **amplitude**.

waveform The shape of a wave (a graph of a wave's amplitude over time).

wavelength The extent of one complete cycle of a wave.

wave table A sequence of wave amplitudes measured at fixed intervals.

wave-table data Any set of values that represent a sound by a wave table.

word callback procedure An application-defined procedure that is executed whenever the Speech Manager is about to speak a word.

Index

A

- A5 register
 - and Sound Manager callback procedures 2-48
 - and Speech Manager callback procedures 4-20 to 4-21, 4-82
- abbreviation entries 4-92
- action flags 5-27
- 'audio' resource type 6-5
- AGC. *See* automatic gain control
- AIFF-C files
 - and AIFF files 1-19
 - creating 1-41
 - defined 1-18 to 1-20
 - file type of 2-87
 - and Finder sound files 1-19
 - format of 2-87 to 2-89
 - playing sounds in 1-19, 1-26
 - recording sounds to 1-31
 - sample frames in 2-89
 - sample of 2-88
 - specifications of 2-82 to 2-89
 - storing sounds in 1-40 to 1-41, 2-9, 3-30
- AIFF files
 - and AIFF-C files 1-19
 - creating 1-41
 - defined 1-18 to 1-20
 - file type of 2-66, 2-87
 - and Finder sound files 1-19
 - format of 2-81 to 2-89
 - playing sounds in 1-19, 1-26
 - recording sounds to 1-31
 - sample frames in 2-89
 - specifications of 2-82, 2-89
 - storing sounds in 1-40 to 1-41, 2-9, 3-30
- alert sounds. *See* system alert sounds
- Alert Sounds control panel 1-16, 1-24, 5-24
- allophones 4-33
- ampCmd command 2-27, 2-96
- amplitude of sounds 2-8, 2-27
- amplitude of speech. *See* speech volume
- Annotation Chunks 2-82
- Apple Mixer. *See* Apple Mixer component
- Apple Mixer component
 - closing 5-34 to 5-35
 - introduced 1-13 to 1-14, 5-6 to 5-7
 - opening 5-33 to 5-34
- Apple Sound Chip (ASC) 1-10, 2-36
- Application Specific Chunks 2-82
- ASC. *See* Apple Sound Chip
- asynchronous sound play 2-46 to 2-56, 2-62
- audio components 6-3 to 6-17
 - See also* sound components
 - creating 6-5 to 6-7
 - data structures for 6-8 to 6-9
 - defined 6-3
 - getting information about 6-14
 - getting mute states 6-11 to 6-12
 - getting volumes 6-10
 - opening resource files 6-8
 - resetting 6-13
 - routines defined by 6-9 to 6-14
 - run-time environment 6-8
 - selectors 6-7 to 6-8
 - setting mute states 6-12 to 6-13
 - setting volumes 6-11
 - subtypes of 6-6
 - types of 6-6
 - writing 6-5 to 6-8
- audio compression
 - determining type of 5-23
 - formats for storage 1-18
 - introduced 1-5, 1-7 to 1-8
 - using MACE routines 2-14 to 2-17, 2-66 to 2-68, 2-142 to 2-145
 - and versions of the Sound Manager 1-14
- audio data
 - See also* sampled-sound data, sounds, square-wave data, wave-table data
 - getting from the source component 5-40
 - mixing 5-6 to 5-7
 - setting the output data type 5-41 to 5-42
 - types of 5-26
- audio decompression. *See* audio expansion
- audio expansion
 - and audio codecs 1-7
 - introduced 1-5
 - using MACE routines 2-14 to 2-17, 2-66 to 2-68, 2-142 to 2-147
 - and versions of the Sound Manager 1-14
- AudioGetInfo function 6-14
- AudioGetMute function 6-11 to 6-12
- AudioGetVolume function 6-10
- AudioInfo data type 6-9
- audio information records 6-9
- Audio Interchange File Format (AIFF). *See* AIFF files
- Audio Interchange File Format for Compression (AIFF-C). *See* AIFF-C files

audio ports 6-3 to 6-5
 AudioRecording Chunks 2-82
 AudioSelection data type 2-53, 2-100
 audio selection records 2-53, 2-100
 AudioSetMute function 6-12 to 6-13
 AudioSetToDefaults function 6-13
 AudioSetVolume function 6-11
 AudioVision 14 Display 6-3 to 6-5, 6-6
 Author Chunks 2-82
 automatic gain control
 defined 3-4
 status of 3-20
 availableCmd command 2-95

B

base frequencies 2-105, 2-107
 baseline pitch. *See* speech pitch
 baseline pitch embedded speech command 4-27
 bilingual speech 1-22, 4-9
 BlockMove procedure, using in doubleback
 procedures 2-72
 bufferCmd command
 described 2-97
 examples of use 2-57, 2-61 to 2-62
 using for compressed sound samples 2-61, 2-62
 buffered expansion 2-15
 buffers. *See* double buffers
 bundle bit 5-11, 6-7
 busy loops, creating 4-14
 byte recording values, converting to milliseconds 3-52

C

callBackCmd command
 described 2-94
 example of use 2-48
 using to synchronize sound with other actions 2-51
 callback procedures
 defined 4-19
 installing 2-48
 and Sound Manager 2-46 to 2-51, 2-152 to 2-153
 and Speech Manager 4-10, 4-19 to 4-23, 4-82 to 4-89
 channels. *See* sound channels, speech channels
 character mode embedded speech command 4-26
 char embedded speech command selector 4-26
 ChunkHeader data type 2-83, 2-113
 chunk header record 2-83
 chunk headers 2-113
 chunks (in AIFF and AIFF-C files)
 Annotation 2-82

Application Specific 2-82
 Audio Recording 2-82
 Author 2-82
 Comments 2-82
 Common 2-82, 2-85 to 2-87, 2-115 to 2-117
 Copyright 2-82
 data types used to describe 2-83
 defined 2-81
 determining size of 2-64
 Extended Common Chunks 2-85, 2-115 to 2-117
 finding 2-62 to 2-66
 Form 2-82, 2-83 to 2-84, 2-113 to 2-114
 Format Version 2-82, 2-84 to 2-85, 2-114
 IDs for 2-98 to 2-99
 Instrument 2-82
 list of types 2-82
 local 2-84, 2-114
 Marker 2-82
 MIDI Data 2-82
 modifying 2-88
 Name 2-82
 order of 2-88
 Sound Accelerator 2-82
 Sound Data 2-82, 2-87, 2-117 to 2-118
 structure of 2-82 to 2-83
 CloseMixerSoundComponent function 5-34 to 5-35
 cmnt embedded speech command selector 4-26
 CmpSoundHeader data type 2-108 to 2-111
 codecs. *See* compression/decompression components
 command delimiters
 changing with an embedded speech command 4-26
 changing with a speech information selector 4-41
 default 4-23, 4-40, 4-54
 defined 4-23, 4-26
 specification of 4-54
 commands. *See* embedded speech commands, sound
 commands
 comment embedded speech command 4-26
 Comments Chunks 2-82
 CommonChunk data type 2-85, 2-115
 Common Chunks 2-82, 2-85 to 2-87, 2-115
 Comp3to1 procedure 2-66, 2-143 to 2-144
 Comp6to1 procedure 2-66, 2-144 to 2-145
 completion routines
 and Sound Input Manager 3-9, 3-54 to 3-55
 and Sound Manager 2-47, 2-52, 2-151 to 2-152
 ComponentDescription data type 5-10, 6-6
 Component Manager
 and audio components 6-3
 and sound components 5-3
 and Speech Manager 1-20, 4-5
 ComponentResource data type 5-9 to 5-11, 6-5 to 6-7
 components. *See* audio components, sound components
 component selectors 5-12 to 5-14, 6-7 to 6-8
 compressed sound header records 2-108 to 2-111

compression. *See* audio compression
 compression/decompression components
 (codecs) 1-7, 1-14 to 1-15, 5-3, 5-6, 5-30
 compression IDs 2-110
 CompressionInfo data type 5-32
 compression information records 5-32
 compression types 2-86, 2-116, 2-117
 computer-generated speech. *See* Speech Manager
 ContainerChunk data type 2-84, 2-114
 container chunks. *See* Form Chunks
 ContinueSpeech function
 described 4-62 to 4-63
 minimizing latency of speech generation with 4-52,
 4-59
 continuing paused speech 4-18, 4-62 to 4-63
 continuous play from disk. *See* play-from-disk routines
 continuous recording
 defined 3-5
 supporting 3-17
 continuous speech 4-51, 4-58
 Control calls 3-5, 3-13 to 3-15
 Copyright Chunks 2-82
 CountVoices function 4-64 to 4-65
 CPU loading values 2-40
 cultural values, associated with sounds 1-24
 current sound input device 1-16
 current sound output device 1-10

D

DAC. *See* digital-to-analog convertor
 data
 See also audio data
 sampled-sound 2-9 to 2-11
 square-wave 2-7 to 2-8
 wave-table 2-8
 data format flags 5-28 to 5-29
 data offset bit in sound commands 2-75
 decompression. *See* audio expansion
 delimiter. *See* command delimiter
 delimiter embedded speech command 4-26
 DelimiterInfo data type 4-54
 delimiter information records 4-54
 Device Manager, and sound input device drivers 3-13
 to 3-17
 'dict' atom type 4-91
 dictionaries. *See* pronunciation dictionaries
 Dictionary Manager 4-37
 'dict' resource type 4-36, 4-89 to 4-93
 digital signal processor (DSP) 1-6, 1-8, 1-10, 5-5
 digital-to-analog converter (DAC) 1-9
 DisposeSpeechChannel function 4-70 to 4-71
 dlim embedded speech command selector 4-26

document annotations, audio 1-24
 documents, and Speech Manager callback
 procedures 4-20
 doubleback procedures
 defined 2-72 to 2-73, 2-153 to 2-154
 limitations of 2-72
 and sound double buffer header records 2-112
 syntax of 2-72
 writing 2-72 to 2-73
 double buffering 1-19
 double buffers 2-68 to 2-73
 managing 2-147 to 2-148
 setting up 2-70 to 2-72
 drop-sample conversion 2-92
 DSP. *See* digital signal processor
 duration of sounds 2-7, 3-6

E

EASC. *See* Enhanced Apple Sound Chip
 Edit menu commands, and alert sounds list 1-16
 embedded speech commands 4-23 to 4-30
 changing delimiters temporarily 4-54
 deemphasizing words 4-32
 defined 4-23
 emphasizing words 4-31
 errors for 4-30
 examples of use 4-30 to 4-32
 format of parameters 4-24
 hexadecimal numbers in 4-24
 list of 4-26 to 4-29
 obtaining errors involving 4-20
 raising the speech pitch 4-32
 specifying relative values 4-24
 synchronization messages in 4-20
 syntax of 4-24 to 4-30
 writing comments in 4-26
 emphasis embedded speech command 4-26
 emph embedded speech command selector 4-26
 emptyCmd command 2-30
 ending prosody
 defined 4-9
 disabling 4-51, 4-58
 Enhanced Apple Sound Chip (EASC) 1-10
 enhanced Sound Manager 1-14
 entry types 4-92
 error callback procedures 4-19 to 4-20, 4-86 to 4-87
 Exp1to3 procedure 2-66, 2-145 to 2-146
 Exp1to6 procedure 2-66, 2-146 to 2-147
 expanding sounds 2-145 to 2-147
 expansion. *See* audio expansion
 ExtCommonChunk data type 2-85, 2-116
 Extended Common Chunks 2-85, 2-115 to 2-117

extended sound header records 2-106 to 2-108
 extended sound headers 2-106 to 2-108
 extensions, installing sound input device drivers
 from 3-13
 ExtSoundHeader data type 2-106

F

file types

'AIFC'. *See* AIFF-C files
 'AIFF'. *See* AIFF files
 'sfil' 1-19

Finder sound files 1-19, 1-23

flushCmd command

described 2-94
 sent by SndDisposeChannel function 2-24, 2-130
 using to flush sound channels 2-29

format 1 'snd' resources 1-18, 2-74, 2-75 to 2-80

format 2 'snd' resources 1-18, 2-74, 2-80 to 2-81

FormatVersionChunk data type 2-84, 2-114

Format Version Chunks 2-82, 2-84 to 2-85, 2-114

format version embedded speech command 4-29

Form Chunks 2-82, 2-83 to 2-84, 2-113 to 2-114

frames of sampled sound 2-10

freqCmd command

calculating proper playback rate for 2-105
 compared to freqDurationCmd 2-41
 described 2-96

freqDurationCmd command

calculating proper playback rate for 2-105
 compared to freqCmd 2-41
 described 2-95
 using to play frequencies 2-41

frequencies

as MIDI note values 2-42, 4-7
 defined 2-7
 distinguished from speech pitches 4-8
 playing 2-41 to 2-46
 playing for indefinite duration 2-41

G

gain 3-20

Gestalt function

and Sound Input Manager 1-27 to 1-28, 3-13, 3-17 to 3-18
 and Sound Manager 1-15, 2-33 to 2-34, 2-35 to 2-37, 2-90 to 2-91
 and Speech Manager 1-31 to 1-32, 4-12 to 4-13

getAmpCmd command 2-28, 2-96

GetDefaultOutputVolume function 2-32, 2-141 to 2-142

GetIndVoice function 4-65 to 4-66

getRateCmd command 2-26, 2-97

GetSoundHeaderOffset function 2-138 to 2-139

GetSoundPreference function 5-36

GetSpeechInfo function 4-77 to 4-78

GetSpeechPitch function 4-7, 4-75 to 4-76

GetSpeechRate function 4-73 to 4-74

GetSysBeepVolume function 2-32, 2-140

GetVoiceDescription function 4-66 to 4-67

GetVoiceInfo function 4-67 to 4-68

getVolumeCmd command 2-31, 2-96

H

hertz 2-16, 4-7

hexadecimal numbers, in embedded speech
 commands 4-24

hissing sound, eliminating during real-time
 expansion 2-17

human interface guidelines. *See* user interface
 guidelines

HyperCard, and format 2 'snd' resources 2-74

I

'ICON' resource type 5-9, 6-6

initialization parameters, for sound channels 2-22 to 2-23, 2-91 to 2-92

inpt embedded speech command selector 4-27

input mode embedded speech command 4-27

Instrument Chunks 2-82

instruments, installing into sound channels 2-10

interleaving of sample points or packets 2-10

interpolation. *See* linear interpolation

interrupt routines, of Sound Input Manager 3-10, 3-55 to 3-56

interrupt time

 Sound Input Manager completion routines at 3-55

 Sound Manager callback procedures at 2-49, 2-153

 Sound Manager completion routines at 2-152

 Sound Manager doubleback procedures at 2-72, 2-154

 sound recording at 3-16

 Speech Manager callback procedures at 4-20, 4-82

IODone function, and sound input device drivers 3-16

J

`JIODone` global jump vector, and sound input device drivers 3-16

K

`kPreflightThenPause` flag bit 4-52, 4-59
`kUseOptionalOutputDevice` constant 2-128

L

`LeftOverBlock` data type 2-119
 leftover blocks 2-119
 lexical stress symbols 4-34
 linear interpolation 2-24, 2-92
`loadCmd` command 2-95
 local chunks 2-84
 localization, sounds and 1-24
 looping sounds 2-45 to 2-46

M

MACE 2-14 to 2-17, 2-66
 testing for version 2-133 to 2-134
`MACEVersion` function 2-35, 2-133 to 2-134
 Macintosh Audio Compression and Expansion (MACE). *See* MACE
`MakeVoiceSpec` function 4-64
 Marker Chunks 2-82
 menu bar, blinking of 2-41
 MIDI (Musical Instrument Digital Interface) 1-6
 MIDI Data Chunks 2-82
 MIDI Manager 1-6
 MIDI note values 4-7
 converting to hertz values 2-43
 defined 2-7
 introduced 2-42
 table of 2-43
 millisecond recording values, converting to bytes 3-51
 to 3-52
 modifiers 2-149 to 2-151
 modulation of speech. *See* pitch modulation
 'movr' creator type 1-19
 multichannel sound. *See* stereo sound
 multilingual speech 1-22, 4-9
 Musical Instrument Digital Interface. *See* MIDI

N

Name Chunks 2-82
`NewSpeechChannel` function 4-69 to 4-70
`nubr` embedded speech command selector 4-27
 notes. *See* frequencies, MIDI note values
 NuBus expansion cards, for audio hardware
 enhancement 1-10
`nullCmd` command 2-94
 number mode embedded speech command 4-27
`NumVersion` data type 2-118

O

offset-binary encoding 2-11
`OpenMixerSoundComponent` function 5-7, 5-33 to 5-34
 output rate 2-16

P

packets 2-11, 2-67
 pad bytes, in AIFF and AIFF-C files 2-87
`param2` field 2-75
`pauseCmd` command 2-29, 2-94
`PauseSpeechAt` function 4-61 to 4-62
 pausing speech 4-18 to 4-19, 4-61 to 4-62
`pbas` embedded speech command selector 4-27
 phoneme callback procedures 4-87 to 4-88
`PhonemeDescriptor` data type 4-53
 phoneme descriptor records 4-53
`PhonemeInfo` data type 4-52
 phoneme information records 4-52 to 4-53
 phonemes
 conversion from text 4-32, 4-79 to 4-80
 getting information about 4-34
 lengthening duration of 4-35
 shortening duration of 4-35
 symbols for 4-33 to 4-34
 phonemic representation of speech 4-32 to 4-34
 pitch
 changing 2-10
 defined 2-7
 pitch modulation
 allowable range 4-8
 defined 4-8
 valid ranges of 4-9
 pitch modulation embedded speech command 4-28
 play-from-disk routines
 introduced 1-19
 testing for availability of 2-35 to 2-37

playing frequencies 2-41 to 2-46
 choosing a data type 2-41
 of indefinite duration 2-41

playing sampled sounds
 at arbitrary frequencies 2-43
 with `bufferCmd` 2-61 to 2-62

playing selections of sound 2-53

playthrough feature 3-5

`pmode` embedded speech command selector 4-28

polyphonic sound. *See* stereo sound

preconfiguring sound channels 2-131, 2-132

preferences
 restoring 5-36
 storing 5-35 to 5-36

pronunciation dictionaries 4-36 to 4-39, 4-89 to 4-93
 creating temporary dictionaries 4-37
 defined 4-36
 and Dictionary Manager 4-37
 entries 4-37 to 4-39
 entry codes 4-92
 example of 4-38
 field type codes 4-93
 format of 4-89 to 4-93
 format version 4-91
 installing 4-37, 4-80 to 4-82
 order of entries 4-38
 resource headers 4-39, 4-91
 resources 4-36 to 4-39, 4-89 to 4-93
 storing in a file's data fork 4-90
 uses of 4-37
 using alternative storage formats 4-90

pronunciation entries 4-92

prosodic control symbols 4-34 to 4-36

prosody 4-9, 4-34 to 4-36

punctuation marks, effect on prosody 4-35 to 4-36

Q

`quietCmd` command 2-94
 sent by `SndDisposeChannel` function 2-24, 2-130
 using with `freqDurationCmd` 2-41

R

rate. *See* sample rate, speech rate

`rateCmd` command 2-26, 2-97

rate embedded speech command selector 4-28

Read calls 3-5, 3-13 to 3-16

real-time expansion 2-15, 2-17

recording sounds 3-6 to 3-9
 described 1-28 to 1-31, 1-38 to 1-41, 3-28 to 3-30

 directly from device 3-6 to 3-9, 3-33 to 3-38
 effect of interruption on sound input device
 driver 3-15
 in stereo 3-16
 introduced 1-15 to 1-17
 specifying duration 3-6
 without standard interface 3-4

`reInitCmd` command 2-23, 2-94

`ReleaseResource` function, and sound
 resources 2-25

request parameter blocks, passed to sound input
 device drivers 3-13

reset embedded speech command 4-28

`ResourceSpec` data type 5-9

resource types
 'audio' 6-5
 'dict' 4-36, 4-89 to 4-93
 'ICON' 5-9, 6-6
 'sift' 5-9
 'snd '
 See 'snd ' resource type, sound resources
 'STR ' 5-9, 6-6
 'thng' 5-8 to 5-11, 6-5 to 6-7
 'ttsd' 4-91
 'vers' 2-35, 2-118

`restCmd` command 2-96

`resumeCmd` command 2-29, 2-94

resuming speech 4-62 to 4-63

`rset` embedded speech command selector 4-28

S

sample. *See* sample point

sampled-sound data 2-9 to 2-11
 computing length of 2-46
 format of 2-10 to 2-11
 modifying during recording 3-55 to 3-56
 obtaining data without header information 3-4
 packet sizes for compressed data 2-67
 setting up header information for 3-4

sampled sounds
 See also sounds
 changing frequency of 2-26
 compressing. *See* compressing sounds
 disk space requirements for 2-14
 expanding. *See* expanding sounds
 input buffer size 3-6
 installing as voices in channels 2-44
 introduced 2-9 to 2-11
 multiple channels of 1-13 to 1-14, 2-14
 number of commands used in 2-21
 output buffer size required 2-66 to 2-67
 pausing 2-27

- playing
 - asynchronously 2-46, 2-50, 2-52 to 2-53
 - continuously 2-45 to 2-46
 - play from disk 1-18 to 1-20, 1-26 to 1-27, 2-52 to 2-53
 - selections of 2-53
 - using low-level routines 2-61 to 2-62
- recording 1-15 to 1-17
- storing 1-18 to 1-20, 2-9, 3-44 to 3-46
- synchronizing 2-31
- sample frames 2-10
- sample points 2-10 to 2-11
- sample rates 2-16, 2-97, 2-105, 2-107, 2-109
- sample routines
 - MyAdjustSpeechAttributes 4-16 to 4-17
 - MyAudioDispatch 6-7
 - MyCallback 2-48
 - MyCanPlayMultiChannels 2-36
 - MyChannelIsPaused 2-39
 - MyCheckSndChan 2-49
 - MyCleanUpTrackedChan 2-55 to 2-56
 - MyCompressBy3 2-67
 - MyCreateSndChannel 2-20
 - MyDBSndPlay 2-70 to 2-72
 - MyDisposeSndChannel 2-25
 - MyDoLoopEntireSound 2-45
 - MyDoubleBackProc 2-73
 - MyFindChunk 2-63 to 2-64
 - MyGetChunkData 2-65
 - MyGetComponentRoutine 5-14 to 5-16
 - MyGetDeviceName 3-12
 - MyGetDeviceSettings 3-12
 - MyGetNumChannels 2-40
 - MyGetSoundHeader 2-60
 - MyGetSoundHeaderOffset 2-58 to 2-59
 - MyHalveFreq 2-26
 - MyHasEnhancedSoundManager 2-35
 - MyHasPlayFromDisk 2-37
 - MyHasSoundInput 1-27
 - MyHasSpeech 1-32
 - MyHasStereo 2-34
 - MyInstallBoysVoice 4-15
 - MyInstallCallback 2-48
 - MyInstallSampledVoice 2-44
 - MyInstallWordCallback 4-21 to 4-22
 - MyLowLevelSampledSndPlay 2-62
 - MyPauseAndContinueSpeech 4-18 to 4-19
 - MyPlayFrequencyOnce 2-42
 - MyPlaySampledSound 2-57
 - MyPlaySndResource 1-26
 - MyPlaySoundFile 1-27
 - MyRecordSnd 3-7 to 3-8
 - MyRecordSndResource 1-29 to 1-30
 - MyRecordSoundFile 1-31
 - MyRecordThruDialog 1-28
 - MySetAmplitude 2-27
 - MySetTrackChanDispose 2-55
 - MySetupCallbacks 4-21
 - MySetVolume 2-32
 - MySoundCompletionRoutine 2-52
 - MySoundComponentGetInfo 5-19 to 5-21
 - MySoundComponentInitOutputDevice 5-17
 - MySpeakStringResource 1-32
 - MySpeakStringResourceSync 1-33
 - MySpeechMgrPresent 4-12 to 4-13
 - MyStartPlaying 2-50
 - MyStopPlaying 2-50
 - MyStopSpeech 1-34
 - MySurfDispatch 5-12 to 5-14
 - MySyncChan 2-30
 - MyUseDictionary 4-37 to 4-38
 - MyUseSpeechChannel 4-13 to 4-14
 - MyWordCallback 4-22
- Scrapbook, representation of sounds in 1-23
- SCStatus data type 2-38, 2-101
- SetDefaultOutputVolume function 2-32, 2-142
- SetSoundPreference function 5-35 to 5-36
- SetSpeechInfo function 4-78 to 4-79
- SetSpeechPitch function 4-76
- SetSpeechRate function 4-74 to 4-75
- SetSysBeepVolume function 2-32, 2-140 to 2-141
- SetupAIFFHeader function 3-46 to 3-48
- SetupSndHeader function 3-9, 3-44 to 3-46
- 'sfil' file type 1-19
- sifters. *See* sound components
- 'sift' resource type 5-9
- silence embedded speech command 4-28
- Simple Beep 1-25, 2-76 to 2-77
- slnc embedded speech command selector 4-28
- SMStatus data type 2-39, 2-102
- SndAddModifier function 2-150 to 2-151, 5-4
- SndChannel data type 2-13, 2-103 to 2-104
- SndChannelStatus function 2-37, 2-46, 2-135 to 2-136
- SndCommand data type 2-12, 2-99 to 2-100
- SndControl function 2-134 to 2-135
- SndDisposeChannel function 2-129 to 2-130
 - introduced 2-24
 - and quietCmd 2-29
- SndDoCommand function 2-130 to 2-131
 - introduced 2-12
 - and other low-level routines 2-17
- SndDoImmediate function 2-131 to 2-132
 - introduced 2-12
 - issuing flushCmd with 2-29
 - issuing quietCmd with 2-28
 - and other low-level routines 2-17
- SndDoubleBuffer data type 2-69, 2-112
- SndDoubleBufferHeader2 data type 2-111
- SndDoubleBufferHeader data type 2-69, 2-111

- SndGetSysBeepState procedure 2-137
- SndManagerStatus function
 - described 2-136 to 2-137
 - example of use 2-40
 - introduced 2-39
- SndNewChannel function
 - described 2-127 to 2-129
 - examples of use 2-20 to 2-22
 - introduced 2-14
 - specifying an initialization parameter 2-22
- SndPauseFilePlay function 2-53, 2-125 to 2-126
- SndPlayDoubleBuffer function 2-68, 2-147 to 2-148
- SndPlay function
 - described 1-35 to 1-36, 2-121 to 2-122
 - examples of use 1-25, 3-9
 - playing compressed sound resources with 2-15, 2-66
 - using to play Finder sound files 1-19
- SndRecord function
 - described 1-39 to 1-40, 3-28 to 3-29
 - example use of 1-28 to 1-29
 - introduced 1-17
- SndRecordToFile function
 - described 1-40 to 1-41, 3-30
 - introduced 1-17
- 'snd' resource type
 - See also* sound resources
 - alternatives to 2-9
 - format 1 1-18, 2-74, 2-75 to 2-80, 3-45
 - format 2 1-18, 2-74, 2-80 to 2-81
 - introduced 1-16, 1-17 to 1-18
 - structure of 2-154 to 2-156
- SndSetSysBeepState function 2-137 to 2-138
- SndSoundManagerVersion function 2-35, 2-133
- SndStartFilePlay function
 - default buffer allocation 1-27
 - described 1-36 to 1-38, 2-123 to 2-125
 - using to play sound files 1-19, 1-27
- SndStopFilePlay function 2-53, 2-126 to 2-127
- Sony sound chip 1-9
- Sound Accelerator Chunks 2-82
- sound channel records 2-25, 2-103 to 2-104
- sound channels
 - allocating 2-20 to 2-22, 2-127
 - bypassing 1-12, 2-12
 - determining number allocated 2-40
 - executing callback procedures 2-94
 - flushing 2-28 to 2-29, 2-94
 - getting information about all channels 2-39 to 2-40, 2-136 to 2-137
 - getting information about a single channel 2-37 to 2-39, 2-135 to 2-136
 - initializing 2-22 to 2-24
 - installing voices into 2-43 to 2-45
 - introduced 1-11, 2-13 to 2-14
 - linking modifiers to 2-150
 - multiple 1-13 to 1-14, 2-14, 2-53 to 2-56
 - pausing 2-29 to 2-30, 2-94
 - playing notes in 2-95, 2-96
 - preconfiguring 2-97, 2-131, 2-132
 - reducing memory requirements of 2-21
 - reinitializing 2-23, 2-94
 - releasing 2-24 to 2-25, 2-129 to 2-130
 - restarting 2-29 to 2-30, 2-94
 - resting 2-96
 - sample rate of 2-97
 - sending commands 2-130 to 2-132
 - setting timbre of 2-96
 - setting volume of 2-96
 - specifying length of 2-21
 - stopping 2-28 to 2-29, 2-94, 2-125 to 2-127
 - synchronizing 2-30 to 2-31, 2-95
 - testing for multichannel sound capability 2-35 to 2-37
 - using low-level routines 2-62
- sound channel status records 2-38, 2-101 to 2-102
- soundCmd command 2-44, 2-97
- sound command records 2-99 to 2-100
- sound commands
 - data offset bit 2-75
 - in sound resources 2-155
 - introduced 1-11, 2-11 to 2-13
 - issuing 2-12, 2-130
 - list of constants for 2-12 to 2-13, 2-93 to 2-97
 - number per channel 2-21
 - referencing sampled-sound data 2-60
 - structure of 2-12
- SoundComponentAddSource function 5-42 to 5-43
- sound component chains 1-8 to 1-9, 5-4 to 5-5
- SoundComponentData data type 5-8, 5-29 to 5-30
- sound component data records 5-8, 5-29 to 5-30
- sound component features flags 5-26 to 5-27
- SoundComponentGetInfo function 5-18 to 5-21, 5-22 to 5-26, 5-44 to 5-45
- SoundComponentGetSourceData function 5-40
- SoundComponentGetSource function 5-39 to 5-40
- sound component information selectors 5-18, 5-22 to 5-26
- SoundComponentInitOutputDevice function 5-37 to 5-38
- SoundComponentPauseSource function 5-48
- SoundComponentPlaySourceBuffer function 5-27, 5-49
- SoundComponentRemoveSource function 5-43 to 5-44
- sound components 5-3 to 5-57
 - See also* audio components
 - constants for 5-22 to 5-29
 - creating 5-8 to 5-11
 - data structures for 5-29 to 5-32, ?? to 5-32
 - defined 1-7 to 1-9, 5-4

- getting information about 5-18 to 5-21, 5-22 to 5-26, 5-31, 5-44 to 5-45
- information selectors 5-18, 5-22 to 5-26
- opening 5-16 to 5-18
- opening resource files 5-16
- registering 5-16 to 5-17
- restoring preferences 5-36
- routines defined by 5-36 to 5-49
- run-time environment 5-16
- setting information about 5-18, 5-22 to 5-26, 5-31, 5-45 to 5-46
- storing preferences 5-35 to 5-36
- subtypes of 5-10
- types of 5-10
- writing 5-8 to 5-21
- SoundComponentSetInfo function 5-23 to 5-26, 5-45 to 5-46
- SoundComponentSetOutput function 5-41 to 5-42
- SoundComponentSetSource function 5-38 to 5-39
- SoundComponentStartSource function 5-46 to 5-47
- SoundComponentStopSource function 5-47 to 5-48
- Sound control panels
 - effect on loudness of sounds 2-27
 - extensions to 1-10
 - and SysBeep procedure 1-24, 1-35, 2-121
- sound data. *See* sampled-sound data, sounds, square-wave data, wave-table data
- SoundDataChunk data type 2-87, 2-117
- Sound Data Chunks 2-82, 2-87, 2-117 to 2-118
- sound double buffer header records 2-69, 2-111 to 2-112
- sound double buffer records 2-69, 2-112 to 2-113
- Sound Driver 2-7
- sound files
 - See also* AIFF files, AIFF-C files
 - advantages over sound resources 1-18
 - asynchronous playing 2-52
 - and Finder sound files 1-19
 - getting information about 2-62 to 2-66
 - introduced 1-18 to 1-20
 - pausing play 2-53
 - playing 1-26 to 1-27, 1-36 to 1-38, 2-123 to 2-125
 - playing several simultaneously 1-20
 - reading 2-87 to 2-89
 - recording 1-31, 1-40 to 1-41, 3-30
 - setting up 3-46 to 3-48
 - stopping play 2-53
 - structure of 2-81 to 2-89
 - translating between operating systems 1-18
 - writing 2-87 to 2-89
- SoundHeader data type 2-104
- sound header records 2-104 to 2-105
- sound headers
 - accessing fields of 2-61
 - compressed 2-108 to 2-111
 - defined 2-10
 - extended 2-106 to 2-108
 - formats of 3-45
 - getting pointers to 2-57 to 2-61, 2-138 to 2-139
 - setting up 3-4, 3-44 to 3-46
 - standard 2-104 to 2-105
 - types of 2-10, 2-62
- Sound In control panel 1-15 to 1-16
 - selecting sound input device from list 3-49
- SoundInfoList data type 5-31 to 5-32
- sound information lists 5-31 to 5-32
- sound input completion routines
 - defined 3-9, 3-54 to 3-55
 - setting 3-6, 3-27
- sound input device drivers 3-13 to 3-17
 - and continuous recording 3-17
 - getting information about 3-4, 3-41 to 3-44
 - installing and initializing 3-13
 - and Memory Manager errors 3-15
 - registering with Sound Input Manager 3-13, 3-48, 3-50
 - routines for 3-5
 - and stereo recording 3-16
 - storage for 3-13
 - types of requests drivers can handle 3-13
- sound input device information selectors
 - introduced 3-5
 - list of 3-18 to 3-25
 - required selectors 3-15
 - reserved by Apple 3-15
 - responding to requests for more than 18 bytes of data 3-13
- sound input devices
 - changing settings of 3-10 to 3-12, 3-41 to 3-44
 - closing 3-4, 3-32 to 3-33
 - connection state 3-22
 - current 1-16
 - displaying Options dialog box for 3-23
 - generating list of 3-49 to 3-50
 - getting information about 3-4, 3-10 to 3-12, 3-18 to 3-25
 - opening 3-4, 3-9, 3-31 to 3-32
 - recording directly from 3-6 to 3-9, 3-33 to 3-38
 - registering 3-48 to 3-51
- sound input interrupt routines
 - defined 3-10, 3-55 to 3-56
 - executing from sound input device driver 3-16
 - setting 3-6, 3-27
- Sound Input Manager 3-3 to 3-67
 - application-defined routines 3-53 to 3-56
 - completion routines 3-9, 3-54 to 3-55
 - constants in 3-17 to 3-25
 - data structures in 3-26 to 3-27
 - interrupt routines 3-10, 3-55 to 3-56
 - introduced 1-5, 1-15 to 1-17
 - recording features 3-5

- routines in 3-27 to 3-53
 - testing for availability 3-13, 3-17 to 3-18
 - testing for version 3-53
- sound input parameter blocks
 - accessing from a sound input device driver 3-15
 - format of 3-6, 3-26 to 3-27
 - setting up 3-7 to 3-8
 - uses for 3-26
- Sound Manager 2-5 to 2-189
 - application-defined routines 2-151 to 2-154
 - and audio components 6-3 to 6-5
 - callback procedures 2-46 to 2-51, 2-152 to 2-153
 - completion routines 2-47, 2-151 to 2-152
 - constants in 2-89 to 2-99
 - data structures in 2-99 to 2-119
 - doubleback procedures 2-153 to 2-154
 - enhanced 1-14 to 1-15
 - features new in version 3.0 1-14
 - improving efficiency 2-61
 - introduced 1-5, 1-9 to 1-15
 - obtaining information 2-32 to 2-41
 - relation to audio hardware 1-11
 - routines in 2-119 to 2-151
 - and sound components 5-4 to 5-8
 - sound component utility routines 5-33 to 5-36
 - testing for features 2-33 to 2-34, 2-35 to 2-37, 2-90 to 2-91
 - testing for version 2-34 to 2-35, 2-133
 - turning off sound output 2-27
- Sound Manager status records 2-39, 2-102
- Sound Out control panel 1-10
- sound output device components 5-5, 5-46 to 5-49
- sound output devices
 - initializing 5-17 to 5-18, 5-37 to 5-38
- sound output rate 2-16
- SoundParamBlock data type 5-30 to 5-31
- sound parameter blocks 5-30 to 5-31
- sound queues
 - bypassing 1-12, 2-11
 - specifying size 2-21
- sound recording dialog box
 - customizing behavior of 1-29, 3-4
 - filtering events in 1-29
 - introduced 1-17
 - recording sounds with 1-28 to 1-31
- sound-recording equipment
 - checking for 1-27 to 1-28
 - types supported 1-27
- sound resource headers 2-155 to 2-156
- sound resources
 - See also* 'snd' resource type
 - alternatives to 2-9
 - containing sampled-sound data 2-77
 - creating manually 2-155
 - format of 2-74 to 2-80, 2-154 to 2-155
 - freeing memory after playing 2-25
 - getting information about 2-57 to 2-61
 - introduced 1-17 to 1-18
 - number of commands used in 2-21
 - playing
 - described 1-25 to 1-26, 1-35 to 1-38, 2-121 to 2-123, 2-123 to 2-125
 - example of use 2-57
 - ignoring parts of 2-61
 - large resources with a small buffer 2-61
 - recording 1-28 to 1-30, 1-39 to 1-40, 3-28 to 3-29
 - reserved IDs 2-75, 2-154
- sounds
 - See also* sampled sounds
 - amplitude 2-8, 2-27 to 2-28
 - changing output channel for 2-24
 - computed 2-9
 - determinants of loudness 2-27
 - digitally recorded 2-9
 - duration 2-7
 - frequency 2-7
 - installing into System file 1-19
 - looping 2-45 to 2-46
 - manipulating while playing 2-25 to 2-28
 - mixing 5-6 to 5-7
 - pitch 2-7
 - recording. *See* recording sounds
 - sample rate. *See* sample rates
 - synchronizing with other actions 2-51
 - timbre 2-8
 - volume 2-8
- sound sources
 - adding 5-42 to 5-43
 - pausing 5-48
 - removing 5-43 to 5-44
 - starting 5-46 to 5-47
 - stopping 5-47 to 5-48
- sound storage formats 2-74 to 2-89
- source components 5-5, 5-38 to 5-40
- source IDs 5-7
- sources. *See* sound sources
- SPBBytesToMilliseconds function 3-52
- SPBCloseDevice function 3-4, 3-32 to 3-33
- SPB data type 3-6, 3-26
- SPBGetDeviceInfo function
 - described 3-42
 - example of use 3-8
 - information selectors, list of 3-20 to 3-25
 - introduced 3-5
 - using in interrupt routines 3-10
- SPBGetIndexedDevice function 3-31, 3-49 to 3-50
- SPBGetRecordingStatus function 3-40 to 3-41
- SPBMillisecondsToBytes function 3-51 to 3-52
- SPBOpenDevice function 3-31 to 3-32
 - example of use 3-8

- introduced 3-4
- and sound input parameter blocks 3-26
- SPBPauseRecording function 3-4, 3-38
- SPBRecord function 3-33 to 3-35
 - example of use 3-8
 - introduced 3-4
 - and sound input completion routines 3-9
- SPBRecordToFile function 3-4, 3-35 to 3-38
- SPBResumeRecording function 3-4, 3-39
- SPBSetDeviceInfo function 3-5, 3-10, 3-43 to 3-44
- SPBSignInDevice function 3-5, 3-48 to 3-49
- SPBSignOutDevice function 3-5, 3-50 to 3-51
- SPBStopRecording function
 - described 3-39 to 3-40
 - introduced 3-4
 - and sound input completion routines 3-9, 3-27
 - and sound input parameter blocks 3-27
- SPBVersion function 3-53
- SpeakBuffer function 4-57 to 4-59
- SpeakString function 1-33 to 1-34, 1-42 to 1-43, 4-55 to 4-56
- SpeakText function 4-56 to 4-57
- speech
 - bilingual 1-22, 4-9
 - continuous 4-19, 4-51, 4-58
 - minimizing latency period of 4-52, 4-59
 - multilingual 1-22, 4-9
 - pausing 4-18 to 4-19, 4-61 to 4-62
 - phonemic representation of 4-32 to 4-34, 4-37
 - resuming 4-19, 4-62 to 4-63
 - starting 4-18 to 4-19, 4-56 to 4-59
 - stopping 1-33 to 1-34, 1-42, 4-18 to 4-19, 4-56, 4-59 to 4-61
 - synchronous generation 1-33
 - tonal qualities of 1-21, 4-5
- speech amplitude. *See* speech volume
- speech attributes
 - changing the rate and pitch 4-16 to 4-17, 4-74 to 4-75, 4-76
 - defined 4-6 to 4-9
- SpeechBusy function 1-43, 4-72
- SpeechBusySystemWide function 4-72 to 4-73
- speech channel control flags
 - changing during speech 4-83
 - described 4-51 to 4-52, 4-58 to 4-59
- speech channels
 - changing settings of 4-78 to 4-79
 - control flags. *See* speech channel control flags
 - creating 4-13 to 4-14, 4-69 to 4-70
 - defined 1-22, 4-9
 - disposing of 4-13 to 4-14, 4-70 to 4-71
 - getting information about 4-77 to 4-78
 - limitations on 1-22, 4-10
 - multiple 1-22, 4-10
 - number synthesizing speech 4-72
 - preventing interruption of speech 4-51, 4-58
 - reference constant values 4-20
 - setting up callback procedures 4-21
 - speaking text with 4-13 to 4-14
 - and suspend events 4-70
 - speech commands. *See* embedded speech commands
 - speech components 1-20, 4-5
 - speech-done callback procedures 4-19, 4-84 to 4-85
 - SpeechErrorInfo data type 4-49
 - speech error information records 4-49 to 4-50
 - speech extension data records 4-53 to 4-54
 - speech generation process 1-20 to 1-22, 4-4
 - speech information selectors 4-39 to 4-45
 - speech input mode 4-33
 - Speech Manager 4-3 to 4-110
 - application-defined routines 4-82 to 4-89
 - callback procedures 4-10, 4-19 to 4-23
 - common uses of 4-3
 - and Component Manager 1-20, 4-5
 - constants in 4-39 to 4-45
 - data structures in 4-45 to 4-54
 - future improvements in 1-21, 4-5
 - introduced 1-5, 1-20 to 1-22
 - memory requirements of 1-22, 4-32
 - position in speech generation process 1-20, 4-5
 - resources 4-89 to 4-93
 - result code of routines 4-55
 - routines in 4-54 to 4-82
 - and Sound Manager 4-3
 - testing for availability 1-31 to 1-32, 4-12 to 4-13
 - testing for version 4-71 to 4-72
 - and voices 4-5 to 4-6, 4-14 to 4-16, 4-63 to 4-68
 - SpeechManagerVersion function 4-71 to 4-72
 - speech modulation. *See* pitch modulation
 - speech pitch
 - causing rise or fall in 4-35
 - changing 4-16 to 4-17, 4-76
 - defined 4-7
 - distinguished from frequency 4-8
 - getting 4-75 to 4-76
 - and Hertz values 4-7
 - range used by human voices 4-7
 - speech rate
 - changing 4-16 to 4-17, 4-74 to 4-75
 - defined 4-6, 4-43
 - getting 4-73 to 4-74
 - speech rate embedded speech command 4-28
 - SpeechStatusInfo data type 4-49
 - speech status information records 4-48 to 4-49
 - speech synthesizer resources 4-89
 - speech synthesizers
 - defined 1-20, 4-4
 - getting information about phonemes supported 4-34
 - internal dictionaries 4-91
 - memory requirements of 4-10

- minimizing latency period of 4-52, 4-59
- SpeechVersionInfo data type 4-50
- speech version information records 4-50 to 4-52
- speech volume 4-45
 - defined 4-9
- speech volume embedded speech command 4-29
- SpeechXtndData data type 4-53
- square-wave data 2-7 to 2-8
- standard sound headers 2-104 to 2-105
- StateBlock data type 2-119
- state blocks 2-119
- state buffers, used by MACE routines 2-67
- Status calls 3-5, 3-13 to 3-15
- stereo sounds
 - defined 2-106
 - expanding 2-15
 - recording 3-16
 - storage format of 2-10
- stopping speech 4-59 to 4-61
- StopSpeechAt function 4-60 to 4-61
- StopSpeech function 4-59 to 4-60
- strings, converting into speech. *See* speech generation
- 'STR' resource type 5-9, 6-6
- suspend events, disposing of speech channels in response to 4-70
- syllable break symbols 4-34
- syncCmd command 2-30 to 2-31, 2-94
- sync embedded speech command selector 4-29
- synchronization callback procedures 4-19 to 4-20, 4-85 to 4-86
- synchronization embedded speech command 4-29
- synchronization messages 4-20
- synchronizing sound channels 2-30 to 2-31, 2-95
- synchronizing sounds with other actions 2-51
- synthesizers. *See* speech synthesizers
- synthesizer-specific embedded speech command 4-29
- SysBeep procedure
 - described 1-35, 2-120 to 2-121
 - example use of 1-24
 - using as notification 1-25
- system alert sounds
 - determining status of 2-40 to 2-41, 2-137
 - disabling 2-40 to 2-41
 - editing list of 1-16
 - enabling 2-40 to 2-41
 - installing new sound 1-19
 - producing 1-24 to 1-25, 1-35, 2-120 to 2-121
 - setting status of 2-137 to 2-138

T

- text
 - conversion into phonemes 4-32 to 4-33, 4-79 to 4-80

- specifying allophones in 4-33
- text-done callback procedures 4-19, 4-82 to 4-84
- text processing modes 4-42
- TextToPhonemes function 4-33, 4-79 to 4-80
- text-to-speech. *See* Speech Manager
- 'thng' resource type 5-8 to 5-11, 6-5 to 6-7
- ticks, used to time system alert sounds 1-25
- timbre 2-8, 2-28, 2-96
- timbreCmd command 2-28, 2-96
- Time Manager, and synchronizing sounds 2-31
- totalLoadCmd command 2-95
- 'ttsd' resource type 4-91
- two's complement encoding 2-11

U

- uncompressed sound data. *See* decompressed sound data, noncompressed sound data
- unit table, installing sound input device driver into 3-13
- unsigned fixed-point numbers, multiplying and dividing 2-149
- UnsignedFixMulDiv function 2-149
- UseDictionary function 4-38, 4-81 to 4-82
- user interface guidelines, for sound 1-23 to 1-24
- utility components 5-6

V

- vers embedded speech command selector 4-29
- versionCmd command 2-95
- version embedded speech command 4-29
- version records 2-118
- version resources 2-35, 2-118
- 'vers' resource type 2-35, 2-118
- VoiceDescription data type 4-47
- voice description records 4-16, 4-47 to 4-48
- VoiceFileInfo data type 4-48
- voice file information records 4-48
- voice resources 4-89
- voices
 - characteristics of 4-6 to 4-9
 - counting 4-14, 4-64 to 4-65
 - defined 4-5 to 4-6
 - getting a description of 4-14, 4-66 to 4-67
 - identifying 4-14, 4-65 to 4-66
 - installing into sound channels 2-10, 2-43 to 2-45
 - synthesized 1-22
 - updating information about 4-66
- VoiceSpec data type 4-46
- voice specification records 4-46 to 4-47, 4-64

`volm` embedded speech command selector 4-29
volume
 See also amplitude, speech volume
 defined 2-8
`volumeCmd` command 2-31, 2-96
volume levels, controlling 2-31 to 2-32, 2-96 to 2-97,
 2-139 to 2-142
Volumes control panel 6-4 to 6-5
VOX recording 3-5, 3-25
VOX stopping 3-5, 3-25

W

`waitCmd` command
 described 2-94
 example of use 2-29
`waveTableCmd` command 2-44, 2-97
wave-table data 2-8
wave tables 2-8, 2-44
word callback procedures
 described 4-88 to 4-89
 example of 4-22
word prominence symbols 4-34

X, Y, Z

`xtnd` embedded speech command selector 4-29

This Apple manual was written, edited, and composed on a desktop publishing system using Apple Macintosh computers and FrameMaker software. Proof pages were created on an Apple LaserWriter II_{NTX} printer. Final page negatives were output directly from text files on an Optrotech SPrint 220 imagesetter. Line art was created using Adobe Illustrator™ and Adobe Photoshop™. PostScript™, the page-description language for the LaserWriter, was developed by Adobe Systems Incorporated.

Text type is Palatino® and display type is Helvetica®. Bullets are ITC Zapf Dingbats®. Some elements, such as program listings, are set in Apple Courier.

LEAD WRITER

Tim Monroe

WRITERS

Tim Monroe, Michael Abramowicz,
Lori E. Kaplan

DEVELOPMENTAL EDITORS

Sanborn Hodgkins, Wendy Krafft,
Antonio Padial, Laurel Rezeau,
Beverly Zegarski

ILLUSTRATORS

Shawn Morningstar, Barbara Carey

ART DIRECTOR

Bruce Lee

PRODUCTION EDITOR

Gerri Gray

PROJECT MANAGER

Patricia Eastman

COVER DESIGNER

Barbara Smyth

Special thanks to Mark Cecys, Kip Olson,
Jim Reekes, and Tim Schaaff.

Acknowledgments to Bob Aron,
Ray Chiang, Ron Dumont,
Sharon Everson, Eric “Braz” Ford,
Jim Nitchals, Guillermo Ortiz,
Kim Silverman, George Towner,
Randy Zeitman, and the entire
Inside Macintosh team.