

Tech Info Library

HyperCard 2.1: String Too Long Error (10/92)

Article Created: 28 June 1991 Article Reviewed/Updated: 30 October 1992
TOPIC
The "String Too Long" message may appear in the Apple Event Primer Stack that shipped with HyperCard 2.1. This article tells how to resolve the problem.
DISCUSSION
1) Be sure you're running HyperCard 2.1 at UserLevel 5 and System 7.0 or greater.
2) Open stack Apple Event Primer.
3) When the "String too long" error appears, click the Script button.
4) The insertion point will be in front of the word "answer" of the errMessage handler (shown below).
on errMessage theOffender if theOffender is not empty then answer¬ "This stack uses features available only in HyperCard" && ¬ "2.1 or greater running with System Software version 7 or" && ¬ "greater. To take advantage of these features, you will need to" &&¬ "upgrade your" && theOffender & ". For now, you will only be" &&¬ "able read about these features." exit to HyperCard end if
end errMessage
5) Shorten the handler by deleting the characters
& ". For now, you will only be" && "able read about these features."
from the sixth and seventh lines of the handler.
6) Close the script editor and save your changes.

This article is adapted from the Claris Tech Info database.

Support Information Services Copyright 1994, Apple Computer, Inc.

Keywords: <None>

This information is from the Apple Technical Information Library.

19960215 11:05:19.00

Tech Info Library Article Number: 14553